Biltmore Lectures

G. S. Hamlin jr.

THE LIBRARY
OF
THE UNIVERSITY
OF CALIFORNIA
LOS ANGELES

FOREST MENSURATION

By

C. A. SCHENCK, PH.D.

*Director Biltmore Forest School, and Forester to
the Biltmore Estate*

—
MCMV
—

UNIV. OF CALIFORNIA
LOS ANGELES
LIBRARY

THE UNIVERSITY PRESS
of SEWANEE TENNESSEE

UNIVERSITY OF CALIFORNIA
LIBRARY
215 SHAW BLVD
BERKELEY

371
532f

PREFACE

DEAR READERS :

In the following pages an attempt is made to treat "Forest Mensuration" from a scientific-mathematical standpoint as well as from the view point of practical application.

Naturally, pamphlets of as restricted a character as this treatise on forest mensuration address themselves to a very restricted circle of readers; and the expense of printing is never covered by the returns from sales.

Thus it becomes necessary, in order to reduce the expense of publication, to omit all, or practically all, lengthy explanation of a mathematical nature which the teacher at a forest school can easily supply in the course of his lectures.

The present Biltmore pamphlet on Forest Mensuration is intended, above all, to assist the students enlisted at the Biltmore School. It contains the teacher's dictation which the students, in former years, were compelled to take down in long or shorthand, to the annoyance of both teacher and students.

It cannot be expected that a present-day lumberman will take a direct and personal interest in any of the following paragraphs. Still, in conservative forestry, in destructive forestry, and in any other business enterprise, the truism is worth remembering that "*knowledge is the best of assets.*"

Knowledge certainly forms the only unalienable factor of production.

With the advent of high stumpage prices, the owner of woodland will be inclined to consider, under many circumstances, the advisability of forest-husbandry—an idea which was as preposterous in past decades of superabundance of timber as the raising of beef cattle, some sixty years ago, in the prairies then abounding in buffalo.

Financially considered, a proper outcome of forest-husbandry is and must be based on a proper application of the theories and principles involved in forest mensuration.

I shall be deeply grateful to a kind reader who, discovering mistakes or incongruities in the following paragraphs, will take the trouble of sending me a timely hint.

Most truly,

C. A. SCHENCK,

*Director Biltmore Forest School, and
Forester to the Biltmore Estate.*

August 1, 1905.

ALDINE BOOK CO.
NOV 25 '42
LIBRARY SETS

449709

LECTURES ON FOREST MENSURATION

SYNOPSIS OF CONTENTS BY PARAGRAPHS.

- Par. I. Definition and subdivision.

CHAPTER I.—VOLUME.

SECTION I.—VOLUME OF TREES CUT DOWN.

- Par. II. Units of volume.
Par. III. Mathematical form of trees.
Par. IV. Cylinder
Par. V. Apollonian Paraboloid.
Par. VI. Cone.
Par. VII. Neill's paraboloid.
Par. VIII. Riecke's, Huber's and Smalian's formule.
Par. IX. Hossfeld's formule.
Par. X. Simony's formule.
Par. XI. Sectional measurement.
Par. XII. Measuring the length of a log.
Par. XIII. Measuring the sectional area.
Par. XIV. Instruments for measuring diameters.
Par. XV. Units of log measurement in the United States.
Par. XVI. Board-rules.
Par. XVII. Standard-rules.
Par. XVIII. Cubic foot-rules.
Par. XIX. Equivalents.
Par. XX. Xylometric method.
Par. XXI. Hydrostatic method.
Par. XXII. Factors influencing the solid contents of cordwood.
Par. XXIII. Reducing factors for cordwood.
Par. XXIV. Local peculiarities with reference to stacked wood.
Par. XXV. Bark.

SECTION II.—VOLUME OF STANDING TREES.

- Par. XXVI. Methods of obtaining the volume of standing trees.
Par. XXVII. Helps and hints to find the volume of standing trees.
Par. XXVIII. Scientific methods of ascertaining the cubic contents of standing trees by mere measurement.
Par. XXIX. Form factor method.
Par. XXX. Kinds of form factors mathematically.
Par. XXXI. Kinds of common form factors in European practice.
Par. XXXII. Means for exact mensuration of standing trees.
Par. XXXIII. Measuring the height of a standing tree.
Par. XXXIV. Factors influencing the exactness of hypsometrical observations.

- Par. XXXV. Indirect mensuration of diameter.
 Par. XXXVI. Pressler's telescope.
 Par. XXXVII. Auxiliaries for calculation.
 Par. XXXVIII. Tree volume tables.

SECTION III.—VOLUME OF FORESTS.

- Par. XXXIX. Synopsis of methods for ascertaining the volume of forests.
 Par. XL. Estimation of forest volume.
 Par. XLI. Principles underlying the exact mensuration of forest volume.
 Par. XLII. Fieldwork for exact valuation surveys.
 Par. XLIII. Basal assumptions.
 Par. XLIV. Selection of sample trees.
 Par. XLV. Draudt-Urich method.
 Par. XLVI. Robert Hartig method.
 Par. XLVII. Average sample-tree method.
 Par. XLVIII. Exact mensuration without cutting sample trees.
 Par. XLIX. Combined measuring and estimating.
 Par. L. Form factor method.
 Par. LI. Form height method.
 Par. LII. Volume table method.
 Par. LIII. Yield table method.
 Par. LIV. Distance figure.
 Par. LV. Algon's Universal Volume Tables.
 Par. LVI. Schenck's graphic method.
 Par. LVII. Factors governing the selection of a method of valuation survey
 Par. LVIII. Factors influencing the selection of sample plots.
 Par. LIX. Sir D. Brandis method.
 Par. LX. Pinchot-Graves method on Webb estate.
 Par. LXI. The gridironing method.
 Par. LXII. Forest reserve methods.
 Par. LXIII. Sample squares.
 Par. LXIV. Pisgah Forest method of 1896.
 Par. LXV. Pisgah Forest method for stumpage sale, bark sale and lumbering operations.
 Par. LXVI. Henry Gannett's method, adopted for the XIIth census.
 Par. LXVII. A forty method used in Michigan.
 Par. LXVIII. Dr. Fernow's forty method used at Axton.

CHAPTER II.—AGE OF TREES AND OF FORESTS.

- Par. LXIX. Age of trees cut down.
 Par. LXX. Age of standing trees.
 Par. LXXI. Age of a forest.

CHAPTER III.—INCREMENT OF TREES AND OF FORESTS.

SECTION I.—INCREMENT OF A TREE.

- Par. LXXII. The kinds of increment.
- Par. LXXIII. Height increment.
- Par. LXXIV. The current height increment.
- Par. LXXV. The average height increment.
- Par. LXXVI. Relative increment of the height.
- Par. LXXVII. Diameter increment.
- Par. LXXVIII. Sectional area increment.
- Par. LXXIX. Relative increment of diameter and of sectional area.
- Par. LXXX. Volume increment.
- Par. LXXXI. Section analysis.
- Par. LXXXII. Noerdlinger's paper-weight method.
- Par. LXXXIII. Schenck's graphic tree analysis.
- Par. LXXXIV. Wagener's method and stump analysis.
- Par. LXXXV. Pressler's method.
- Par. LXXXVI. Breyman's method.
- Par. LXXXVII. Factors influencing the cubic volume increment.
- Par. LXXXVIII. Volume increment percentage of standing trees.
- Par. LXXXIX. Interdependence between cubic increment and increment in feet b. m., Doyle.
- Par. XC. Construction of volume tables.

SECTION II.—INCREMENT OF A WOOD.

- Par. XCI. Increment of forests.
- Par. XCII. Method of construction of normal yield tables.
- Par. XCIII. Gathering data for normal yield tables.
- Par. XCIV. Normal yield tables, their purpose and contents abroad.
- Par. XCV. Retrospective yield tables.
- Par. XCVI. Yield tables of the Bureau of Forestry.
- Par. XCVII. The increment of a woodlot.
- Par. XCVIII. Ascertaining the increment of woodlots by sample trees.
- Par. XCIX. Current increment ascertained from average increment.

CHAPTER IV.—LUMBER.

- Par. C. Units of lumber measure.
- Par. CI. Inspection rules and nomenclature.

CHAPTER V.—STUMPAGE-VALUES.

- Par. CII. Stumpage-values.

FOREST MENSURATION

PARAGRAPH I.

DEFINITION AND SUBDIVISION.

Definition: By "Forest Mensuration," the forester ascertains the volume, the age, the increment and the stumpage value of trees, parts of trees and aggregates of trees. As a branch of forestry, forest mensuration may be divided into the following five parts:

- I. Determination of volume of trees cut down, of standing trees and of forests.
- II. Determination of age of trees and of forests.
- III. Determination of increment of trees and of forests.
- IV. Determination of sawn lumber.
- V. Determination of stumpage value.

Circular 445 of the Bureau of Forestry defines mensuration as "the determination of the present and future product of the forest."

American literature is found in Bulletin 20, Division of Forestry; Bulletin 36, Bureau of Forestry; S. B. Green, page 132; Lumber & Log Book and Lumberman's Handbook, edited by the "American Lumberman."

CHAPTER I.—VOLUME.

SECTION I.—VOLUME OF TREES CUT DOWN.

PARAGRAPH II.

UNITS OF VOLUME.

The volume of a tree or of a tree section is expressed:

1. For scientific purposes, on the basis of exact measurements, in cubic feet or cubic meters.
2. For practical purposes, by estimates according to local usage, often assisted by partial measurement, in local units (feet board measure; standards; cords; cubic feet; cord feet; etc.).

PARAGRAPH III.

MATHEMATICAL FORM OF TREES.

Trees do not grow, like crystals, according to purely mathematical laws. Tree growth is deeply influenced by individuality, by surroundings, by accidental occurrences, etc.

The body of a tree, considered as a conoid (a solid body formed by the revolution of a curve about an axis), is very complicated, being formed by a curve of high power. This is the case even in straight and clear boled conifers. The tree bole shows, however, in certain sections of its body frequently a close resemblance to a truncated neilloid, cylinder, paraboloid and cone.

The longitudinal section of conoids is outlined by a curve corresponding with the general equation

$$y^2 = px^n$$

in which y is the ordinate (corresponding with the radius of the basal area), x the abscissa (representing the height of the conoid), n the power of the curve; whilst p is merely a constant factor. The volume v of the conoid is obtained by integral calculus:

$$v = \frac{y^2 \pi x}{n+1}$$

It is equal to sectional area, s , times height, h , over $(n+1)$.

The truncated volumes are developed by deducting a small top conoid from a large total conoid.

$$\text{vol. trunc.} = \frac{s_1 h_1 - s_2 h_2}{n+1}$$

In the general curve equation

$$y^2 = px^n$$

we find represented:

- A. For n equal to 0, the cylinder;
- B. For n equal to 1, the Apollonian paraboloid, wherein the ratio between sectional area and height is constant;
- C. For n equal to 2, the cone, wherein the ratio between radius of sectional area and height is constant;
- D. For n equal to 3, Neill's paraboloid, the truncated form of which is found at the basis of our trees.

The top of the tree resembles a cone or Neilloid; the main bole resembles the cylinder or the Apollonian paraboloid.

The cross section (see Par. XIII.) through a tree taken perpendicular to its axis shows a more or less circular form. Near sets of branches and near the roots, however, the outline is irregular. The center of the circle usually fails to coincide with the axis of the tree.

PARAGRAPH IV.

CYLINDER.

The cubic contents v of a cylinder are equal to the height h of the cylinder, multiplied by the sectional area s of the cylinder.

$$\text{vol. cylinder} = h.s$$

PARAGRAPH V.

APOLLONIAN PARABOLOID.

The volume v of the Apollonian paraboloid is equal to height multiplied by $\frac{1}{2}$ sectional area, or equal to $\frac{1}{2}$ of a cylinder having the same height and the same basal area.

$$\text{vol. apol.} = \frac{h.s}{2}$$

The volume t of the truncated Apollonian paraboloid may be ascertained as:

- A. Height of trunk times arithmetical mean of top sectional area and base sectional area.

$$t. \text{ apol.} = h \frac{s_1 + s_2}{2}$$

- B. Height of trunk times sectional area in the midst of the trunk.

$$t. \text{ apol.} = h.s_{\frac{1}{2}}$$

PARAGRAPH VI.

CONE.

The volume of the ordinary cone is equal to height of cone times $\frac{1}{3}$ sectional area at the base.

$$\text{vol. cone} = \frac{h.s}{3}$$

The volume t of the truncated cone is equal to $\frac{1}{3}$ height of trunk times sum total of top sectional area s_1 , basal sectional area s_2 , and $\sqrt{s_1 s_2}$

$$t. \text{ cone} = \frac{h}{3} (s_1 + s_2 + \sqrt{s_1 s_2})$$

PARAGRAPH VII.

NEILL'S PARABOLOID.

The volume of the Neilloid equals $\frac{1}{4}$ of its height times sectional area at the base.

$$\text{vol. neil.} = \frac{h.s}{4}$$

The volume of the truncated neilloid t equals

$$t. \text{ neil.} = \frac{h}{4} \left(s_1 + s_2 + \sqrt[3]{s_1 s_2} \left[\sqrt[3]{s_1} + \sqrt[3]{s_2} \right] \right)$$

wherein h denotes the height of the trunk; s_1 and s_2 the top sectional area and the basal sectional area of the trunk.

PARAGRAPH VIII.

RIECKE'S, HUBER'S AND SMALIAN'S FORMULE.

Formules of practical and scientific application, used here and abroad, to ascertain the contents of logs, are those published by Smalian, Riecke and Huber.

Riecke's formula holds good for n equal to 0, 1 and 2, and is almost correct for the neilloid.

Smalian over-estimates and Huber under-estimates the actual contents of the truncated cone and of the truncated neilloid.

$$\text{Riecke—Vol. of trunk} = \frac{h}{6} (s_1 + 4s_{\frac{1}{2}} + s_2)$$

$$\text{Huber—Vol. of trunk} = h.s_{\frac{1}{2}}$$

$$\text{Smalian—Vol. of trunk} = \frac{h}{2} (s_1 + s_2)$$

$S_{\frac{1}{2}}$ designates the sectional area in the midst of the trunk, whilst s_1 and s_2 represent basal sectional area and top sectional area.

PARAGRAPH IX.

HOSSFELD'S FORMULE.

The formule given by Hossfeld is:

$$\text{Vol. of trunk} = \frac{h}{4} (3 s_{\frac{1}{2}} + s_2)$$

It holds good for cylinder, cone and paraboloid. $S_{\frac{1}{2}}$ designates the sectional area at $\frac{1}{2}$ of the height of the trunk.

PARAGRAPH X.

SIMONY'S FORMULE.

Simony's formule requires measurements of sectional areas at $\frac{1}{4}$, $\frac{1}{2}$ and $\frac{3}{4}$ of the height of the trunk, thus avoiding the irregularities caused by the roots at the base and by the branches at the top of a tree-trunk.

$$\text{Vol. of trunk} = \frac{h}{3} (2 s_{\frac{1}{4}} - s_{\frac{1}{2}} + 2 s_{\frac{3}{4}})$$

This formule holds good for the four standard conoids.

PARAGRAPH XI.

SECTIONAL MEASUREMENT.

The formules given in Paragraphs III. to X. have, in C. A. Schenck's opinion, a historic interest only when applied to whole trees. It is much safer to ascertain the volume of a tree bole by dissecting it into (imag-

inary) log sections of equal length, considering each of such sections as a cylinder or as a truncated paraboloid. The shorter the length of the sections, the greater the accuracy of the result. In scientific research, the length of a section varies from 5 feet to 10 feet. Obviously, at the top of the bole an uneven length is left, which it might be wise to ascertain as a cone (or paraboloid—Bulletin 20). The volume of the total bole, from stump to tip, equals, if the length of such full section is “l,” and that of the top cone is “b,” and

1) if sectional areas $s_1, s_2, s_3, \dots, s_n$ are measured at the big end of each section:

$$\text{vol bole} = \frac{1}{2} (s_1 + 2s_2 + 2s_3 \dots + s_n) + \frac{b \cdot s_n}{3}$$

2) if sectional areas $s_I, s_{II}, s_{III}, \dots, s_m$ are measured in the midst of each full section, and sectional area s_n at the basis of the top cone:

$$\text{vol. bole} = l (s_I + s_{II} + s_{III} \dots + s_m) + \frac{b \cdot s_n}{3}$$

The former formula is based on Smalian and the latter on Huber.

In a similar way, and with still greater accuracy, the more complicated formulas of Riecke, Hossfeld and Simony might be adapted to sectional measurements.

REMARK: If the diameter in the middle of a log is larger than the arithmetical mean of the end diameters, then the log contains more volume than the truncated cone, and *vice versa*.

If the sectional area at the midst of the log is larger than the arithmetical mean of the end sectional areas, then the log contains more volume than the truncated paraboloid, and *vice versa*.

PARAGRAPH XII.

MEASURING THE LENGTH OF A LOG.

The length of a log is measured with tape, stick or axe handle. In American logging, logs are usually cut in lengths of even feet, increased by an addition of two inches to six inches, which addition allows for shrinkage, for season checks, for damage to the log ends inflicted by snaking or driving, and for the trimming in the saw mill required to removed such end defects.

In Continental Europe, the standard log lengths are multiples of even decimeters. An excess-length of up to eight inches is neglected.

Crooked logs are made straight by deductions either from the length or from the diameter. Crooked trees should be dissected into very short logs.

The standard length of a New England log is 13 feet.

In the case of big logs, great care must be taken by the sawyers to obtain end-cuts perpendicular to the axis of the log.

The sum of the lengths of logs cut from a tree is termed “used length.” The total length of that portion of a bole which is merchantable under given conditions is called “merchantable length.”

PARAGRAPH XIII.

MEASURING THE SECTIONAL AREA.

The sectional areas are ascertained with the help of measuring tape, caliper, tree shears, tree compasses, Biltmore measuring stick, etc.

The sectional area is thus derived from the measurement either of the diameter or of the circumference.

For exact scientific investigations the planimeter or the weight of an even-sized piece of paper may be used.

It is best to consider the sectional area of a tree as an ellipse, the surface of which is:

$$\text{surface} = \frac{\pi}{4} D.d,$$

the big diameter D being measured vertically to the small diameter d .

Usually, however, the average diameter of the tree at a given point is found as the arithmetical mean of the big and small diameter at that point measured crosswise and not as the square root of the product of such diameters. Since

$$\frac{D+d}{2} > \sqrt{D.d},$$

the average diameter is invariably, though slightly, over-estimated by crosswise measurement. Hence it is wise to drop, as an arbitrary offset, the excess of fractions of inches over full inches.

The arithmetical mean of the sectional areas belonging to diameters measured crosswise leads to still greater mistakes.

PARAGRAPH XIV.

INSTRUMENTS FOR MEASURING DIAMETERS.

Log calipers are made of pyrus wood or of metal. American make (Morley Bros., Saginaw, Mich.) cost \$4.00 each. The moving leg of the caliper is kept in place by a spring or a screw or a wedge.

The best European makes are the "Friedrich" and the "Heyer and Staudinger." Wimmenauer's "addition-caliper" counts the trees and adds their sectional areas automatically.

Short legged calipers, named "Dachshunds" by C. A. Schenck, can be used for trees the radius of which exceeds the length of the legs. The diameter is, in that case, indirectly found by the help of the secant joining the tips of the legs, which are about 5" long.

"Tree compasses," opening from six inches to thirty-six inches, and made of nickel-plated steel, cost (at Morley Bros.) \$7.50. "Tree shears" (Treffurth) find the angle formed by the shear-legs when pressed against the tree and directly derive therefrom the diameter or the sectional area of the tree.

The "diameter tape" slung around the tree usually yields too large a diameter, since the circle embraces the maximum of surface by the minimum of length.

The "Biltmore Measuring Stick" can be well used in timber cruising. It requires the exact adjustment of distance between eye and fist of observer (usually 26 inches), and gives directly the diameter at the point of the stick where the sight line passes the tree tangentially. The stick is held horizontally against the tree.

26-INCH BILTMORE MEASURING STICK.

Length on the stick.	Diameter with bark.	Contents of butt log.	Contents of two logs.	Contents of three logs.
2.8"	3"	Allowing three inches for bark and three inches for taper, per log; assuming that all logs are 14' long.		
5.4"	6"			
7.7"	9"			
9.9"	12"			
11.9"	15"	22 ft. b. m.	29 ft. b. m.	39 ft. b. m.
13.8"	18"	56 " "	78 " "	85 " "
15.6"	21"	106 " "	162 " "	184 " "
17.3"	24"	171 " "	277 " "	333 " "
18.9"	27"	253 " "	424 " "	530 " "
20.4"	30"	350 " "	603 " "	774 " "
21.9"	33"	463 " "	813 " "	1066 " "
23.3"	36"	591 " "	1054 " "	1404 " "

Mr. Snead recommends to measure the circumference outside the bark at the big end and to divide the result by 4. He claims that the quotient yields the diameter at the small end inside bark in such a way as to offset mistakes made by Doyle, who under-estimates small logs and over-estimates big logs. Snead's suggestion is good, provided, that the cross section of the log is fairly circular, and that the difference between the small diameter inside bark at the small end and the big diameter outside bark at the big end, amounts to about 7 inches.

Diameter at small end inside bark.	Contents of 16 foot logs, in feet b.m.		
	Doyle.	Snead.	Actual saw cut.
10 inches.....	36'	81'	70'
15 "	121'	169'	157'
20 "	256'	289'	279'
25 "	441'	441'	436'
30 "	676'	625'	628'
35 "	961'	841'	856'

The multiples of sectional area (derived from the diameter in inches, but expressed in square feet) by length of log are readily obtained from cylinder tables published by various authors. The log scale or log rule used by the lumbermen (Lufkin rule) gives at a glance the contents of logs 8 to 20 feet long, according to their diameter.

PARAGRAPH XV.

UNITS OF LOG MEASUREMENT IN THE UNITED STATES.

The units of log measurement used in the United States differ greatly. Graves' Handbook gives 43 "rules." The rules can be subdivided into three main groups:

- Board feet group (Par. XVI.);
- Standard log group (Par. XVII.);
- Artificial cubic foot group (Par. XVIII.).

PARAGRAPH XVI.

BOARD-RULES.

A foot board measure is a superficial foot one inch thick, in boards one inch or more in thickness. It is a superficial foot, irrespective of thickness, in boards less than one inch in thickness.

The "board rules" merely guess at the number of feet board measure obtainable from logs of a given diameter. The guess is based upon either graphical considerations, circles of specified diameters being subdivided into parallelograms $1\frac{1}{4}$ inch thick (diagram method), or else on mathematical considerations, with a view to the fact that a cubic foot of timber should theoretically yield 12 board feet of lumber, whilst the actual loss for slab, saw kerf, etc., will reduce the output by 30% to 50%. In the Biltmore band saw mill, by over one thousand tests, the actual loss for logs 12 inches to 40 inches in diameter has been found to amount to 30%, or close to $1/3$. Consequently, it is safe to say that the band saw obtains from a cubic foot of log 8 board feet of lumber.

The number of board feet which a log actually yields depends on:

1. The actual cubic volume of a cylinder having the length and smallest diameter inside bark of the log.
2. The defects of the log (heart rot, wind shake, bad knots, crooks), which are usually eliminated by edger or trimmer.
3. The gauge of the saw, on which the saw kerf depends. The kerf of band saws amounts to $\frac{1}{8}$ inch, of circular saws to usually $\frac{1}{4}$ inch, of inserted tooth saws (of large diameter) to $\frac{3}{8}$ inch, of resaws to $1/16$ inch.
4. The exactness of the work, especially depending on trueness of saw, proper lining of saw and sawyer's skill; further, on the exactness of the networks.
5. The thickness of boards obtained; the minimum width of boards permitted; the amount of lumber wasted in the slabs; shrinkage in drying.

The following table compares the contents of logs in cubic feet with their contents in feet board measure as found by C. A. Schenck through a thousand tests of actual yield in yellow poplar, as given by Doyle's rule and by Lumberman's Favorite rule.

The figures given in columns c, f and i show the contents of a log in feet board measure after Schenck's findings, Doyle's and Favorite

rules. They are converted into cubic feet (columns d, g, and j) by dividing by 12. The loss incurred in sawing is shown by percentages (columns e, h, k) representing the ratio between the actual cubic contents of a log (as given in column b), and the cubic contents of inch boards (columns d, g, j) obtained from such log.

It will be observed that the loss in the actual yield according to Schenck forms a nearly constant proportion of the cubic contents of a log in the case of all diameters, whilst, according to Doyle's and Favorite rules, the figures of loss vary greatly.

The table refers to logs 12' long sawed into 1-inch boards.

Diameter of Log. Inches.	Contents. Cubic Feet.	Schenck.			Doyle.			Favorite.		
		Feet b. m.	Cubic Feet.	Loss %	Feet b. m.	Cubic Feet.	Loss %	Feet b. m.	Cubic Feet.	Loss %
a.	b.	c.	d.	e.	f.	g.	h.	i.	j.	k.
8	4.2				12	0.9	76			
9	5.3				19	1.6	70			
10	6.5				27	2.3	65			
11	8.0				37	3.1	61			
12	9.4	78	6.5	31	48	4.0	57	49	4.1	56
13	11.0	96	8.0	27	61	5.1	54	62	5.2	53
14	12.8	112	9.3	27	75	6.3	51	74	6.2	52
15	14.7	129	10.7	27	91	7.6	48	90	7.5	49
16	16.8	146	12.2	27	108	9.0	46	107	8.9	46
17	18.9	162	13.5	29	127	10.6	44	125	10.4	45
18	21.2	180	15.0	29	147	12.3	42	148	12.3	42
19	23.6	197	16.4	30	169	14.1	40	170	14.2	39
20	26.2	212	17.7	32	192	16.0	39	186	15.5	41
21	28.9	230	19.2	34	217	18.1	37	214	17.8	38
22	31.7	248	20.7	35	243	20.3	36	243	20.3	36
23	34.6	266	22.2	36	271	22.6	35	268	22.3	36
24	37.7	298	24.8	34	300	25.0	33	294	24.5	35
25	40.9	331	27.6	32	331	27.6	32	326	27.2	33
26	44.2	362	30.2	32	363	30.3	31	358	29.8	33
27	47.7	394	32.9	31	397	33.1	30	390	32.5	32
28	51.3	422	35.2	31	432	36.0	30	422	35.2	31
29	55.0	456	38.0	31	469	39.1	29	448	37.3	32
30	58.9	488	40.7	31	507	42.3	28	474	39.5	33
31	62.9	518	43.2	31	547	45.6	27	509	42.4	33
32	67.0	556	46.3	31	588	49.0	27	544	45.3	32
33	71.3	596	49.7	30	631	52.6	26	589	49.1	31
34	75.7	634	52.8	30	675	56.3	26	634	52.8	30
35	80.2	670	55.8	30	721	60.1	25	662	55.2	31
36	84.8	710	59.2	30	768	64.0	25	690	57.5	32
37	89.6	755	62.9	30	817	68.1	24	734	61.2	32
38	94.5	806	66.7	29	867	72.3	23	778	64.8	31
39	99.5	850	70.8	29	910	75.8	24	824	68.7	31
40	104.7	901	75.0	28	972	81.0	23	870	72.5	31

From column e it is evident that the bandsaw wastes close to 1/3 of the cubic contents of a cylindrical log, or 4' b. m. out of every cubic foot.

Consequently, from hardwood logs 12 feet to 16 feet long, the band-

saw will obtain the following *actual* number of feet b. m. (in 4/4" thickness) :

(a) from 12 foot logs: $\frac{D^2 \times 0.78 \times 12 \times 8}{144}$, almost equal to $D^2 \times .5$

(b) from 14 foot logs: $\frac{D^2 \times 0.78 \times 14 \times 8}{144}$, almost equal to $D^2 \times .6$

(c) from 16 foot logs: $\frac{D^2 \times 0.78 \times 16 \times 8}{144}$, almost equal to $D^2 \times .7$

Hence it can be stated generally, for logs of medium length "L," that their contents in band-sawed inch lumber approximate

$$\frac{D^2}{10} \times \frac{L-2}{2} \text{ feet b. m.}$$

PARAGRAPH XVII.

STANDARD RULES.

The standard rules do not estimate the contents of a log according to output in board feet, but compare the log with a local average log. Such average logs used to have, in the Northeast, formerly, a diameter of either 19 inches (Adirondacks) or 22 inches (Saranac River) or 24 inches, and were in all cases 13 feet long.

The 19 inch standard log rule is known as Dimick's rule. Here the "standard" or "market" is a log 13 feet long and 19 inches thick. On a 22 inch base it is 13 feet long and 22 inches thick. On a 24 inch base it is 13 feet long and 24 inches thick.

The standard contents of a given log are found by dividing the cubic volume of the standard log into the cubic volume of the given log.

$$v \text{ (in standards) equals: } \frac{d^2 \times h}{19^2 \times 13}$$

Scientifically and mathematically the standard rules are superior to the board rules. One market, at a 19 inch base, is generally considered equivalent to 200 board feet; at a 22 inch base, to 250 board feet; at a 24 inch base, to 300 board feet.

It is easily shown that the output of small logs is not as badly underestimated, and the output of big logs not as badly over-estimated on the basis of standard rules, as is the case when Doyle's rule alone is applied.

PARAGRAPH XVIII.

CUBIC FOOT-RULES.

In a third group of rules, a new unit, the "artificial cubic foot," is introduced. This group of rules is established by law in Maine and New Hampshire. (See Graves' Handbook, page 45.)

The artificial cubic foot corresponds with a log 12 inches long and 16 inches thick, which naturally contains 1.4 cubic feet. The rule assumes that 40/140 or 28.5% of a log goes to waste in the sawing process as dust or slab.

To quickly transform artificial cubic feet into board feet, the laws prescribe certain arbitrary equivalents, instead of allowing 12 board feet to equal one artificial cubic foot of timber. In New Hampshire, 10 board feet equal one artificial cubic foot. In Maine, 11.5 board feet equal one cubic foot. The rules might be used in connection with a cylinder table, deducting 28.5% from the table data and multiplying the remainder by 10 or by 11.5.

REMARK: According to the Forest Reserve Manual, logs over 24 feet long are treated as 16 foot logs and fractions thereof.

PARAGRAPH XIX.

EQUIVALENTS.

One cubic meter equals 35.316 feet or 1.308 cubic yards.

1,000 board feet of sawn lumber, 1 inch and more thick, correspond with 2.36 cubic meters of sawn lumber.

A product of one cubic meter per hectare ($2\frac{1}{2}$ acres) equals a product of 14 cubic feet per acre.

One gallon equals 231 cubic inches in liquid measure, or 268.8 cubic inches in dry measure (which is also $\frac{1}{2}$ peck).

One liter equals 1.0567 quarts; one cubic foot equals 7.4805 gallons or 28.3 liters.

Logs yielding when split one cord of wood, will yield, when sawn:

For log diameter:	Feet board measure:
20"	515'
25"	566'
30"	605'
35"	629'
40"	649'

The Forest Reserve Manual adopts 2 cords as equivalent to 1,000 cubic feet b. m., provided that the wood is split from timber 10 inches in diameter and over.

TABLE SHOWING RELATIVE CONTENTS OF LOGS WITHOUT BARK.

Log diameter.	5"	10"	15"	20"	25"	30"
1 cubic foot equals ft. b. m. Doyle		4.12	6.2	7.3	8.09	8.64
1 cubic meter per hectare corresponds with ft. b. m. Doyle per acre:.....		57.68	86.8	102.2	113.26	120.96
1 cubic meter of log yields ft. b. m. Doyle:.....	44.8	145.5	218.2	258.8	285.7	303.7
1000 ft. b. m. Doyle equal cubic ft.:.....	787.4	242.7	161.8	136.4	123.6	116.3
1000 ft. b. m. Doyle equal cubic meters:.....		6.87	4.39	3.86	3.5	3.29
Artificial cubic feet per 1 ft. of log		.4	.9	1.56	2.45	3.51
No. of legal N. H. feet b. m. per 1 ft of log:.....		4.	9.	15.6	24.5	35.1
Ft. b. m. Doyle per 1 ft. of log:.....		2.3	7.5	16.	27.5	42.5

PARAGRAPH XX.

XYLOMETRIC METHOD.

The so-called "physical methods," by which the volume of a (particularly irregular) piece of a tree may be accurately found, require either the submersion of the piece in water (xylometric method) or the weighing of the piece after finding its specific gravity (hydrostatic method, § XXI.).

The xylometric method can be applied in three ways, thus:

a. Submerge the wood in a graded cylinder partly filled with water and find the water level before and after submersion.

b. Submerge the wood in a barrel partly filled with water; dip out the water with a gallon measure until the water is as low as it was before submersion. The number of gallons dipped out equals the volume of the wood submerged. One gallon equals 231 cubic inches.

c. Place a piece of wood in an empty barrel of known contents; fill to the rim with water by the gallon. The difference between the known contents and the number of gallons required gives the quantity of wood in gallons.

In *a*, *b* and *c* it is necessary to use wood dry on the outside, to leave the wood in the water a short time only, and to stir it up while in the water so as to remove air bubbles.

PARAGRAPH XXI.

HYDROSTATIC METHOD.

The hydrostatic method deals with specific gravities. Specific gravity is weight of an object divided by the weight of an equal volume of

water. In the metric system, it equals weight in kilograms over cubic-decimeters of volume. The specific gravity is found by weighing a given body, and then weighing it again immersed in water. It equals weight outside water over loss of weight submerged in water. The division of the metric weight of a large body by the specific gravity of a sample piece yields the volume of the body in cubic decimeters.

Since wood is lighter than water, usually, a piece of lead must be attached to the wood in order to submerge it. There must be ascertained:

1. The absolute weight of the piece of lead, H ;
2. The weight of the same piece submerged in water, h ;
3. The absolute weight of the wood and of the lead, G ;
4. The weight of wood and lead submerged in water, g .

The weight of the wood alone is, consequently, $(G-H)$.

The specific gravity of the wood is

$$s = \frac{G - H}{(G - g) - (H - h)}$$

The volume, in cubic feet, of a quantity of wood weighing n pounds, and having the specific gravity s , is

$$\text{volume} = \frac{n}{s} \times \frac{1}{63} = \frac{16n}{1000s}$$

The figure 63 represents the weight in pounds of one cubic foot of water.

The specific gravity of wood is greatest close to the stump and in the branches. For some species the outer layers show the greatest specific gravity; for others the inner layers.

Species.	Spec. gravity, air dry.	Weight of lumber per 1000 ft. b. m. in lbs.	Weight of one cord in lbs.
White oak.....	.75	3900	3985
Beech.....	.71	3692	3767
Hard maple....	.66	3432	3510
Yellow pine....	.52	2704	2761
Spruce.....	.45	2340	2391
White pine.....	.39	2028	2069

Rules to convert specific gravity into weight per 1,000 feet board measure or into weight per cord read as follows:

1. Multiply specific gravity by 5,200. The result is the weight of lumber per 1,000 feet board measure in pounds.

2. Multiply specific gravity by percentage of solid wood contained in a stacked pile; then multiply the product by 8,050. The result gives the weight per cord in pounds.

PARAGRAPH XXII.

FACTORS INFLUENCING THE SOLID CONTENTS OF CORDWOOD.

The solid contents of wood stacks depend on the size and the form of the pieces composing them and on the method of piling. The solid contents of a cord can be found only by the methods described in Paragraphs XX. and XXI. The European experiment stations have collected data to that end on a very large scale, and have established the following laws:

a. The bigger the pieces of wood in a stack, the larger are the solid contents of the stack.

b. The longer the pieces of wood, the smaller are the solid contents of the stack.

c. Pieces piled parallel and tightly greatly increase the solid contents of the stack.

d. During the drying process, hardwoods shrink approximately by 12%, and soft woods by 9%. The shrinkage is partly offset by the cracking of wood.

These rules are important in the pulp, tanningwood and firewood trade.

PARAGRAPH XXIII.

REDUCING FACTORS FOR CORDWOOD.

The countries using the metric system pile wood in space cubic meters. One space cubic meter equals .274 cord. The pieces contained therein are 3.28 feet long. For such conditions the following figures hold good:

a. First class split wood, obtained from sound pieces 12 inches in diameter, contains per cord 102.4 cubic feet of solid wood (reducing factor 80%).

b. Composed of inferior split wood, obtained from round pieces having a diameter of 6 inches, a cord contains 96 cubic feet of solid wood (reducing factor 75%).

c. In heavy, round branch wood (diameters of about 6½ inches) 87 cubic feet of solid wood are found in a cord (reducing factor 68%).

d. In round pieces of branch wood, 4 inches in diameter, 77 cubic feet are found in a cord (reducing factor 60%).

e. In faggots, 25 to 51 cubic feet make a cord (reducing factor 20% to 40%).

The percentages for broad leafed species are smaller than those for conifers, owing to the latter's straight growth.

At Biltmore, one cord of 8 foot split oak contains about 80 cubic feet; one cord of kindling finely split about 90 cubic feet; one cord of blocks 12 inches long about 100 cubic feet of solid wood.

In the sale of tannin wood it is well to sell 5 foot sticks finely split rather than heavy blocks 4 feet long.

In the sale of pulp wood, 12 foot sticks yield much higher returns than 4 foot sticks, if sales are made by the cord.

PARAGRAPH XXIV.

LOCAL PECULIARITIES WITH REFERENCE TO STACKED WOOD.

Tannin and pulp wood industries sometimes figure at a cord containing 160 stacked cubic feet, equal to $1\frac{1}{4}$ ordinary cords of 128 stacked cubic feet.

After Graves (page 65), a cord of firewood is in certain sections understood to be 5 feet long, 4 feet high and $6\frac{1}{2}$ feet wide.

Under "a cord foot" is understood a stack 1 foot by 4 feet by 4 feet ($\frac{1}{8}$ cord or 16 stacked cubic feet).

Under "a cylindrical foot" is understood a stacked cubic foot equal to $1/128$ cord. The number of such feet (a misnomer for stacked cubic feet) in a stick is

$$\frac{d^2 \times l}{144}$$

(l equals length of stick in feet; d equals its diameter in inches).

In New England, a cord of pulp wood is sometimes measured by calipering the round sticks composing it, and tables are constructed to facilitate calculation. Proceed as follows:

Ascertain diameter of sticks in inches, square them singly, total the results and divide by 144. Multiply the quotient by length of sticks in feet and divide by 128.

PARAGRAPH XXV.

BARK.

Bark is usually sold and bought by the cord. The tanneries, however, instead of measuring a cord of 128 cubic feet, apply the misnomer "one cord" to a weight of 2,240 lbs. (the long or European ton).

Twelve cords of bark fill one common (old) freight car.

A stack of bark contains from 30% to 40% solid bark. The specific gravity of fresh oak bark is 0.874; dried, it is 0.764.

The bark of white oak has been found (at Biltmore), to comprise:

In trees 20 years old, 55% of the wood, or 35% of the whole bole;

In trees 60 years old, 41% of the wood or 28% of the whole bole;

In trees 100 years old, 29% of the wood or 22% of the whole bole;

In trees 140 years old, 21% of the wood or 17% of the whole bole.

Chestnut oak peeled at Biltmore yields the following results per tree, arranged according to the diameter of the trees $4\frac{1}{2}$ feet above ground:

Diameter of tree chest high in inches.	Dry Bark in Kilogram = $\frac{1}{1000}$ cord, per Tree.		
	Minimum	Average.	Maximum.
6	5	13	27
7	6	17	36
8	8	24	48
9	12	33	61
10	18	45	77
11	26	60	95
12	37	73	114
13	50	88	135
14	65	105	158
15	81	126	180
16	98	150	204
17	116	172	234
18	136	195	266
19	159	224	314
20	181	250	365
21	205	275	...
22	230	305	...
23	265	336	...
24	275	375	...

If the percentage of bark in a log or tree (scaled with the bark) is p , then the bark percentage in ratio to the solid wood alone is:

$$\frac{100 \times p}{100 - p}$$

According to thickness of bark and diameter of logs, the following percentages can be given for the ratio:

$$\frac{\text{bark}}{\text{bark plus timber}}$$

Diameter with bark—inches.	Thickness of bark.			
	$\frac{1}{2}$ "	1"	$1\frac{1}{2}$ "	2"
10	19%	36%	51%	64%
15	12%	24%	36%	46%
20	9%	19%	27%	36%
25	7%	15%	22%	29%
30	6%	12%	19%	24%

$$\frac{P}{100} = \frac{\text{bark}}{\text{volume}}$$

SECTION II.—VOLUME OF STANDING TREES.

PARAGRAPH XXVI.

METHODS OF OBTAINING THE VOLUME OF STANDING TREES.

The volume of standing trees may be ascertained

By estimating it (Par. XXVII.);

By measuring heights and diameters (Par. XXVIII.);

By the form factor method, which combines estimates and measurements (Par. XXIX. f.f.).

By these means can be obtained the volume of the bole (from roots to top bud), or the volume of saw timber in any of the 43 log scales, or the volume of firewood in cords, etc., or the total volume, including brush and roots.

Under "used volume," Circular 445 of the United States Bureau of Forestry understands the sum of the volumes of logs cut from a tree; under "merchantable volume" the total volume of that portion of the tree which is merchantable under certain conditions.

PARAGRAPH XXVII.

HELPS AND HINTS TO FIND THE VOLUME OF STANDING TREES.

It is difficult to estimate the cubic contents, wood contents or lumber contents of a standing tree. In the case of estimates in board feet, the result depends on the exclusion or inclusion of crooked and defective pieces, on the taper of the bole, on the soundness of the heart, and on the minimum diameter admissible in the top log. Compare end of Paragraph XXXII.

Most hazardous is the volume estimate of over-aged trees, especially in the case of hardwoods (chestnut).

The following helps might guide the novice:

1. The volume of a sound tree bole, in cubic meters, is equal to

$$\frac{1}{1000} D^2$$

for example, diameter (breast high) 30 c. m.; contents 0.9 cubic meters.

2. The contents of a standing tree, in cubic feet, are about

$$\frac{2}{10} D^2$$

for example, diameter (breast high), 25 inches; contents (from butt to tip), 125 cubic feet.

3. The number of feet Doyle in a tall sound tree equal

$$\frac{3}{2} D^2$$

for example, diameter (breast high), 20 inches; contents 600 feet board measure.

4. The contents of a tree in feet Doyle approximate, assuming that the bole is cut into 16 foot logs, and that the tree tapers 2 inches per log:

$$N \times D (D - 12)$$

wherein N represents the number of logs obtainable; D the diameter of the butt log without bark at breast height.

5. The cordwood contained in a sound bole is:

$$\frac{D^3}{1000} \times C$$

wherein C amounts to:

- 1.5 in the case of trees 8" through;
- 2.0 in the case of trees 16" through;
- 2.5 in the case of trees 24" through.

PARAGRAPH XXVIII.

SCIENTIFIC METHODS OF ASCERTAINING THE CUBIC CONTENTS OF STANDING TREES BY MERE MEASUREMENT.

The cubic volume of the bole, on the basis of diameter measurement and height measurement, in the case of a standing tree, may (with the help of climbing iron, ladders, camera or instruments constructed for the purpose) be figured out:

1. According to the formulas of Hossfeldt, Riecke and Simony. In this case, the upper diameters must be measured indirectly.

2. According to Huber's and Smalian's formulas, the diameters of equal sections of the trees being indirectly measured.

3. According to Pressler's formula, which is, for the volume of the bole lying between chest height and top bud, $\frac{2}{3}$ of sectional area "S" at chest height times "rectified" height of bole. The rectified height "r" is the distance of chest height from that point of the tree bole which has $\frac{1}{2}$ of the chest height diameter (from the "guide point"). The equation $\frac{2}{3} r \times S$ holds good for paraboloid, cone and, at a slight mistake, for the neilloid.

The volume of that part of the tree bole which lies below chest height is ascertained (as a cylinder) as being equal to sectional area chest high times 4.5.

REMARK: 4.3' is the chest height usually recognized by the authors; Pinchot adopts 4.5'.

The Pressler formula does not hold good for truncated boles.

PARAGRAPH XXIX.

FORM FACTOR METHOD.

The form factor or form figure method relies on the measurement of the sectional area—usually the one at breast height,—the measurement or the estimation of the total height and the estimation of the form figure.

The form factor is a fraction expressing the relation between the actual contents of a tree, in any unit, and the ideal contents which a tree would have if it were carrying its girth (like a cylinder) up to the top bud undiminished.

The form factor may be given in reference to the volume of the entire tree, inclusive of branches in cubic feet; or in reference to the volume of the bole only; or in reference to the merchantable part of the bole; in the latter case either in feet board measure or in standards or in cords.

HISTORIC REMARKS: Some of the older authors on mensuration saw in the cone and not in the cylinder the ideal form of the tree, basing their form factors on the ideal volume $\frac{s \times h}{3}$.

PARAGRAPH XXX.

KINDS OF FORM FACTORS MATHEMATICALLY.

Scientifically we distinguish between:

1. The absolute form factors which have reference only to the volume standing above chest height. They can be readily ascertained with the help of Pressler's formula. Generally speaking, V equals $S \times H \times F$. After Pressler, V equals $S \times \frac{2}{3} \times r$; thus $\frac{\frac{2}{3} r}{H}$ equals F .

For the cone the absolute form factor is one-third; for the neiloid one-fourth; for the paraboloid one-half, whatever the height of the tree may be. Hans Rienicker, the author of these form factors, finds for trees up to 50 years old a form figure of 35% to 43% (in regular, dense German woods); in trees 50 to 100 years old, F increases up to 50%; thereafter occurs a slight decrease below 50%.

2. The normal form factors which were recommended by Smalian, Pressler and other old-time authors. They have reference to the entire volume and necessitate the measurement of the diameter at a given fraction (usually $1/20$) of the total height of the tree. Frequently, in case of tall trees, the point of measurement cannot be reached from the ground. The bole form factor for diameters measured at $1/20$ of the height is: For a paraboloid, 0.526; for a cone, 0.369; for a neiloid, 0.292. These form factors, like the absolute form factors, are independent of the height.

3. The so-called "common form factors" which do not express, as a matter of fact, the form of the tree, since they do not bear any direct ratio to the degree of the tree curve. They should be termed, more

properly, "reducing factors." These form factors alone are nowadays practically used. They are based on diameter measurements, chest high, and have reference not merely to the bole of the tree, but as well to any parts of the bole, to root and branch wood, to saw logs, etc. These form factors depend entirely on the height. If, for instance, a paraboloid is one rod high, the form factor is 0.673; and if it is 8 rods high, the form factor is 0.517.

PARAGRAPH XXXI.

KINDS OF COMMON FORM FACTORS IN EUROPEAN PRACTICE.

The following kinds of form factors may be distinguished:

1. Tree form factors. The tree is considered as bole plus branches.
2. Timber form factors. The term timber, in Europe, includes all parts of the tree having over 3 inches diameter at the small end.
3. Bole form factors. Bole is the central stem from soil to top bud. For America, form factors would be of great value ascertained by exact measurements and arranged according to diameter, height and smallest log diameter used.

Tables of form factors may be constructed, for instance, for shortleaf pine, on the basis of Olmsted's working plan, pages 17-33.

PINUS ECHINATA.

Diameter.	Merchantable length of bole.	Cubic feet Ideal cylinder.	Form fig.	Contents b. m. Doyle.
16"	36'	50.3	3.6	180'
18"	47'	83.1	3.6	300'
20"	51'	112.1	4.0	440'
22"	56'	147.8	4.0	600'
24"	59'	185.3	4.2	780'
26"	61'	224.9	4.4	980'
28"	62'	263.1	4.5	1190'
30"	62' 6"	306.7	4.6	1420'
32"	63'	351.8	4.7	1680'
34"	63' 6"	400.3	4.8	1930'
36"	64'	457.3	4.9	2200'

The influence of age, soil, density of stand, height, diameter and species on the various form factors, with cubic measure as a basis, has not been fully ascertained.

For the tree form factor, the most important influence, in the case of trees less than 150 years old and raised in a close stand, seems to be that of the height of the tree; with increasing height the tree form factor decreases—*e. g.*, for Yellow Pine:

One pole high	.93
Two poles high	.65
Four poles high	.53
Six poles high	.49

The timber form factor, based on cubic measure of a tree, rises with increasing age and increasing height up to a certain point (for Yellow Pine at 3 poles), provided that the term timber includes all stuff over 3 inches in diameter. The timber form factor is a function more of the diameter than of the height. Timber form factors of Yellow Pine are:

Trees 1 pole high	.07
Trees 2 poles high	.36
Trees 3 poles high	.48
Trees 4 poles high	.46
Trees 7 poles high	.45

The timber form factor in shade bearers is a little higher than that in light demanders (within an age limit of 150 years, for trees in close stand).

The bole form factor can be found, in fact, only for species forming a straight bole free from large branches (hence especially for conifers). The bole form factors, to begin with, are large; with increasing height, they decrease gradually to a par with the timber form factors—*e. g.*, for Yellow Pine:

1 pole high.....	.70	3 poles high.....	.49
2 poles high.....	.55	4 poles high.....	.47
7 poles high.....	.45		

European common form factors are collected by thousands of measurements taken in a large variety of localities. It must be remembered that a form factor read from a table is never applicable to an individual tree, and is only applicable to an average tree amongst thousands.

For trees less than 120 years old, the branch wood (stuff less than 3 inches in diameter) comprises from 15% to 28% of the entire tree volume; this figure, in the case of broadleaved species, rises from 25% up to 33%. For trees as now logged in America, the branchwood percentage is naturally very much smaller.

The tree form factor equals $\frac{\text{stump plus bole plus branches}}{\text{ideal cylinder}}$

The timber form factor equals $\frac{\text{all stuff having over 3" diameter}}{\text{ideal cylinder}}$

The bole form factor equals $\frac{\text{bole from ground to tip}}{\text{ideal cylinder}}$

By form height is meant the product of height (total height of tree) times form factor, or else that much of the height of the ideal cylinder which the tree volume, poured into the ideal cylinder, would fill. Since the form factor on the whole decreases with increasing height, the form height is a fairly constant quantity; at least for trees of merchantable size. Hence the helps and hints given in Paragraph XXVII (to quickly find the volume of standing trees from mere diameter-measurement) may

lay claim to correctness in many cases. For instance: The cubic contents of a tree are supposed to be equal to

$$\frac{\pi}{4} \times \frac{D^2 \times H \times F}{144}$$

After Paragraph XXVII., 2, these contents are also

$$\frac{2}{10} \times D^2$$

$$\frac{D^2}{5} = D^2 \times 78 \times H \times F$$

$$H \times F = \frac{288}{7.8} = 37$$

As a matter of fact, the form height of trees 1 foot to 2 feet in diameter is close to 37. And for such trees the equation holds good.

The form height may also be defined as "volume (standards, cords, bark, etc.) per square foot of sectional area chest-high."

PARAGRAPH XXXII.

MEANS FOR EXACT MENSURATION OF STANDING TREES.

The means used to find the exact solid volume of standing trees are instruments for measuring the total height of the merchantable length of a tree; instruments for measuring the diameter at given heights; further tables based on scientific research and experience, or tables merely meant to facilitate calculation. Instruments for measuring diameters far above ground are needed for the use of the formulas given by Riecke, Hossfeldt, Pressler, etc.

The six paragraphs following next dwell upon these topics.

PARAGRAPH XXXIII.

MEASURING THE HEIGHT OF A STANDING TREE.

The height of a tree can be measured by comparing its shadow with the shadow of a stick, say 10 feet long. The "Lumber and Log Book" gives another old method (page 133) of height measurement. If the observer places himself in such a way that a small pole stands between him and the tree at a distance e , and if he marks on the pole two points where his sight, directed towards the top and base of the tree, touches the small pole, and if he further ascertains the distance E separating him from the tree, then the height of the tree H equals

$$\frac{E}{e} \times h$$

wherein h represents the number of feet between the two points marked on the pole.

Instruments (hypsometers) for height measuring are sold in many forms. The following are frequently used: Rudnicka's instrument; Pressler's "Measuring Jack;" Faustmann's "Mirror Hypsometer;" Weise's Telescope; Koenig's "Measuring Board;" Brandis' "Clinometer;" Klausner's instrument; Christen's "Non plus ultra."

Compare Woodman's Handbook, pages 136 to 137, for staff method; page 138 for Faustmann's; page 140 for tangential clinometer; page 143 for mirror clinometer.

Christen's stick is not accurate enough for the measurement of trees over 100 feet high. It does not require the measurement of distances. Its form is improved by Pinchot.

PARAGRAPH XXXIV.

FACTORS INFLUENCING THE EXACTNESS OF HYPOMETRICAL OBSERVATIONS.

The best results are obtained if the distance between tree and observer equals the height to be measured. In sighting towards the spreading top of a hardwood tree, the observer is apt to overrate the height, the tip being buried in the spreading crown. The line of sight strikes the edge of the crown instead of striking the apex of the crown.

Timber cruisers are usually satisfied to determine the number of logs obtainable from the bole instead of determining the length of the bole. As a matter of fact, where the tree furnishes saw logs only, the total height of the tree is a less reliable indicator of the total contents than the length of the merchantable bole.

Instruments like Faustmann's, Koenig's and Pressler's cannot be used in windy and rainy weather. Dense undergrowth and dense cover overhead render exact measurement impossible.

PARAGRAPH XXXV.

INDIRECT MENSURATION OF DIAMETERS.

The following instruments are used to measure the diameter of the tree at any point of bole:

- a. Winkler, an addition to Koenig's measuring board.
- b. Klausner.
- c. An ordinary transit.
- d. Wimmenauer's telescope.

PARAGRAPH XXXVI.

PRESSLER'S TELESCOPE.

Pressler's telescope is used to find the "guidepoint" and the "rectified height," as defined in Paragraph XXVIII., 3. The diameter chest-high is taken between the nails at the end of the instrument. Then the telescope is pulled out to a length double the original, divided by the cosin

of the angle found between the horizon and the probable sight to the "guidepoint" (at which the observer expects to find one-half the diameter chest-high). Thus, actually, the instrument merely examines the correctness of an original estimate.

The Pressler telescope can be used for finding the merchantable length of any bole. Merely place a stick, equal in length to twice the minimum diameter permissible in a merchantable log, at the foot of the tree, catch it between the nail points and proceed as described.

PARAGRAPH XXXVII.

AUXILIARIES FOR CALCULATION.

Auxiliaries for calculation are:

1. Sectional area tables (Schlich, Vol. III.); engineering books like Haswell's; Bulletin 20; also Green.)
2. Ideal cylinder tables (Schlich and Bulletin 20).
3. Multiplication tables and logarithm-tables.
4. Tables showing contents of logs in any of the 43 rules, according to length and diameter.

PARAGRAPH XXXVIII.

TREE VOLUME-TABLES.

Tree volume tables have been constructed on a very large scale for the leading species in the old country. In the United States, the Government is now beginning to make such tables. The tables give the cubic, lumber and cord wood contents of trees, according to species, diameter and sometimes according to total height and merchantable height (number of logs).

Bulletin 36 reprints the following tree volume tables:

A. According to diameter measure merely.

- Page 92. Adirondack White Pine, volume in standards.
- Page 94. Pennsylvania Hemlock, volume in feet, b. m., Scribner.
- Page 94. Adirondack Hemlock, in standards.
- Page 95. Adirondack Spruce in standards.
- Page 96. Adirondack Birch, Beech, Linden, Sugar Maple in Scribner, feet, b. m.
- Page 96. Adirondack Balsam, in standards.
- Page 97. Adirondack White Cedar, in standards.
- Page 98. Arkansas Shortleaf Pine, in feet, b. m., Doyle.
- Page 98. Missouri Ash, Elm, Maple, Cypress, Gum, Oak, Hickory, Poplar, in feet, b. m., Doyle.
- Page 99. Western Yellow Pine, in feet, b. m., Doyle (Black Hills), distinguishing between the volume of first and second growth.
- Page 99. Yellow Poplar in Pisgah Forest in feet, b. m., Doyle, distinguishing between good, average and poor conditions of growth.

All tables, except Yellow Poplar tables, are based on the measurement of a large number of trees. The Yellow Poplar tables are based on stem analyses of a small number of trees.

B. According to measurement of height and diameter combined.

Page 93. Wisconsin White Pine (height expressed by the number of logs obtainable from merchantable bole) in feet, b. m., Doyle.

Page 103. Adirondack Spruce expressed in feet, b. m., Scribner, the total height of trees being measured.

Page 104. The same in cubic feet.

Page 105. The same in cords for pulp wood.

Page 106. New Hampshire Spruce in feet, b. m., in New Hampshire cubic feet sanctioned by law.

Pages 108 and 111. Adirondack White Pine with bark, expressed in cubic feet.

Page 110. Adirondack White Pine in feet, b. m., Doyle.

Monographic investigation into the growth of the leading American species is of great importance. The trees of virgin forests are very defective, however, and tree tables can never be constructed giving the contents of defective trees.

SECTION III.—VOLUME OF FORESTS.

PARAGRAPH XXXIX.

SYNOPSIS OF METHODS FOR ASCERTAINING THE VOLUME OF FORESTS.

The methods used to find the volumes of entire forests, of forest compartments, tracts, quarter sections, coves, etc., are:

1. Estimating (Par. XL.).
2. Exact calculation after measurements (Par. XLI., f. f.).
3. Combined measuring and estimating (Par. IL., f. f.).

Obviously, measuring without estimation is possible only in forests containing little unsound timber.

PARAGRAPH XL.

ESTIMATION OF FOREST VOLUME.

In primeval woods, where a few assortments only are salable and where stumpage is cheap, the estimation of stumpage necessarily takes the place of the measurement. If any measurements are taken, they are merely meant to back the estimation of the cruiser. The more defective the trees are, the more preferable is judgment and local long experience in the mill and in the woods on the side of the cruiser to mere measuring.

The volume of a wood is ascertained by cruisers' estimates in the following ways:

- a. By estimating the number of trees and the volume of the average tree with due allowance for defects.
- b. By counting the trees and estimating the volume of average trees with allowance for defects.
- c. By estimating the volume of each tree separately, sounding it with an axe, when necessary, and judging its soundness from all sides.

The above methods (*a*, *b*, *c*) are applied either to sample plots or to sample strips or to the entire area.

A blazing hammer is often used to prevent duplication; the revolving numbering hammer might be used in case of scattering trees, so as to allow of control of the estimates by the owner, his forester or the prospective purchaser of stumpage.

In irregular forests—hardwood forests of the United States—the only safe way is separate estimating of each individual tree after careful inspecting. Incredible errors result from wholesale and rapid estimates.

In the case of even aged woods, a look at the height growth and a knowledge of the age gives a good idea of the forest's volume. Under very poor conditions of growth, the annual timber production per acre and year is as little as 15 cubic feet; under the best conditions it is as much as 250 cubic feet per acre and year. On an average (on absolute forest soil), 50 cubic feet per acre and year may be considered as the production of healthy and densely stocked forests.

PARAGRAPH XLI.

PRINCIPLES UNDERLYING THE EXACT MENSURATION OF FOREST VOLUME.

The basis of any exact measurement of volume is formed by a survey of the sectional area, combined with an account of the number of stems; sectional area and number are found by calipering (valuation survey). Whatever rule of log measurement may be at stake, the total sectional area of the forest is always of first importance for a survey of forest volume. Next in importance is the calipering of sample trees, followed by an exact survey of their volume. The ratio *r* existing between the volume of the sample trees (expressed in any unit or mixture of units) and the sectional area of the sample trees is identical with the form height (compare Par. XXXII., towards end) of the sample trees. The form height of sample trees properly selected is the form height of the forest. The sample trees are usually cut and worked up into logs, cordwood, tannin wood, etc., for the purpose of volume survey.

$$\frac{V}{S} = \frac{v}{s} = \frac{f. h. s.}{s} \quad \text{and} \quad V = S. f. h$$

If the trees of the forest are defective, the sample trees should exhibit average defects.

PARAGRAPH XLII.

FIELD WORK FOR EXACT VALUATION SURVEYS.

The valuation survey requires:

1. Calipering of all trees; the diameter is taken in inches or in multiples of inches. Each species and each height class or age class are or may be taken separately.
2. Entering the takings on tally sheets, arranged as follows:

Diameter.	Spruce.		Beech.	
	Height classes.		Height classes.	
	I	II	I	II
10"				
11"				
12"				
13" etc.				

The larger the trees are, the bigger is the permissible interval of calipering. If trees average two feet in diameter, an interval of 3 inches is permissible, provided that a large number of trees are calipered.

It is a strange fact that the diameter measured from east to west is larger on the whole than the diameter from north to south.

PARAGRAPH XLIII.

BASAL ASSUMPTIONS.

The only assumption made in calculating the volume of the forest after Paragraph XLI. is that the form height of the sample trees equals the form height of the forest. No other estimate or assumption is being made. This premise is much safer than the assumption that the volume of the forest bears the same ratio to the volume of the sample trees which the number of trees in the forest bears to the number of the sample trees. More unsafe is the assumption that the volumes of forest and sample trees bear the ratio of the acreage occupied by the forest on the one hand and by the sample trees on the other hand.

PARAGRAPH XLIV.

SELECTION OF SAMPLE TREES.

Sample trees are selected either irregularly or after a regular plan. In the latter case, it is best to distribute them equally among the diameter classes composing the forest (Draudt-Urich method and Robert Hartig method), instead of selecting sample trees of average diameter.

It is more important that the sample trees should have proper average class-form height (and average defects) than that they should have exact average class-diameters.

PARAGRAPH XLV.

DRAUDT-URICH METHOD.

The Draudt-Urich method is in common use abroad for measuring the forest. The trees of the forest are divided into a number of classes (usually five). Each class contains an equal number of trees, class I containing the largest and class 5 the smallest trees. In each class an equal number of sample trees, having about the average diameter of the class, are felled and worked up into logs, cordwood, ties, poles, etc. The form height of all sample trees is obtained as the quotient of their volume (in any unit or mixture of units) divided by their sectional area. Multiplying the sectional area of the forest with this form height, the exact volume of the entire forest and its composition (logs, poles, cords, etc.) are given by one operation.

Sample trees of the average diameter of a class are found by dividing the sectional area of the entire class by the number of trees per class. It is wrong to find the average diameter by dividing the sum total of the diameters by the number of trees.

Diameter Breast High.	Number of Trees.	Diameter Classes of Trees.	Number of Sample Trees.	Average Diam- eter of Sample Trees.
40"	310	I	11	29"
35"	240			
30"	506			
25"	1226			
20"	9	II	11	17"
15"	1040			
	1233	III	11	14"
	1847			
	435	IV	11	10"
10"	2282			
	2282	V	11	10"

The advantages of the Draudt-Urich method are:

1. All sample trees can be worked up in a bunch.
2. Not only the entire volume but as well the different grades of timber, fuel, ties, etc., composing the volume are found by one operation.

A large number of sample trees are, however, required, and, since the volumes of the various classes are unequal, a negative mistake made in establishing the volume of one class is not apt to be counter-balanced by a positive mistake made in finding the volume of another class.

PARAGRAPH XLVI.

ROBERT HARTIG METHOD.

Robert Hartig's method forms tree classes containing equal sectional areas—not equal numbers of trees. An equal number of sample trees is cut in each class and worked up separately for each class. The volume of the forest is also obtained separately for each class. Otherwise, the manner of proceeding is identical with that of Paragraph XLV.

Preferable it would seem to cut in each class a number of sample trees having, in the aggregate, the same sectional area. This scheme, however, would represent the big-diameter class by an absurdly small number of samples.

PARAGRAPH XLVII.

AVERAGE SAMPLE TREE METHOD.

If average trees of the entire forest are taken as samples, then the volume of the forest is obtained with smaller accuracy.

The proportion which the different assortments of timber, wood, bark, etc., form in the entire output is not clearly shown by such sampling.

In a normal, even-aged wood the tree of average cubic volume is found by deducting 40% from the total sectional area, beginning with the deduction at the biggest end. The largest tree then left is, or happens to be, *the* average tree of the wood.

PARAGRAPH XLVIII.

EXACT MENSURATION WITHOUT CUTTING SAMPLE TREES.

Frequently the cutting of sample trees for the purpose of a valuation survey is not feasible. The volume of the forest in cubic feet—but not the assortments composing the volume—may then be ascertained as follows:

a. Take the total sectional area of the forest according to diameters and species and, if necessary, according to height classes.

b. Ascertain the bole volume of some available trees with the help of Pressler's tube or by indirect measurement of heights and diameters.

c. Proceed as indicated in the last three paragraphs, keeping in mind, however, that only the cubic volume of the boles is thus obtainable. The branch-wood-percentage or the timber-percentage of the bole must be estimated.

The Hartig method (Paragraph XLVI.) might be combined with the use of Pressler's telescope, and the bole volume of a wood above breast height might be ascertained as $\frac{2}{3}$ of the total sectional area of the forest, multiplied by the arithmetical mean of the rectified heights of the sample trees representing the various diameter classes.

$$V = \frac{2}{3} \times \frac{S(r_1 + r_2 + r_3 + r_4 + r_5)}{5}$$

The bole volume below breast height in cubic feet is equal to the sectional area of the wood times $4\frac{1}{2}$.

PARAGRAPH XLIX.

COMBINED MEASURING AND ESTIMATING.

If measuring and estimating are combined, the following typical methods may be used to ascertain the volume of woods:

1. The form factor method (Paragraph L.).
2. The form height method (Paragraph LI.).
3. The volume table method (Paragraph LII.).
4. The yield table method (Paragraph LIII.).

These methods might be used in connection with the so-called "distance figure" of Paragraph LIV.

In applying these methods, one or the other of the three factors of volume (sectional area, height and form factor) are obtained by estimation.

The paragraphs following Paragraph LVIII. give a number of methods practically used and also based on combined measuring and estimating.

PARAGRAPH L.

FORM FACTOR METHOD.

The form factor method ascertains the sectional area by calipering, according to species, and, if necessary, according to height classes. The average height of the wood (by species, classes) is obtained by actual hypsometric measurement. The form factor is read from local form factor tables.

The average height is obtained—not as the arithmetic mean of a number of heights measured, but much more—correctly from the ratio existing between the sum total of the ideal cylinders and the sum total of the sectional areas of the trees hypsometrically measured. The form factors appearing in form factor tables must be averages obtained by many hundreds of local measurements.

Mistakes amounting to up to 25% in the sum total of the volume obtained by the form factor method are not impossible, since average form factors appearing from a form factor table are often at variance with the actual form factor.

Form factor tables for American "second growth" are still lacking. In primeval woods the form factor method seems out of place.

PARAGRAPH LI.

FORM HEIGHT METHOD.

The form heights of merchantable trees are, generally speaking, subject to only small variations. Those, *e. g.*, for Adirondack White Pine scaling from 18" to 36" in diameter breast-high are (for standard rule) close to 1.25.

Multiplying the sectional area of a White Pine woodlot (say 100 square feet) by the form height previously obtained through official measurements (like those by T. H. Sherrard), the volume of the woodlot—in the present example about 125 standards—is easily obtained.

Form height tables based on feet b. m., Doyle, are not as simple as those based on the standard rules and cubic foot rules, owing to the mathematical inaccuracy of Doyle's rule, which causes the form heights to be pre-eminently dependent on the diameters.

Form height tables should be constructed for the leading merchantable species in the United States. Of course, such tables are more readily applicable to second growth than to first growth.

The form height tables should exhibit the number of standards, cords, ties, etc., obtainable per square foot of sectional area in each diameter class. In case of defective trees, proper allowance must be made for defects—rather a hazardous risk in primeval hardwoods.

PARAGRAPH LII.

VOLUME TABLE METHOD.

In Paragraph XXXVIII. a number of volume tables have been enumerated, from which the volume of trees of given species and diameter (and height) can be readily read.

A valuation survey of the forest (or of a woodlot or of a sample plot) yields the diameters of the trees stocking thereon. The number of trees found for each diameter class is multiplied by the contents of a tree of that diameter appearing from the volume table. The sum total of the multiples is the sum total of the volume of the forest.

SAMPLE.

Diameter.	Yellow Pine.			Hickory.			Oak.		
	No. trees.	Average volume.	Total volume.	No. trees.	Average volume.	Total volume.	No. trees.	Average volume.	Total volume.
12	30	60	1.800	7	140	980	14	160	1.400
15	42	120	5.040	9	240	2160	5	200	1.000
18	17	300	5.100	18	370	6600	23	350	8.050
21	36	520	18.720	5	500	2500	22	520	11.440
24	33	780	25.740	12	660	7920	22	730	16.060
27	20	1080	21.600	6	840	5040	7	940	6.580
30	10	1420	14.200	3	1050	3150	10	1150	11.500
33	1	1800	1.800				5	1400	7.000
36	1	2200	2.200				5	1800	9.000
Totals.			96.200			28.350			72.030

Grand total.....196.580' B. M.

The volumes of the column "Average Volume" are taken from tables published by the Bureau of Forestry.

PARAGRAPH LIII.

YIELD TABLE METHOD.

All over Europe local yield tables are used to quickly ascertain the volume of pure, sound, even aged woods. For America, such yield tables—normal local yield tables—exist only in the white pine tables given in Pinchot and Graves' pamphlet, "The White Pine."

The method of construction of yield tables appears from Paragraph XCII. and following.

Under yield tables are understood "acre-volume-tables," whilst under volume tables are understood "tree-yield-tables."

Normal yield tables specify the age of even aged and pure woods, the height of such woods and the volume (by assortment) of such woods, according to the productiveness of the soil. An indication for the latter is found in the height growth.

Such yield tables hold good only for woodlots normally stocked. A woodlot is normally stocked "when all local factors of wood production have pronounced themselves unhampered in the annual production of fibre." Normal woods, even of small extent, are extremely rare. In Germany the average wood lacks 25% of being normal. Since the normal yield tables give the yield for normal conditions only, a deduction must be made from the volume indicated by the yield table when applied to a given woodlot, according to the abnormality of the same.

Proceed as follows:

Ascertain age and average height of the trees; find the yield table which gives a similar height for the same age; reduce the volume indicated by this yield table and for this age, by estimating the deficiency of the growing stock.

Obviously, there is much room for guessing, since neither height nor form figure nor sectional area in woodlots abnormally stocked can lay claim to normality.

Schuberg, denying a truism otherwise generally acknowledged, claims that the height alone does not indicate the productiveness of the soil.

At present, normal yield tables are of little use in American forestry.

PARAGRAPH LIV.

DISTANCE FIGURE.

Under "distance figure," an invention of Kœnig's, is understood the quotient a formed by the side l of the average growing space of a tree (considered as a square) and by the diameter of the average stem d .

$$a = \frac{l}{d}$$

The average distance from tree to tree and the average diameter of a number of trees is obtained by a number of measurements in the forest. If the area of the forest is F square feet, then the sectional area of the forest is

$$= \frac{\pi}{4} \times \frac{F}{a^2} \text{ square feet}$$

The actual test proves the fallacy of Kœnig's assumptions. The explanation lies in the fact that the average diameter of a wood is not the arithmetical mean of the diameters composing it. Further, the growing space of a tree is not a square.

The actual growing space per tree can be correctly ascertained by laying a sample strip through the forest, counting at the same time the trees within the strip. The sectional area of the forest is obtainable, however, without greater trouble and with much greater accuracy, from the product calipered sectional area of trees in the sample strip times area of the forest over area of the sample strip.

On an acre of average soil, there is on an average room for the following numbers of healthy trees, according to age:

- At 20 years 1,600 specimens.
- At 50 years 600 specimens.
- At 100 years 240 specimens.
- At 150 years 150 specimens.

PARAGRAPH LV.

ALGON'S UNIVERSAL VOLUME TABLES.

So-called "universal volume tables" have been constructed by H. Algon, a Frenchman. For a description of these tables see "Indian Forester" of July, 1902.

The volumes given for each diameter of trees, whatever the species be, are presented on a number of tables as follows:

Diameter.	Volume in Cubic Feet.				
	Table 1.	Table 5.	Table 10.	Table 15.	Table 20.
6"	2.	3.	4.	6.	8.
9"	5.	8.	10.	16.	18.
12"	9.	15.	21.	27.	33.
15"	19.	28.	39.	50.	61.
18"	27.	39.	59.	69.	84.
21"	43.	60.	83.	109.	128.
24"	54.	78.	108.	138.	168.
27"	72.	107.	147.	188.	228.
30"	87.	129.	177.	228.	276.
33"	111.	163.	221.	288.	349.
36"	129.	189.	258.	333.	405.

The tables are used as follows:

1. Caliper the entire forest according to diameters and species.
2. Measure a number of type trees, selected at random, after felling them.
3. Find that volume table amongst the 20 tables given which best corresponds with the diameters and volumes of the type trees. Apply the volume table, which is found to be the proper one, to all diameter classes calipered in the woods.

Objections to the method are:

- a. The danger of mistakes is very great. In an absolutely even aged wood, one tree of 15 inches diameter may easily show 50% more volume than another tree of the same diameter, the latter being more tapering and shorter.
- b. In an uneven aged wood the tables are necessarily wrong because the form height is a function of age as well as of height and diameter.
- c. The method does not give any idea of the proportion of logs, fuel, bark, etc.

Algon calls these tables "universal" assuming that they hold good for all species of the universe.

PARAGRAPH LVI.

SCHENCK'S GRAPHIC METHOD.

This method, as well, can be used only for sound woods. No calculation is required. The procedure is:

1. Caliper the whole wood.
2. Cut sample or type trees of small, big and average diameters, find the contents of each tree separately, together with the composition of contents as logs, fuel and bark.
3. On a piece of cross section paper, use as many units along a horizontal line as there are trees (or tens or hundreds of trees) calipered.
4. Mark the unit which each sample tree, according to its diameter, would occupy if the biggest tree were placed to the right and the smallest to the left of the horizontal line.
5. Enter over the marked units the volume of the type trees (according to the composing factors, if required) in square units. A square unit might correspond with ten feet board measure, or with 1/100 of a cord, etc.
6. Draw a line joining the ends of the columns, adjusting it by an average curve.
7. Measure the space (in square units) between the curve and the horizontal line with the help of a planimeter; the number of square units giving directly the number of feet Doyle, or of cords, etc.

If there are several assortments of volumes, several curves must be drawn. This method allows of separating the volumes of trees allotted to the several diameter classes. Mathematical errors are, practically, excluded.

PARAGRAPH LVII.

FACTORS GOVERNING THE SELECTION OF A METHOD OF VALUATION SURVEY.

In the case of a valuation survey ("stock taking") in the woods, the following points must be considered:

- a. The degree of exactness required, which depends on the purpose at stake (*e. g.*, scientific investigations, or preparation for logging, or taxation).
- b. The regularity, uniformity and soundness of the growing stock.
- c. The minimum diameter of logs; assortments; marketability of species.
- d. The possibility of cutting sample trees.
- e. The expense permissible.

The question usually arises whether the entire forest or sample plots only must be surveyed. The answer depends on the configuration of the ground, uniformity of the growing stock as to size, age, species and quality of its components; further on the value of stumpage, on the accuracy required, on the available time and on the available funds.

The following *METHODS OF VALUATION SURVEYS* might be distinguished:

I. *Cutting sample trees.*

- a. Sample trees selected for about five diameter classes, each class containing about one-fifth of the number of trees present (Draudt-Urich method).
- b. Sample trees selected for about five diameter classes, each class containing about one-fifth of the sectional area of all trees present (Robert Hartig method).
- c. Sample trees selected as average-diameter-trees of the entire forest (Old Bureau method).
- d. Sample trees selected at random—*e. g.*, from dead and down trees (C. A. S. method—applied in the Balsams; Algon Universal tables; Graphic method).
- e. Stem analysis, together with investigations as to thickness of bark.

II. *Without cutting sample trees.*

- a. Measuring height and diameter and estimating form figure of sample trees.
- b. Measuring rectified heights and diameters.
- c. Measuring merely diameters and estimating form heights.
- d. Photographing sample trees, having a scale—say a stick 6 feet long—on the picture.

III. *With the help of volume tables.*

IV. *With the help of yield tables.*

PARAGRAPH LVIII.

FACTORS INFLUENCING THE SELECTION OF SAMPLE PLOTS.

If sample plots are taken, there must be determined:

- a. The number, situation and distribution of the sample plots.
- b. The absolute and relative size of the sample plots. The Bureau of Forestry prescribes sample plots equalling from 1 to $4\frac{1}{2}\%$ of the forest. The "Forest Reserve Manual" prescribes 5% or more.
- c. The form of the sample plots and the manner by which the size of the sample plot is ascertained.

In Europe an ordinary workman calipers, on an average, 5,000 trees (in maximo 12,000 trees) per day. In Pischah Forest 500 trees is a good day's work for one estimator and one helper.

PARAGRAPH LIX.

SIR DIETRICH BRANDIS' METHOD.

The Brandis method is indicated where the object at stake consists in a rapid survey of the stumpage on large tracts, like the vast Teak and Bamboo forests of upper Burmah.

Traversing existing trails of known length on horseback, the estimator records the diameter of each tree within a given distance (say 200 yards) on either side of the trail.

The widths of the strips traversed multiplied by the length of the trail yields the area of the sample plot. The number of the trees of the various diameters found on the sample strip appears from the records.

PARAGRAPH LX.

PINCHOT-GRAVES METHOD ADOPTED ON DR. WEBB'S ESTATE.

1. Sample acres, measuring 4 x 40 poles, are irregularly laid into swamps, hardwood slopes and spruce slopes. The sum total of the sample acres is 3½% of the total acreage.
2. The length of a sample acre is actually chained off, whilst the width is ascertained (two poles to the left and two poles to the right of the chain) by tape, by pacing and by estimating.
3. The sites of the sample acres are not marked on maps.
4. All trees on the sample acres are calipered; a number of heights are taken on each sample acre; for each sample acre the average diameter, the average height and the number of trees are ascertained.
5. From these averages is deduced, for all sample acres, the average diameter, the average height and the number of trees. All these data, of course, must be given for the various species separately.
6. From volume tables previously constructed the volume of the trees having average height and average diameter is obtained and is multiplied by the average number of trees.
7. This multiplication yields the volume of the average sample acre.

Objections to this method of valuation survey are:

- a. The tree of average diameter has neither average volume nor average height.
- b. The average diameter should be obtained from the fraction "total sectional area over number of trees." It cannot be obtained correctly from the fraction "sum total of diameters over number of trees." Similar objections hold good for average height.
- c. Guessing at the width of a strip, in dense growth, is rather risky.

REMARK: Bulletin 36, page 125, states that volumes are now computed by the Bureau either by averaging the volumes found for the sample acres, thus obtaining the volume of a model acre as

$$\frac{v_1 + v_2 + v_3 + \dots + v_n}{n}$$

(wherein n equals the number of sample acres); or by summing up all trees of each diameter class, by dividing each sum by the number of sample acres, and by thus finding for a model acre the average number of trees for each diameter class. In both cases the volumes for each diameter class are read from volume tables.

Allowance for defects is made according to local experience, all trees being calipered as if they were sound.

PARAGRAPH LXI.

THE GRIDIRONING METHOD.

1. Work with compass (if a topographical map is required, also with barometer or clinometer) and with several tapes or ropes. These ropes are meant to denote the sides of a strip; within the strip the sectional areas are taken with calipers or Biltmore sticks.

2. The tapes move continuously with the caliper men, and there is no stopping. The compass man keeps ahead of the measuring crew. One of the outside "tapers" has the correct length desired for a section. His tape must be run straight. The inner tapes may make snake lines. The tally man uses a fresh tally sheet for each section.

3. All strips lie parallel and are equidistant. The width of the strips depends on the density of growth, smallest diameter calipered, available help and accuracy required.

4. The distance between two parallel strips depends upon accuracy required, width of strip and variety of configurations.

5. Each strip is divided into sections of equal length. The tally sheet gives for each section the diameters (with bark) of the trees in that section; further, remarks on the run and altitudes of ridges and creeks traversed, on roads, settlements, existing surveyor's marks, forest fires, forest pasture, previous lumbering and regeneration. The number of seedlings in a section might be approximately given under the same head.

Advantages of the gridironing method are:

- a. A topographical map is obtained at a slight extra expense. The original survey is controlled and the area of the tract is re-ascertained.
- b. Cruisers are forced to traverse all sorts of country and are not allowed to skip swamps, cliffs, etc.
- c. The proportion of flats, ridges, slopes, swamps, farms, or farm soil, pastures, etc., is found at the same time.
- d. The strips may be used as permanent statistical sample plots, if they start from definite points (corners) and run in definite directions.
- e. The procession of the cruisers is uninterrupted by stops; hence no loss of time.

For a picture of a convenient tally sheet holder see Graves' Handbook, page 123.

The gridironing method has been adopted by the working plan division in a somewhat altered form as follows (Bulletin 36, page 120):

1. Strips are always one chain (66 feet) wide. A section invariably comprises one acre equaling 1 x 10 chains.
2. The measuring tape is trailing in the center of a strip; two caliper men (proceeding one at the left, the other at the right hand of the tape) caliper a belt one-half chain wide, estimating the width at either side of the central tape.
3. The compass man or tally man with the front end of the tape attached to his belt goes ahead and stops at the end of every chain, allowing the calipers to catch up.
4. Thus there are ten stops for every acre; after 10 chains the tally man enters general notes.
5. Heights may be measured by a separate crew.

A crew of four men calipers in merchantable timber 20 to 40 acres per day; in small and merchantable timber from 15 to 25 acres per day; in longleaf pine up to 65 acres per day.

PARAGRAPH LXII.

FOREST RESERVE METHODS.

Roth's Forest Reserve Manual gives three methods of valuation survey, No. 1 and No. 2 being sample-area-methods, and No. 3 an entire-area-method.

1. Sample circles with a radius of 20 yards, the circle containing $\frac{1}{4}$ acre; the radius is estimated, or paced from a central stick. Two sub-methods are permitted, namely:

- a. Count the number of trees of merchantable size; estimate the average tree according to log length, taper and thickness of bark; estimate the percentage of defectiveness (from 10% to 40% after Manual, page 49).

b. Caliper the trees in the circle into two-inch classes; estimate the average tree for each class and allow for defects as before.

In both cases a map must show the site of the sample circles. The circle method is not allowed in scattering timber. At least 5% of the entire area must be sample-circled.

2. Sample strips. Strips should be four rods wide, should run across ridges, should be shown on a map. Otherwise proceed as under 1.

3. The "forty" method is used on surveyed land. It is an entire-area method applied to 40 acres. The sides of a "forty" are 80 x 80 rods, equal to 440 x 440 yards. Prescriptions:

a. Traverse each "forty" on lines about 100 yards apart, thus crossing 4 times.

b. Halt at every 100 yards and estimate the trees within a square of 100 yards surrounding the stopping place.

c. If possible, have a compass man control the length and the direction of your runs.

PARAGRAPH LXIII.

SAMPLE SQUARES.

Sample squares containing about one acre are used in Maine and in Northern New York. The side of a sample square is 14 rods. A cruiser, from the center of the square, under the density of the growth existing in Maine and New York, can overlook a circle of 7 poles radius surrounding him. Hence, as a matter of fact—or rather of theory—he skips the corners of the square, counting only the trees in a circle which has the side of the square for its diameter. The square contains 196 square rods, whereas the circle of 7 poles radius contains 155 square rods. The cruiser estimates the contents of all trees within the "square" from his central standpoint.

PARAGRAPH LXIV.

PISGAH FOREST METHOD OF 1896.

1. The diameters of all trees promising to yield a log are measured in diameter classes of $\frac{1}{2}$ foot interval by a crew of 4 to 5 helpers armed with Biltmore sticks.

The diameters are measured (or often estimated if beyond reach) at the point above which the tree is supposed to be sound.

2. Each tree measured is marked by a blaze. The foreman enters on a tally sheet the species and the diameters called out by the helpers. A special tally sheet is used for each cove.

3. The average contents of the diameter classes are estimated with the help of sample trees selected for each species and each diameter—a very uncertain estimate owing to the unsoundness of the trees.

4. Each cove is numbered or lettered to correspond with the tally sheet on a tree standing at the outlet of the cove.

PARAGRAPH LXV.

PISGAH FOREST METHOD FOR STUMPAGE SALE, BARK SALE AND LUMBERING OPERATIONS.

1. Each tree is approached individually, its diameter measured and its defects, especially its hollowness, examined by "sounding." The diameter measure and the estimated volume are entered on a tally sheet opposite the number of the tree, which is inserted in the stump of the tree by a stroke of the "revolving numbering hammer."

2. One cruiser and one helper tally 400 trees per day.

3. The method allows of ready control by the owner, the forester and the buyer. It is adapted to hardwood forests in a rough mountainous country where the merchantable trees per acre are few; and where no tree is, practically, free from defects. (Compare Graves' Bulletin No. 36, page 115).

PARAGRAPH LXVI.

HENRY GANNETT'S METHOD, ADOPTED FOR THE TWELFTH CENSUS.

1. Base the estimate on the cruising reports obtainable from the local lumber companies and railroad companies.

2. Control the applicability of the estimates to huge tracts by traversing them and by overlooking them from a mountain top.

Mr. Gannett expects that mistakes made in one county will be offset by those made in another.

PARAGRAPH LXVII.

A "FORTY" METHOD USED IN MICHIGAN.

1. A "forty" (a square of 80 x 80 poles) is subdivided into 10 rectangles of 4 acres each, measuring 16 x 40 rods.

2. The cruisers estimates when entering a rectangle. He counts the number of trees on every 4 acres and multiplies the number by the size of the average tree.

3. For each "forty" the cruiser records in a memorandum the factors influencing the logging operations or the timber values, notably the swamps, ridges, forest fires, degree of defectiveness, facilities of transportation.

A central line traversing the "forty" in a north and south direction is sometimes kept by a compassman assisting the cruiser. The outer lines of the "forty" are plain from the official survey marks.

A number of variations of this method exist, according to the custom of local cruisers and according to the predilections of the lumbermen, largely governed by the value of stumpage. Compare Graves' Bulletin 36, page 116.

PARAGRAPH LXVIII.

DR. FERNOW'S "FORTY" METHOD USED AT AXTON.

1. Each "forty" is subdivided into 16 squares of $2\frac{1}{2}$ acres each, the sides of a square being 20 x 20 poles.
2. The head estimator, stepping from the corner of the square 10 poles east (or west) and 10 poles north (or south) places himself in the center of the square.
3. Helpers (students) are sent out, four in number, towards the north-east, north-west, south-east and south-west, each helper reporting the diameter and species of the trees found in that one-quarter of the $2\frac{1}{2}$ acres which is allotted to him.
4. The "forties" are carefully surveyed and surrounded by carefully trimmed lines. The outlines of the $2\frac{1}{2}$ acre sections are merely paced.

CHAPTER II.—AGE

PARAGRAPH LXIX.

AGE OF TREES CUT DOWN.

The age of trees cut down is found by counting the annual rings on a cross section (preferably an oblique cut) made as low above the ground as possible. Allowance must be made for the "stump years," by which is understood the number of years required by the top bud of the seedling, after sprouting, to reach the stump height ("cutting height," after Circular 445).

Ring-counting in the case of even-porous hardwoods requires the use of a lens and of some coloring liquid (aniline and ferro-chloride) on a disc planed with a knife, a chisel or a hollow planer.

The difference of the ring-numbers on the stump and the ring-numbers at any place higher up indicates the number of years used by the top bud of the tree to traverse the intervening distance. Endogenous trees do not form any rings.

False rings are formed under the influence of late frost, early frost, drought, fire and insect pests. They do not run all around the tree.

As long as the tree lives, it must annually form a ring of growth (or rather an additional coat, the sleeves of which cover the branches), the outside of which becomes a layer of bark, the inside of which is a layer of wood. In tropical countries this rule does not hold good provided that there is no change of season.

The formation of rings in the branches is regular. Branch-rings are, however, eccentric and elliptical. The formation of rings in the roots is said to be irregular, not representing the age of the root, possibly because there is no or little change of seasons in the soil.

PARAGRAPH LXX.

AGE OF STANDING TREES.

The age of standing trees can be estimated only when regular annual whorls of branches can be counted.

The records of seed years and the history of the forest kept by many forest administrations usually give an idea of the age of the trees.

PARAGRAPH LXXI.

AGE OF A FOREST.

The age of a forest is the average age of the trees composing it.

In the case of a thicket suppressed for a long time by the superstructure of a leaf canopy overhead, a so-called "economic age" is frequently substituted for the actual age. In the case of Adirondack spruce, for example, a diameter of 1 inch in the center of the trunk had better be counted, as, say, 15 years, although it may contain as many as 60 rings.

The mean age of an uneven-aged wood is defined as follows:

1. That number of years which an even-aged wood would require on the same soil, in order to produce the same volume as is now at hand.
2. That number of years which an even-aged wood would require in order to produce at the time of maturity the same volume which the uneven-aged wood is likely to produce.

The latter definition is scientifically more correct. Unless it is adopted, an uneven-aged wood may get over 20 years older in 20 years, owing to the fact that the trees dying in the meantime are mostly minors in age.

CHAPTER III.—INCREMENT

SECTION I.—INCREMENT OF A TREE.

PARAGRAPH LXXII.

THE KINDS OF INCREMENT.

The following kinds of increment must be distinguished:

- a.* Increment of height, diameter, sectional area and volume.
- b.* Current annual increment, current periodic increment and total increment.
- c.* Average annual increment, average periodic increment and average increment at the age of maturity.
- d.* Increment of the past and increment of the future.
- e.* Absolute increment and relative increment.

The increment of stems cut down is found by counting and measuring the annual rings on several cross sections.

The term "stem" or "tree analysis" designates an investigation into the past height growth, diameter growth and volume growth of a tree.

Circular 445 of the Bureau of Forestry defines the term "increment," somewhat narrowly, as follows: "The volume of wood produced by the growth in height and diameter of a tree or of a stand."

For definition of the term "tree analysis," see Circular 445 of Bureau of Forestry.

This circular distinguishes between:

1. Stump-analysis, being a tree analysis which includes measurements of the diameter growth at given periods on the stump only, no matter what other measurements it may comprise;
2. Section-analysis, being a tree analysis which includes measurements of the diameter growth at given periods upon more than one section of a tree;
3. Partial tree (stump or section) analysis, wherein the measurement of the diameter growth at given periods covers a portion only of the total diameter growth.

PARAGRAPH LXXIII.

HEIGHT INCREMENT.

The height increment, from the silvicultural standpoint, is of interest to the forester dealing with mixed woods.

The difference between the number of rings found on two separate cross sections through the bole indicates the number of years which the tree

has required to grow through the distance lying between these two sections. By counting the number of rings at several cross sections, one of which is made as close to the ground as possible, the current and the average height growth (increment) may be obtained by arithmetical or by graphical interpolation.

A dense cover favors height increment. In rare instances, however, the stand of saplings or poles is so close that the height increment of the individual suffers from lack of food.

PARAGRAPH LXXIV.

THE CURRENT HEIGHT INCREMENT.

In the high forest the current annual height increment reaches a maximum at an early age; passing this maximum, it sinks more or less rapidly. The culmination of the current annual height increment occurs the much earlier and its slackening after said culmination goes on at a more rapid rate if

1. the species is fast growing and light demanding;
2. the tree observed belongs to the dominant class;
3. the soil is good.

For yellow pine the culmination of the current annual height increment occurs amongst dominant saplings between the 10th and 15th years; for spruce at about the 20th year; for beech and fir between the 25th and 30th years. Suppressed trees show the maximum of current height growth much later than dominant trees.

As a general rule for all species, in case of dominant trees, the longest shoot is made 10 to 15 feet above ground. Slow growing species, shade bearers and trees stocking on poor soil reach that level at a later date than trees and species growing under reversed conditions.

In the case of coppice forest, the maximum of the current height growth lies in the first three years of the life of the shoot. For oak coppice, the following table may serve as an illustration of height growth:

GROWTH IN FEET.

Age in years.....	10	20	30	40	50
Actual height	13'	23'	30'	37'	43'
Current annual increment.....	1.3'	1.0'	0.7'	0.65'	0.63'

PARAGRAPH LXXV.

THE AVERAGE HEIGHT INCREMENT.

The average annual height increment culminates later than the current annual height increment, and, after the culmination, it decreases at a less

rapid rate than the current annual height increment. The average annual height increment culminates at the very age at which it is equal to the current annual height increment.

As long as the average increment increases the current increment is larger than the average. The average increment still rises during a period of decrease of current increment.

These laws hold good not only for height growth, but also for the growth of diameter, sectional area and volume. They are based merely on mathematical principles and are, for that reason, independent of species, climate and soil.

If "a" denotes the current annual increment, and if "d" denotes the average annual increment, whilst the indices 1, 2, 3, etc. (up to n), indicate the year of increment, then the following five equations hold good:

$$\begin{aligned} n \times d_n &= a_1 + a_2 + a_3 \dots\dots + a_n \\ (n+1) d_{n+1} &= a_1 + a_2 + a_3 \dots\dots a_n + a_{n+1} \\ (n+1) d_{n+1} &= n \times d_n + a_{n+1} \\ n \times d_{n+1} &= n \times d_n + a_{n+1} - d_{n+1} \\ n (d_{n+1} - d_n) &= a_{n+1} - d_{n+1} \end{aligned}$$

PARAGRAPH LXXVI.

RELATIVE INCREMENT OF THE HEIGHT.

The percentage of height increment forms, from the start on, an irregularly descending progression.

If the height is h at the beginning of a period of n years of observation and H at the end of that period, then

$$\begin{aligned} h \times 1.01^n &\text{ equals } H \\ \text{and} \\ p &\text{ equals } 100 \sqrt[n]{\frac{H}{h}} - 100 \end{aligned}$$

Pressler substitutes for this formula in case of short periods of observation the following:

$$p = \frac{200}{n} \times \frac{H - h}{H + h}$$

This formula is derived as follows: Imagine that we are in the midst of the period of n years. At that time, the increment is apt to be $\frac{H - h}{n}$, whilst the height at that time is apt to be $\frac{H + h}{2}$; hence, for that middle year, the equation is:

$$\frac{p}{100} = \frac{H - h}{n} \times \frac{2}{H + h}$$

PARAGRAPH LXXVII.

DIAMETER INCREMENT.

The current diameter increment is obtained by counting and measuring the rings on a disk through the tree. It is generally best to count from the bark towards the center, along two radii standing perpendicular to each other.

The general laws of diameter growth are identical with those of height growth relative to culmination, decrease and increase of absolute (Paragraph LXXV.) as well as of relative (Paragraph LXXVI.) increment.

If we exclude the butt-piece below chest-height, the annual rings along the tree bole measured at various elevations above ground show a gradual increase of width with elevation, provided that the leaf canopy of the forest is complete and uninterrupted—*e. g.*, the width of the ring 50 feet from the ground, formed in 1903, is greater than the width of the ring formed 20 feet above ground in the same year.

For trees standing in open crown-density, the width of the ring decreases with the elevation above the ground, especially within the crown itself.

A tree standing in a thin crown-density may show an even width of ring all over the tree bole.

For very old trees in closed stand it is sometimes found that the diameter, say 40 feet above ground, is larger than the diameter, say, 20 feet above ground.

The rings on a disk are not actually circles; they more closely approach the form of eccentric ellipses (see Paragraph XIII.).

PARAGRAPH LXXVIII.

SECTIONAL AREA INCREMENT.

The increment of the sectional area is obtained from the increment of the diameters. Where greater exactness is required, and especially in case of irregular rings, the planimeter or the weight of a piece of paper having the form of the sectional area may be used for measuring to good advantage (Paragraph XIII.).

The increment of the sectional area at chest height depends on the crown density overhead; further, on the quality of the soil. At chest height the culmination of the current annual sectional area increment takes place, in the case of dominant trees, fast growing species and complete cover overhead, between the years 40 and 70.

The culmination of the current annual sectional area increment occurs always later than the culmination of the current height and diameter increment. After culmination it remains uniform for a long time.

The absolute increment of a sectional area higher up on the bole, compared with the absolute increment at chest height, is found to be equal to it in the case of dominant trees; larger in the case of suppressed trees; and smaller in the case of isolated trees.

Pressler establishes as the "law of bole formation" the following rule: "The absolute increment of the sectional area at any point of a bole is directly proportioned to the leaf surface above that point."

This rule is, on the whole, correct. An unexpected swelling, however, is often found at 9/16 of the height of the tree. Within the crown of the tree, the decrease of sectional area increment is rapid.

PARAGRAPH LXXIX.

RELATIVE INCREMENT OF DIAMETER AND OF SECTIONAL AREA.

The increment percentage at any point of the bole, like all increment percentages, forms a constantly but irregularly descending progression.

At any point of the bole the increment percentage of the sectional area is the double of the increment percentage of the diameter.

Schneider gives a handy formula for the sectional area increment percentage, viz.:

$$P \text{ equals } \frac{400}{nd}$$

wherein d represents the diameter at the beginning of the period of observation, and wherein n indicates the number of rings per inch at the time of observation.

The percentage of the sectional area increment increase along the bole with increasing height of the disk measured, excepting, however, possibly, the case of very isolated trees.

The average sectional area increment percentage of the bole is found at a point a little below one-half of the total height, namely, at about 0.45 of the total height from ground.

PARAGRAPH LXXX.

VOLUME INCREMENT.

The (current and future) volume increment of standing trees is of great interest to forest financiers; it can be estimated only, and cannot be measured exactly.

The volume increment of trees cut down may be ascertained as follows:

1. By the sectional method, or by "section analysis" (Paragraph LXXXI.).

2. From the increment of sectional area chest high, height increment and form figures (Paragraph LXXXIV.).

3. From the increment of sectional area in the midst of bole (Paragraph LXXXV.).

4. On the basis of the average annual increment (Paragraph LXXXVII., last 4 lines).

PARAGRAPH LXXXI.

SECTION ANALYSIS.

The section-method is a complete tree analysis by sections. The entire bole is divided into a number of sections, preferably of even length, at both ends, or, better, in the midst of which the periodical increment of the sectional area is ascertained (compare Paragraph XI.).

In the latter case, multiplying such sectional areas (in square feet) as belong to the same age of the tree by the length (in feet) of the sections, the volumes (in cubic feet) of the different sections at given ages are obtained.

The "top pieces," however, must be figured out separately, their length differing from the even length of the sections. These top pieces are usually considered as cones, and their volumes are ascertained as one-third height times basal area of top piece. The basal area of the top piece is identical with the upper area of the uppermost full section of a given age.

EXAMPLE FOR HUBER-SECTIONS TEN FEET LONG.

Total height.....	25 feet.	40 feet.	67 feet.
Total age.....	20 years.	40 years.	60 years.
Sectional area of Section 1.....	0.34 sq. ft.	0.78 sq. ft.	1.23 sq. ft.
Sectional area of Section 2.....	0.15 sq. ft.	0.45 sq. ft.	0.87 sq. ft.
Sectional area of Section 3.....		0.25 sq. ft.	0.64 sq. ft.
Sectional area of Section 4.....		0.03 sq. ft.	0.53 sq. ft.
Sectional area of Section 5.....			0.25 sq. ft.
Sectional area of Section 6.....			0.04 sq. ft.
Summary of sectional areas.....	0.49 sq. ft.	1.51 sq. ft.	3.56 sq. ft.
Summary sectional areas x 10.....	4.90 cu. ft.	15.10 cu. ft.	35.60 cu. ft.
Volume of top piece.....	0.05 cu. ft.	0.09 cu. ft.	0.08 cu. ft.
Total volume.....	4.95 cu. ft.	15.19 cu. ft.	35.68 cu. ft.

The volume of the top pieces forms in the older age columns an insignificant part of the total volume.

If the logs as cut in the woods are used as sections, then each section has a separate length and its volume must be separately ascertained for every decade of age of tree.

REMARK: It is wise to first ascertain the full age of the tree, allowing for stump years. It is further wise to throw off that number of years which exceeds full decades—*e. g.*, in case of a tree 117 years old, 7 years.

At the stump the rings had best be counted from the inside out, allowing for stump years. Instance: Age of tree, 117; stump years, 4 years; counting on the stump, from the inside, 6 rings establishes the ring formed in the year 10. Continuing, the rings of the years 20, 30, 40, 50, etc., up to year 110, are pencil marked. The outside seven rings are thrown off.

At all other disk-sections, count and measure from the outside in, after discarding the 7 years exceeding full decades of tree life.

PARAGRAPH LXXXII.

NOERDLINGER'S PAPER WEIGHT METHOD.

The total length of the tree is divided into 8 Huber sections, and cuts are made in the midst of these sections, at the height of $1/16$, $3/16$, $5/16$, $7/16$ and up to $15/16$ of the bole. On each cross section the radii are measured, not with the rule, but with dividers.

On a piece of paper folded 4 times and thus divided into 8 sectors the measurements are entered with the help of the dividers, one sector being allotted to the first cross section, the next sector to the next cross section, etc. Multiplying the total weight of the zone indicating, say, the year 70, by height of the tree and dividing the product by the weight of a square foot of paper, the volume of the tree when 70 years old is directly obtained in cubic feet. Similarly the zones corresponding with the year 50, 60, etc., are cut out, weighed and multiplied.

If the volume increment percentage p alone is to be obtained, then it is enough to divide, say, the "weight" of the year 70 by the weight of the year 60, and the 10th root of the quotient will equal 1.0*p*.

PARAGRAPH LXXXIII.

SCHENCK'S GRAPHIC TREE ANALYSIS.

Graphic tree analysis offers the following advantages:

1. Mistakes are impossible, being at once noticeable on the diagram paper.
2. The volume in feet Doyle can be readily obtained for any stated minimum diameter.
3. The graphical sketch is adaptable to any of the 43 scales in use in the United States, as well as to the metric system.
4. The thickness of heart wood and sap wood and bark readily appears.
5. It is immaterial whether measurements are taken in meters or in feet, the graphical sketch readily allowing of transfers into other units.
6. Height growth and diameter growth appear at the same time, and from the same entries.
7. The length of the sections taken need not be uniform.

The method of proceeding is as follows: On millimeter paper a system of co-ordinates is established; heights are entered as ordinates, diameters

or radii as abscissas. The scale for the height entries should be much smaller than that of the diameter entries.

Diameter points, at the different section-heights, corresponding to a given decade of years are joined (beginning at the outside), by which procedure the outline of the tree at that decade is established.

Th top cones are obtained by prolonging such outlines arbitrarily until they intersect with the height-axis.

The merchantable bole for each decade is dissected, on the diagram, into logs the length and diameter of which are measured on the diagram.

PARAGRAPH LXXXIV.

WAGENER'S METHOD AND STUMP ANALYSIS.

Wagener recommends a partial stem analysis for cases in which a knowledge of the absolute increment, not a knowledge of the absolute tree volume, is required. Tree volume is sectional area chest high times height of tree times form factor.

Wagener analyses:

- a. the height growth by counting the rings at various altitudes along the bole;
- b. the growth of the sectional area at chest height by measurement in decades in the usual way.

Wagener then estimates the form factor according to form factor tables.

In the latter proposition, obviously, lies the danger of mistakes. Since, however, increment is a difference of volumes, merely the difference of mistakes—a comparatively small item—enters into the problem.

Age in years.....	60	80	100	120
Diameter b. h.....	14.	17.	19.	21.
Sectional area b. h.....	0.25	0.35	0.50	0.71
Height in feet.....	75.	85.	93.	105.
Form factor.....	0.50	0.50	0.50	0.50
Volume in cubic feet.....	9.4	13.	23.	36.
Increment in cubic feet.....	3.6	10.	13.	

The "stump analysis" (compare Paragraph LXXII.) introduced by the Bureau of Forestry rests on premises similar to those proffered by Wagener.

If the form height for the stump-diameters (or the number of feet b. m. per square foot of stump area for given stump diameters) is known, the rate of volume increment can be quickly ascertained by mere stump analysis.

It is, however, a well known fact that the diameter growth at the stump—especially at a low stump—is particularly unreliable as an index of volume growth, owing to the exaggerating influence on stump growth exercised by light, by water, by depth of soil and by superficial roots.

Stump analysis as a means to bring a volume in reference to a sectional area at the stump is permissible only as a necessary evil.

PARAGRAPH LXXXV.

PRESSLER'S METHOD.

Frequently the task before the forester is merely that of ascertaining the increase of bole volume during the last 10 or 20 years. Then after Pressler, one single investigation into the growth of the sectional area is sufficient when made with the help of the accretion borer in the midst of the "decapitated" bole. The volume increment in cubic feet equals the sectional area increment in question multiplied by the height of the tree.

The bole is decapitated by that number of top shoots which have been formed during the period of observation. This operation corresponds very well with the usual practice of judging the bole increment percentage from the sectional area increment ascertained at 0.45 of height of tree.

Pressler measures the sectional area at the end of the period of observation too large, measuring it at too low a point. He multiplies this sectional area, however, by too small a height—namely, the decapitated height; thus a mistake made in the positive sense is apt to be eliminated by a mistake made in the negative sense.

The axe can be used to better advantage frequently than the accretion borer.

PARAGRAPH LXXXVI.

BREYMANN'S METHOD.

Breymann gives the following formula:

1. For the current annual volume increment T:

$$T = V \left(2 \frac{\delta}{d} + \frac{\lambda}{l} \right)$$

wherein "δ" and "λ" denote the annual increase of diameter "d" and length "l" respectively.

2. For the corresponding increment percentage P:

$$P = 100 \left(2 \frac{\delta}{d} + \frac{\lambda}{l} \right)$$

It appears that for trees of old age and hence of little height growth the increment percentage is merely dependent on the diameter increase.

Breymann, however, neglects:

1. The change of form figure, during the period of observation;
2. A number of small factors which ought to be embraced in the formula.

For stopping height growth or for $\lambda=0$, the term given for P can be easily reduced to the term given by Schneider for the sectional area increment percentage.

PARAGRAPH LXXXVII.

FACTORS INFLUENCING THE CUBIC VOLUME INCREMENT.

The culmination of the current annual volume increment takes place at a later year than the culmination of the sectional area increment at breast height. Naturally so, because with increasing age of a tree, its root system as well as the branch system, the feeders of the body, show continuous increase.

Big and long branches, of course, require a great deal of wood fibre to increase and maintain their own strength, like levers increased in length. Hence, from a certain size of branch on, all wood fibre produced by the branch is used up within the branch itself, for its own purposes, instead of being added as increment to the merchantable bole.

After Dr. Metzger, the crown of a tree yields the maximum of bole increment if its crown diameter is, and if the number of trees per acre are:

Quality of soil.	Diameter of crown, in feet.	No. of trees per acre.
Very good.	16.5	203
Good	14.7	256
Medium	12.7	343
Poor	9.3	640
Very poor	8.3	807

From the theoretical standpoint it seems wise, consequently, to force the lower branches of a tree to die, with the help of proper tension and friction within the leaf canopy, when they exceed a length of 8.25, 7.35, 6.35, 4.65 and 4.15 feet respectively (the halves of the diameters).

Metzger's investigations are interesting, but his conclusions seem to be too sweeping.

P. P. Pelton recommends the lopping of branches in order to shorten the length of the branch-levers.

The average annual volume increment of dominant and sound trees

culminates at a very high age only, if ever, owing to the late culmination of the current annual average increment.

The volume increment percentage forms—as in all cases of increment—a steadily but irregularly decreasing progression. This percentage is invariably equal to or higher than the sectional area increment percentage at chest height.

Roughly speaking, the volume increment percentage amounts to from 1 to 1.75 times the sectional area (at chest height) increment percentage, or, as Pressler gives it, to from 2 to $3\frac{1}{2}$ times the diameter (at chest height) increment percentage.

Crown covers part of bole	Height Growth.			
	Seemingly nil.	Medium.	Good.	Excellent.
$\frac{1}{2}$ or more.	2.33	2.67	3.00	3.17
$\frac{1}{2}$ to $\frac{1}{4}$.	2.50	2.83	3.17	3.33
Less than $\frac{1}{4}$.	2.67	3.00	3.33	

Since the average volume increment of a tree is equal or closely equal to the current annual increment at a high age only, it is usually not permissible to substitute the average increment, which is easily ascertained, for the current annual increment.

PARAGRAPH LXXXVIII.

VOLUME-INCREMENT PERCENTAGE OF STANDING TREES.

In the case of standing trees the volume increment percentage cannot be measured, owing to the impossibility of ascertaining a change of form height.

The Pressler data given in the preceding paragraph allow of estimating the volume increment percentage of standing trees on the basis of a diameter-increase, measured at breast height.

The Pressler "accretion borer" is used for the purpose, or an axe.

Stoetzer, Director of the Forest Academy at Eisenach, modifies the Schneider formula for sectional area percentage, writing it

$$p = \frac{C}{nd}$$

wherein n indicates number of years (rings) required to form one inch; d represents the diameter at the beginning of the period of investigation, whilst C (the so-called "constant factor of increment," which is not a constant factor at all) must be ascertained for a given species, soil, diameter, age and position by actual tests on felled trees.

In old dense beech woods C is, e. g., 540. After a seed cutting in the same woods during the final stage of regeneration C is only 450 (observation by Dr. Wimmenauer).

Trees growing as cones would grow, have C equal to 600; trees growing as Apollonian paraboloids would grow, have C equal to 800; after Stoetzer, C might amount to as much as 930, in case of suppressed trees. The minimum possible (in sound trees) for C is 400.

The Pressler values given in the table of the preceding paragraph closely correspond with the constant factors of increment ascertained after Stoetzer. In the case of the Pressler table (at end of Paragraph LXXXVII.) we find, for medium height growth and very small crown, a factor 3.00 by which the diameter increment percentage is to be multiplied. This factor 3.00 corresponds with 600 for a constant factor of increment.

If the diameter in the midst of the bole is $\frac{1}{2}$ of the diameter at the end, then the tree, it seems, is conical, and an increment factor of 600 might be assumed. If the sectional area in the midst of the bole equals $\frac{1}{2}$ the sectional area at the end, then the tree is a paraboloid, and the increment factor seems apt to be 800.

It must be remembered, however, that a tree forming a paraboloid grows as a paraboloid only, if its percentage of height growth is equal to its percentage of growth of sectional area—a rare case in merchantable trees.

Similarly, a tree growing as a cone must have the height increment percentage equal to its diameter increment percentage.

If n and ν represent the number of rings per inch added to original diameters d and δ at chest height and at 0.45 of the height of the tree respectively, then the "constant factor of increment C " is found as follows:

$$p \text{ (volume)} = \frac{400}{\nu \delta} = \frac{C}{nd}$$

$$C = 400 \frac{nd}{\nu \delta}$$

PARAGRAPH LXXXIX.

INTERDEPENDENCE BETWEEN CUBIC INCREMENT AND INCREMENT IN FEET B. M. DOYLE.

Doyle's rule under-estimates the contents of small logs and over-estimates those of big logs.

Consequently, the growth of a tree bole in feet b. m. Doyle is (for small trees yielding logs under 28" diameter) relatively faster than the growth of a tree bole expressed in cubic feet. The figures of Column D denote, in the following table, this excess rate of growth:

A Diameter of logs without bark.	B No. of ft. b. m. per one cu. ft. of tim- ber estimated after Doyle.	C Differences of con- secutive figures in Column B.	D "Extraordinary" percentage of incre- ment Doyle co-in- ciding with 1" growth.
12"	5.09		8.1
13"	5.50	0.41	6.4
14"	5.85	0.35	5.7
15"	6.18	0.33	4.2
16"	6.44	0.26	4.3
17"	6.71	0.27	3.3
18"	6.93	0.22	2.1
19"	7.07	0.14	3.2
20"	7.33	0.26	2.5
21"	7.51	0.18	2.2
22"	7.67	0.16	2.0
23"	7.82	0.15	1.7
24"	7.95	0.13	1.8
25"	8.09	0.14	1.4
26"	8.20	0.11	1.5
27"	8.33	0.12	1.1
28"	8.41	0.09	1.1
29"	8.52	0.11	1.0
30"	8.60	0.08	...

For the standard rules, the increment percentage of a tree can be ascertained by cubic measure as well as by standard measure.

If n years are required to form one additional inch of diameter, then the extraordinary percentage of Doyle-increments amounts annually to $\sqrt[n]{1.0D}$, wherein D represents the values of Column D in the foregoing table.

By this factor $\sqrt[n]{1.0D}$, the cubic volume increment percentage of a bole may be converted, *ceteris paribus*, into Doyle increment percentage, provided that

1. The cubic increment percentage of the total bole coincides with the cubic increment percentage of the merchantable bole;
2. The merchantable bole does not increase in length during the period of observation.

PARAGRAPH XC.

CONSTRUCTION OF VOLUME TABLES.

Volume tables are "tree yield tables" from which the volume of a tree of given species, given age, given diameter breast high or stump high, given height, given merchantable bole, given position (suppressed, dominant, etc., or isolated, crowded, etc.), given locality and so on can be readily read. The units of volume are cubic feet, board feet, standards, cords, etc., according to the requirements of the case.

Obviously, volume tables give, or should give, the volumes of average trees; they may give, in addition, the maximum and minimum volume possible in a tree of stated description.

Volume tables are constructed either on the basis of hundreds (thousands) of measurements taken from trees actually felled in the woods (possibly also sawn at a saw mill, to ascertain the grades) or on the basis of a smaller number of complete section analyses.

The rapidity of volume growth of a species and the development of its form height depend on many local factors—notably on climate, soil, silvicultural systems at hand, influence of fires, fungi, insects, etc.

Owing to the multitude of local factors influencing the volumes and the changes of volumes, local volume tables alone are entitled to a place in exact mensuration.

Volume tables for second growth are more reliable than volume tables for first growth.

Circular 445 of Bureau of Forestry defines volume table as "a tabular statement of the volume of trees in board feet or other units upon the basis of their diameter breast high, their diameter breast high *and* height, their age, or their age *and* height."

The method of construction of volume tables is either mathematical or graphical.

1. *Mathematical method.*

The volumes ascertained for trees of a given diameter (breast high or stump high with or without bark), a given merchantable length or total length, a given age or a given quality or locality are added up.

The sum total of these volumes divided by the number of trees forming it yields the average volume of the tree of stated description.

These averages are shown, for the various diameters, lengths, ages and localities, in tabular form.

The volumes corresponding with such diameters, lengths, ages and localities, for which sample trees were not cut and measured, are found by arithmetic interpolation.

Finally, the differences in volume shown by average trees of similar description (*i. e.*, differing but slightly in diameter, length, etc.) are formed and rounded off in a manner causing the volumes to show a more steady mathematic progression.

2. Graphic method.

The volume of each tree measured is entered as the abscissa on a diagram-system of co-ordinates, whilst the diameters of the trees (or the age, etc.) are registered on the ordinate axis. Similarity of length is indicated by color of mark representing the tree; similarity of locality is indicated by the form of the mark (square, triangle, cross, circle, etc.).

Corresponding marks are then joined by chains (having square, circular, triangular links) of the proper color.

Finally, average curves as well as maximum and minimum curves are drawn for the various colors and forms of marks.

Maximum and minimum curves should not represent the very best and the very worst possibilities; they should represent the average of very good and very bad trees.

The graphic method is more reliable, because less depending on mere figures, than the mathematical method. Both methods are frequently combined.

A number of complete tree analyses furnishes more reliable results than a large number of mere volume measurements because it yields more reliable curves (guide-curves) of development for one and the same locality, and because it prevents the forester from drawing curves of growth at random.

If the sample trees (or sample logs) are sawn up at a saw mill where the lumber is properly graded according to the inspection rules prevailing for the species in question, the volume tables may also give the actual average output of specified trees in lumber of the various grades.

SECTION II.—INCREMENT OF A WOOD.

PARAGRAPH XCI.

INCREMENT OF FORESTS.

The volume increment of the virgin forest is on the whole nil.

In America the value increment of a primeval forest is based more on a price increment of stumpage than on a volume increment of trees. The volume increment, in addition, can scarcely be ascertained with sufficient accuracy for a given piece of forest at a reasonable expense.

In second growth forests, on the other hand, say in Virginia, an absolute knowledge of the productiveness of the forest renders forestal investments safer in the eyes of the owner; and the safety of the investment it is which alone can tempt the capitalist to invest in forestry. A knowledge of

the increment in second growth woodlands can be obtained from tabulated statements ("yield tables") showing the rate of growth for woodlands of a given species in a given locality. Under normal yield tables are understood such tables which give the rate of growth for even-aged, pure, normally stocked, well thinned woodlots for given localities (compare Paragraph LIII. and XCIV..).

Such normal yield tables are constructed abroad for beech, pine, spruce, fir and oak. In this country they exist only in Pinchot's and Graves' yield tables for white pine. In America, pure even-aged woods are found in rare cases only (taeda, echinata, rigida, jack and longleaf pines, tamarack, coppicewood).

In the construction of normal yield tables the following points require consideration:

1. The different methods of construction (Paragraph XCII.).
2. The combination, interpolation, adjustment and correction of the results (Paragraph XCIII.).
3. The contents and use of yield tables (Paragraph XCIV.).

PARAGRAPH XCII.

METHODS OF CONSTRUCTION OF NORMAL YIELD TABLES.

Normal yield tables may be based on:

A. Repeated survey of some typical woodlots during their entire lifetime.

B. Repeated survey of different woods standing on an equal quality of soil, during a period of years equal at least to the longest difference in age found amongst them.

C. One-time, simultaneous survey of a very large number of woods of different ages standing on different qualities of soil. Missing links are here obtained by graphic or mathematical interpolation (Paragraph XCIII.).

If tables are constructed by repeated survey of several woods (B), it is often found that the links cross one another for unexplainable reasons.

PARAGRAPH XCIII.

GATHERING DATA FOR NORMAL YIELD TABLES.

In order to see whether or not two woods, in the case C of the preceding paragraph, belong to the same chain of growth, two methods are in use:

- a. The horn or curve method, after Baur.
- b. The stem analysis method.

Remarks on *a*:

The contents and age of all woods (normal) surveyed are plotted in a diagram, the age forming the abscissa and the volume the ordinate of the system.

Curves are then drawn outlining the maxima and minima of growth observed.

The horn-shaped space between these curves is divided into a number of sectors equal to the number of yield classes to be distinguished. The middle line of each sector illustrates the productiveness of its class.

The average height growth is obtained in a similar way, the height data forming the ordinates in a system of co-ordinates.

Baur finds that the allotment of a given plot to a volume-sector corresponds with its allotment to a height sector. In other words, the height is, after Baur, an absolutely reliable indicator of the quality of the soil, or, what is the same, of the yield class.

The growth of sectional area, height and volume being known, the development of the form factors for the various sectors is readily obtained from the fraction $\frac{v}{s \times h}$.

Remarks on *b*:

An analysis of the average stems in lots surveyed would not throw any light on their connection as members of one and the same chain of observation. After Robert Hartig, the 200 strongest trees are analyzed. After Wagener, the ideal cylinders merely of these 200 strongest stems are analyzed by ascertaining their height growth and their diameter growth at breast height. Weise and Schwappach are satisfied with an analysis of the heights merely of the 200 best stems.

The selection of sample plots is not easy, even in second growth raised under forestal care. A valuation survey establishes for each plot the number of stems and the sectional area for each diameter class of stems (usually divided into 5 classes); further, the average age and the average height of the plot. The volume is then figured out, usually, according to the Draudt-Urich method.

The experiment stations maintained by the European Governments control the growth of a large number of experimental plots, which should not be smaller than $\frac{1}{2}$ acre each.

The sample plots are corner marked, and, more recently, the individual trees contained therein are numbered consecutively. Surveys of these plots are made every five years. The point of measurement is indicated by a chalk line.

In America normal sample plots have not been established as yet by the Bureau of Forestry in second growth. The sample plots at Biltmore do not represent a normal second growth.

PARAGRAPH XCIV.

NORMAL YIELD TABLES, THEIR PURPOSES AND CONTENTS ABROAD.

Normal yield tables are especially used for the following purposes:

1. To ascertain the quality of the soil (*e. g.*, for taxation).
2. To ascertain the volume of the growing stock.
3. To ascertain future yields of the forest.
4. To solve problems of forest finance, especially those of forest maturity (length of rotation).

German normal yield tables have the following contents:

A. Tables for the main forest—the secondary forest comprising such trees on the same lot as are about to be removed by way of thinning:

- (1) Age, graded at five year intervals.
- (2) Number of trees.
- (3) Sectional area at chest height, inclusive of bark.
- (4) Average diameter.
- (5) Average height and height increment.
- (6) Volume in cubic measure arranged according to assortments as logs, fuel, bark, etc.
- (7) Periodical and average annual volume increment.
- (8) Increment percentage.
- (9) Form factor.
- (10) Normal growing stock.

B. Tables for the secondary forest, giving merely its volume, which, as stated, is to be removed by way of thinning.

Circular 445 of the Bureau of Forestry defines "future yield tables" as follows: "A tabular statement of the amount of wood which, after a given period, will be contained in given trees upon a given area expressed in board feet or some other unit."

PARAGRAPH XCV.

RETROSPECTIVE YIELD TABLES.

In "retrospective" yield tables an attempt is made to rebuild the growing stock as it was before lumbering from the stumps found on the ground and from stem analyses of the trees now standing. Prerequisite is a knowledge of the year in which lumbering took place and of the conditions of growth since prevailing.

Method of proceeding:

1. Make stem analyses and construct tree volume tables, showing the probable contents of trees for stumps of a given diameter and for given diameters *b. h.*

2. On land cut over n years ago, find by valuation survey and stem analyses:

a. The present volume "F."

b. The volume "y" of the trees now standing as it was " n " years ago with the help of tree volume tables.

c. From the stumps the volume "x" of the trees logged " n " years ago.

3. A product of "F" units (with an undergrowth not fit for logging) has been derived in " n " years from an original stand aggregating "y" plus "x" units of volume.

4. Grouping hundreds of sample plots together, yield tables for local use are obtained. Misleading is, of course, the multiplicity of conditions (mixture of species, soils, original stands, pasture and fire) surrounding a second growth which check the applicability and the combination of the tables found.

The tables are way signs, not ways, toward a true knowledge of the productiveness of cut-over woodlands.

PARAGRAPH XCVI.

YIELD TABLES OF THE BUREAU OF FORESTRY.

Bureau yield tables are meant to show the growth on cut-over land occurring within the next 10, 20 or 30 years, if a tract is logged to a 10", 12" or 14" (or any other) limit. Bureau yield tables are based on tree volume tables and on an account of the numbers of tree individuals found in the various age classes of forest, viz., diameter classes of trees.

The influence of the different qualities of soil on tree growth is not given, only one average volume table being constructed. The volume tables show the number of years which a tree requires to increase its diameter b. h. by one inch. The volume tables record, in addition, the volume increase corresponding with such diameter increase. Applying these findings to the stumpage presumably left after logging, the volume can be ascertained which is expected to be on hand 10, 20 or 30 years later. The volume growth is forecasted, as if it were taking place under primeval conditions.

The Bureau neglects entirely the death rate of trees, due to natural causes and especially high amongst seedlings and saplings, or else due to the logging operations themselves. The results forecasted in this way must be invariably too high.

Pinchot's Spruce Tables (The Adirondack Spruce, p. 77) are based on similar premises:

a. Construct volume tables by stem analysis (stump-analysis) on land cut over for a second time, thus showing rate of growth for trees left standing at the first cut.

b. Construct tables, by actual measurements in the woods, giving the

number of trees of the various diameters, composing a stumpage of from 1,000 to 12,000 feet board measure.

c. Predict the number of trees and their exact diameters to be found 10, 20 or 30 years after logging, according to severity of logging (diameter limit).

d. With the help of the volume tables, give the contents of these trees.

In these tables as well, the death rate amongst trees is disregarded. For normal death rate, compare Pinchot's "White Pine," p. 80, ff; also remarks at end of Paragraph LIV.

PARAGRAPH XCVII.

THE INCREMENT OF A WOODLOT.

The current as well as the annual average increment of normal, even-aged woods culminates at a much earlier date than the increment of the trees composing such woods. The explanation lies in the death rate of the trees.

Under a close crown density in even-aged, normal woods, the stronger half of the trees yield, from the pole stage on, practically all the increment, the weaker half of the trees being almost inactive.

The better the quality of the soil, the earlier occurs the culmination of the increment; consequently, on good soil, shorter rotations are apt to be advisable than on poor soil.

Light demanding (intolerant) species show an earlier culmination than shade bearers (tolerant) species.

For white pine woods, after Pinchot, the years of increment culmination are as follows:

Culmination of	For entire volume with bark in cu. ft.			For volume Doyle in ft. b. m.		
	I.	II.	III.	I.	II.	III.
Current incrt....	40th	50th	60th yr.	70th	70th	110th yr.
Average incrt...	60th	80th	100th yr.	135th	160th	210th yr.

I denotes best; II denotes medium, and III denotes poorest quality of soil.

The increment of a woodlot, whether normal or abnormal, can be obtained:

a. With the help of yield tables.

b. By special investigations made into the rate of growth of sample trees (Paragraph XCVIII.).

c. With the help of the average annual increment of the woodlot (Paragraph XCIX.).

The increment of a past period is never exactly equal to that of a future period, unless the age of the woods is close to that year at which the increment culminates. The increment percentage during a past period is always larger than the increment percentage during a coming period (aside of temporary increase due to light-increment).

The general laws (Paragraph LXXV.) relative to the culmination, increase and decrease of increment hold good for the volume increment of woodlots as well as for that of trees.

PARAGRAPH XCVIII.

ASCERTAINING THE INCREMENT OF WOODLOTS BY SAMPLE TREES.

The current annual volume increment and the volume increment percentage of a wood, from which its maturity largely depends, can be correctly found only by a valuation survey, combined with an investigation into the present rate of growth exhibited by a number of sample trees.

Borggreve recommends to gauge the increment of the sample trees by the Schneider increment percentage. This is usually insufficient.

The correct volume increment percentage p of a woodlot is obtained from the volume increment percentage p_1, p_2, p_3, p_4 and p_5 of the class sample trees—which represent class-volumes v_1, v_2, v_3, v_4 and v_5 —as

$$p = \frac{v_1 p_1 + v_2 p_2 + v_3 p_3 + v_4 p_4 + v_5 p_5}{v_1 + v_2 + v_3 + v_4 + v_5}$$

Where the form heights of the classes differ slightly only, the sectional areas of the classes may be substituted for the volumes of the classes.

Again, where classes of equal sectional area are formed (after Robert Hartig), there the volume increment per cent. of the woodlot equals the arithmetic mean of the volume increment percentages of the sample trees, so that

$$p = \frac{p_1 + p_2 + p_3 + p_4 + p_5}{5}$$

PARAGRAPH XCIX.

CURRENT INCREMENT ASCERTAINED FROM AVERAGE INCREMENT.

Within certain limits, a short time previous and a short time after the culmination of the average annual increment, the annual average increment equals the current increment and can be used in its place as a basis for yield calculation. European Governments frequently prescribe this *modus operandi* for yield forecasts in working plans.

CHAPTER IV.—LUMBER

PARAGRAPH C.

UNITS OF LUMBER MEASUREMENT.

For rough lumber one inch thick, or thicker, the unit of measure, known as one foot board measure, is a square foot of lumber one inch thick. This unit is the $\frac{1}{12}$ th part of a cubic foot.

For rough lumber thinner than one inch, the unit of measure, also known as one foot board measure, is the superficial square foot, and the thickness of the lumber is here entirely disregarded.

All dressed stock is measured and described as if it were the full size of the rough lumber necessarily used in its manufacture. "Inch flooring," *e. g.*, is actually $\frac{13}{16}$ inch thick; and " $\frac{3}{8}$ inch ceiling" is actually $\frac{5}{16}$ inch thick.

Standard thicknesses are:

$\frac{3}{8}$, $\frac{1}{2}$, $\frac{5}{8}$, $\frac{3}{4}$, 1, $1\frac{1}{4}$, $1\frac{1}{2}$, 2, $2\frac{1}{2}$, 3 x 4".

Standard lengths are:

in hardwoods 6 to 16 feet;

in softwoods 10 to 24 feet.

In both cases, lengths in even feet (not in odd feet) are required.

A shortness of 1" or 2" in the length of hardwood boards is disregarded.

Standard defects are:

- I. In hardwoods: one sound knot of $1\frac{1}{4}$ " diameter;
 one inch of bright sap;
 one split, its length in inches equalling the contents of
 the board in feet b.m.
- II. In softwoods: sound knots, viz.:
 - (a) pin-knots of not over $\frac{1}{2}$ " diameter;
 - (b) standard knots of not over $1\frac{1}{2}$ " diameter;
 - (c) large knots of over $1\frac{1}{2}$ " diameter;
 pitchpockets, viz.:
 - (a) small pitchpockets $\frac{1}{8}$ " wide;
 - (b) standard pitchpockets up to $\frac{3}{8}$ " wide and up to 3'
 long;
 pitchstreaks, viz.:
 - (a) small pitchstreaks not wider than $\frac{1}{2}$ the width and
 not longer than $\frac{1}{8}$ the length of board;
 - (b) standard pitchstreaks with dimensions up to twice
 as large as given under (a);
 sap, viz.:
 - (a) bright sap;
 - (b) blued sap;
 splits, wane, scant width, tongues, less than $\frac{3}{16}$ " long.

The point at which a defect is located greatly influences its effect on the grade of the lumber.

The two faces, the two edges and the two ends of a board must be parallel. In case of unevenness, the thinnest thickness, the narrowest width and the shortest length are measured.

Lumber is measured with the help of a lumber rule (Lufkin rule) which yields for inch boards of given lengths and given width the corresponding contents in feet b. m.

In measuring the widths, fractions of an inch are neglected in rough lumber.

PARAGRAPH CI.

INSPECTION RULES AND NOMENCLATURE.

The lumber inspection prevailing in a given market is governed by local custom or by agreement within the body of local associations of lumbermen.

The tendency of all inspection rules is directed toward a gradual lowering of rigidity.

The wholesaler's inspection is generally stiffer than that of the manufacturer. Diversity of rules is a sadly demoralizing element in lumber circles.

Lumber sawn for special purposes (*e. g.*, wagon bolsters) must be inspected with a view to its adaptability for such special purpose.

A. *Hardwood.* The grade of a board depends on

1. Its width and length;
2. Its standard defects;
3. The percentage of clear stock contained therein;
4. The number of cuttings yielding such clear stock.

The following table shows average specifications prevailing for the various grades of hardwood lumber in the U. S. markets.

The defects specified invariably indicate the coarsest stock admissible in a given grade.

Designation of Grade.	HARDWOOD LUMBER SPECIFICATIONS.						
	Minimum		Actual		Allows of		
	Len'h feet.	Wi'th inch- es.	Length feet.	Width inches.	No. of standard defects.	Rate of clear stock.	Con'd in c't'ngs not more than
Firsts.....	10	8	10 & over	8 & 9	none	Practically all.	Practically one.
	..	..	10 & over	10 & over	one		
Seconds.....	8	8	8	8 & 9	none		
	..	..	8	10 & over	one		
	10	6	10 & over	6 & 7	none		
	..	..	10 & over	8 & 9	one		
	..	..	10 & over	10 & 11	two		
	..	..	10 & over	12 & over	three		
No. 1 Com...	6	6	6	6 to 8	none	all	1
	..	..	6	9 & over	one	all	1
	8	4	8	4	none	all	1
	..	..	8	5	one	all	1
	..	..	8 & 10	6 & over		all	2
	..	..	12 to 16	6 & over		all	3
No. 2 Com...	6	3	6 to 10			$\frac{1}{2}$	3
	..	..	12 to 16			$\frac{1}{2}$	4
No. 3 Com...	4	3				$\frac{1}{2}$	..

B. *Softwoods.* Softwood lumber is inspected from its best side Under "edgegrain" is understood lumber the face of which forms an angle of less than 45 degrees with the plain of the medullary rays contained in the board. All other lumber is termed "flat grain" or "slash grain," also "bastard grain."

I. *Finishing Lumber*, 1" to 2" thick, dressed one or two sides.

1. First and second clear,
up to 8" wide; absolutely clear;
10" wide; one small defect permitted;
12" and over wide; $\frac{1}{3}$ of stock may have one standard knot or its equivalent.
2. Third clear,
allows of twice as many defects.

II. *Flooring*, 1" thick and 3" or 4" or 6" wide before dressing; either with hollow back or with solid back;

1. A, B and C flat grain flooring; wherein "A" is clear and "B" allows of one or two standard defects;
2. A, B and C edgegrain flooring; with the same allowance;
3. No. 1 and No. 2 fence flooring.

- III. *Ceiling*, $\frac{3}{8}$, $\frac{1}{2}$ and $\frac{3}{4}$ inch thick; 3, or 4, or 6 inches wide.
1. "A" ceiling and "B" ceiling, with small defects only;
 2. No. 1 and No. 2 common ceiling, with one and two standard defects, or their equivalent.
- IV. *Drop Siding*, which is either "shiplapped" or "tongued and grooved;" it is $\frac{3}{4}$ " thick and $3\frac{1}{4}$ or $5\frac{1}{4}$ inches wide. Grades A, B and No. 1 common.
- V. *Bevel Siding*, which scales $\frac{3}{8}$ " at the thin edge and $\frac{1}{2}$ " at the thick edge, resawn from stock dressed to $1\frac{1}{8}$ " x $5\frac{1}{2}$ ". Grades as under IV.
- VI. *Partition*, measuring $\frac{3}{4}$ " x $3\frac{1}{4}$ " or $\frac{3}{4}$ " x $5\frac{1}{4}$ ". Grades as under IV.
- VII. *Common Boards*, graded as No. 1, No. 2 and No. 3 common boards, 8", 10" or 12" wide, dressed one or two sides, or rough.
- VIII. *Fencing*, graded as No. 1, No. 2 and No. 3 fencing, 3", 4" or 6" wide. The grade "No. 3" includes defective lumber with knot-holes, red rot, very wormy patches, etc., on $\frac{1}{2}$ of the length of the board. Fencing is either dressed or rough.

CHAPTER V.—STUMPAGE VALUES

PARAGRAPH CII.

STUMPAGE VALUES.

Forestry is a business; the forest largely represents its business investment; its purpose is the raising of money, of dividends.

Thus it is with investments and the dividends therefrom that the forester is concerned; and it is the task of "forest finance" and "forest management" to ascertain the factors and to regulate the components of such investments.

Forest mensuration, as a subsidiary to forest management, may well devote a chapter to the measurement of the stumpage value of trees.

Stumpage value is the price which a tree brings or should bring if it were sold on the stump.

The stumpage-value of a tree depends on the value of the lumber contained therein and obtained therefrom, deducting the total expense of lumber production (logging, milling, shipping, incidentals.)

Since the value of lumber fluctuates, as well as the cost of production, stumpage values are subject to continuous variation. The tendency of stumpage prices, all over the world, is a tendency to rise—especially so in countries of rapid development, rapid increase of population and inadequate provisions for re-growth.

The cost of production is composed about as follows:

1. Expense of logging and log transportation, varying locally between \$2 and \$5 per 1,000' b. m.
2. Expense of milling, varying between \$1.50 and \$5 per 1,000' b. m.
3. Expense of freightage of lumber to the consuming market, amounting per 1,000' b. m. to \$1.50 for very short hauls; to \$12 for a haul from Atlanta to Boston; to \$21 for a haul across the continent from Portland (Oregon) to New England.

Freight rates have, in the long run, a decided downward tendency. Still, with a majority of the lumber produced in the U. S., the item "freight" forms the chief expense of production.

For Pisgah Forest a reduction of freight rates equalling 1 cent per 100 lbs. involves a net gain for the owner of approximately \$60,000. In this possibility lies one of the strongest arguments for conservative lumbering.

An increase of the price of lumber from \$20 to \$21 at the place of consumption endears the lumber to the consumer by 5%; the owner of the forest now valuing his stumpage at \$5 will eventually experience this increase as a 20% increase of stumpage values.

The only factors of stumpage-values, which the owner himself—unaided by the development of the country—may influence, consist in the expense of logging and log freighting, and in the expense of milling, the former largely depending on the quality of available means of transportation, the latter governed by the quality of the sawmill.

In ascertaining the stumpage-value of a tree the forester considers:

- a. The cost per 1,000' b. m. of logging it, of milling it and of freighting its timber;
- b. The volume of timber contained in the tree, by grades;
- c. The value of such lumber, by grades.

If a tree contains

45% of lumber worth \$31 per 1,000' b. m.

It is necessary to find Stuetzer's constant factor of increment or to ascertain the relative increment of the sectional areas of the sample trees at 0.45 of their heights.

35% of lumber worth \$21 per 1,000' b. m.

15% of lumber worth \$16 per 1,000' b. m.

5% of lumber worth \$8 per 1,000' b. m.

then the lumber value of the tree, per 1,000' b. m., is

$$\frac{45 \times 31 + 35 \times 21 + 15 \times 16 + 5 \times 8}{100} = \$24.10$$

Deducting from this figure the expense of logging, milling and freighting, the actual stumpage-value, per 1,000' b. m., is derived.

The actual prices paid for stumpage in the U. S. fall deeply below the figures which a test-calculation is apt to yield.

This discrepancy may be explained, above all, by

- Ignorance of owners of stumpage;
- Agents' and dealers' profits;
- Incidental expenses overlooked.

Stumpage-values show a rapid decrease with the increase of the distance separating the tree from the nearest railroad or stream.

The grades of lumber and their proportion obtainable from logs of given species, diameter and soundness (including presence and location of defects) can be ascertained only by test-sawing in the mill.

This has been done in 1896 for yellow poplar at Biltmore (bandsaw mill). The stumpage-values then ascertained are shown by the following table:

MARKET VALUE OF POPLAR STUMPAGE IN WESTERN NORTH CAROLINA, PER TREE, IN CENTS.

At the age of years.	Under good conditions.				Under average conditions.				Under poor conditions.			
	Diam. inches.	Logging and Milling expenses being per 1000 feet B. M.			Diam. inches.	Logging and Milling expenses being per 1000 feet B. M.			Diam. inches.	Logging and Milling expenses being per 1000 feet B. M.		
		\$9	\$10	\$11		\$9	\$10	\$11		\$9	\$10	\$11
100		Nega- tive.	Nega- tive.	Nega- tive.		Nega- tive.	Nega- tive.	Nega- tive.		Nega- tive.	Nega- tive.	Nega- tive.
120	18.8	8	"	"		"	"	"		"	"	"
140	21.3	40	25	"	18.2	4	"	"		"	"	"
160	23.5	105	72	2	20.4	22	5	"		"	"	"
180	25.7	265	170	98	22.4	67	35	"		"	"	"
200	27.7	445	325	230	24.3	160	103	30	18.5	"	"	"
220	29.6	620	465	350	26.0	287	200	109	20.0	7	"	"
240		...	...	...	27.5	430	330	210	21.3	27	3	"
260		...	...	...		...	460	330	22.1	60	25	"
280		...	...	...		...	...	...		...	45	"
300		...	...	...		...	...	...		...	...	5
320		...	...	...		...	...	...		...	...	30

FOOTNOTE: Dots below a column of figures indicate higher values, not specifically ascertained.

The values above the columns of figures are all negative and were not ascertained specifically either.

It is to be hoped that similar tests will be made for our leading species on a large scale by the U. S. Forest Service or by the various associations of lumber manufacturers. Conservative forestry as a business badly requires data allowing to estimate the actual value of logs, and hence of trees, if the uncertainty of financial results now checking the progress of conservative forestry in America is to be definitely reduced.

G. S. Hamlin Jr.

Forest Utilization.

TO THE READER.

The Biltmore Forest School has offered annually, since 1898, a course of lectures on Forest Utilization—a vast topic comprising every art, every industry, all activity connected with the utilization of our woods.

If forestry is and means a business, then it is safe to say that forest utilization comprises the major—the by far major—part of the American forester's activity, provided that the term "forester" describes a man placed in charge of a forest and of its administration.

There cannot be any doubt that American forest utilization is conducted on the grandest, most ingenious scale which the world ever knew. The conditions surrounding and bearing it are entirely at variance from those now confronting the European forester. It is not to be wondered at, consequently, that little knowledge of American forest utilization can be gathered from European handbooks on European forest utilization or from European travels.

Like all disciplines of forestry, forest utilization had best be studied in and near the woods. Lectures delivered at a forest school, unless they be continuously illustrated by object lessons in the forest and in the workshop, can merely lay a bare foundation of the topic in the mind, or rather in the memory of the student.

The pages herewith submitted are printed primarily for the use of the students attending the Biltmore Forest School; they comprise the dictation given by the teacher during and after lectures; they are a skeleton of lectures merely, and it is the teacher's task to clothe the skeleton with flesh, obtained from his practical experience in the American woods.

There is ample reason to believe that one-sided and local experience has allowed a number of mistakes to creep into the following paragraphs. The Biltmore Forest School begs to be corrected by the reader, and any suggestions relative to errors and erroneous statements contained in this little publication will be most thankfully received.

Aside from the entire literature on forest utilization available in America and abroad, liberal use has been made of communications appearing in all of the leading trade papers; of the catalogues issued by the leading firms manufacturing implements for forest utilization; of the experience of the rangers and foremen of the Biltmore Estate; of information privately obtained through correspondence.

Most truly,

C. A. SCHENCK, Ph.D.,

Director Biltmore Forest School and Forester to the Biltmore Estate.

BILTMORE, N. C., Sept. 1, 1904.

Forest Utilization.

- § 1. Definition.
- § 2. Literature.

PART I. LOGGING OPERATIONS.

CHAPTER I. LABOR EMPLOYED IN LOGGING.

- § 3. Manual labor.
- § 4. Animal labor.

CHAPTER II. CUTTING OPERATIONS.

- § 5. Woodcutter's tools and implements.
- § 6. Felling the trees.
- § 7. Dissecting the boles.

CHAPTER III. TRANSPORTATION.

- § 8. Transportation on land, without vehicles.
- § 9. Transportation by water.
- § 10. Transportation on land, by and on vehicles.
- § 11. Choice between the various systems of transportation.

PART II. MANUFACTURE OF WOOD PRODUCTS.

CHAPTER IV. FOUNDATIONS OF MANUFACTURE.

- § 12. The American forester as a lumberman.
- § 13. Motive power.
- § 14. Transmission of power.
- § 15. Technical use made of the trees by species.
- § 16. Technical qualities of the trees.

CHAPTER V. MANUFACTURING INDUSTRIES.

- § 17. Saw mill.
- § 18. Woodworking plant.
- § 19. Veneering plant.
- § 20. Box factory.
- § 21. Basket factory.
- § 22. Cooperage.
- § 23. Wagon works.
- § 24. Shingle mills.
- § 25. Lath mills.
- § 26. Clapboard mill.
- § 27. Novelty mill.
- § 28. Matches.

- § 29. Shoe pegs.
- § 30. Excelsior mill.
- § 31. Manufacture of wood pulp and chemical fibre.
- § 32. Tannery.
- § 33. Charcoal.
- § 34. Lampblack and brewer's pitch.
- § 35. Pyroligneous acid and wood alcohol.
- § 36. True aethyl alcohol.
- § 37. Artificial silk.
- § 38. Oxalic acid.
- § 39. Maple sugar.
- § 40. Naval stores.
- § 41. Vanillin.
- § 42. Beechnut oil.
- § 43. Pine leaf hair.
- § 44. Impregnation.

FOREST UTILIZATION.

§ I. DEFINITION.

The term "forest utilization" comprises all acts by which forests—the immobile produce of nature—are converted into movable goods or commodities. Considered as a science or as an art, forest utilization constitutes the major part of forestry now practiced in our new country, abounding in forests.

As a discipline, forest utilization may be divided into two main parts, namely: "logging operations" and "manufacture," arranged in the following five chapters:

- Chapter I. Labor employed in the forest.
- Chapter II. Cutting operations.
- Chapter III. Transportation.
- Chapter IV. Foundations of manufacture.
- Chapter V. Manufacturing industries.

§ II. LITERATURE.

There exists, unfortunately, no handbook on American forest utilization, although forest utilization shows a higher development in the United States than in any other country.

Among the foreign literature on forest utilization, publications of the following authors are particularly worthy of note:

Carl Gayer, Richard Hess, William Schlich, Hermann Stuetzner, Carl Grebe, Wilhelm Franz Exner, Carl Schuberg, Heinrich Semler, H. von Noerdlinger, Carl Dotzel, E. E. Fernandez, L. Boppe, M. Powis Bale.

Part 1. Logging Operations.

CHAPTER I. LABOR EMPLOYED IN THE FOREST.

§ III. MANUAL LABOR.

A. Duration of employment.

I. Determining factors are:

- (a) Climatic conditions;
- (b) Economic conditions;
- (c) Local custom.

In the South, work lasts all the year round.

In the Lake States and in New England, late fall, winter and early spring (from four to eight months) comprise the usual period of activity.

In the European mountains, logging is restricted to the summer months; in the European lowlands, to the winter months.

II. Advisability of continuous employment in conservative forestry, especially in the case of foremen and sub-foremen, leads to the adoption of means tending to attach the laborer to his job and to his employer.

Such means are:

- (a) Advances for tools.
 - (b) Rent of cabins and farms at reduced rates.
 - (c) Help in case of sickness and accidents.
 - (d) Wholesale purchase of victuals so as to give the workmen the benefit of a reduced price.
 - (e) Firewood, forest pasture and forest litter free of charge.
 - (f) Permission of agricultural use, for a number of years, of clear cut areas. (This last system is called in India "tongya.")
 - (g) Employment during the season when cutting is stopped, in road building, fire patrol, planting, weeding, nursery work etc.
 - (h) Possibility for hands to rise to a foreman's position.
 - (i) Encouragement of home industries so as to keep the workmen busy on rainy or cold days, i. e., basket weaving, shingle making, wood carving, sieve making.
- It seems most important to supply the family of the woodworker with a comfortable home and school and church advantages.

B. Remuneration.

I. Means of remuneration.

- (a) Money. Wages in the South are from 50 to 75 cents a day. At Biltmore, now \$1 per day, even in the mountains. On the Pacific coast, \$2 to \$3 per day. In Lake States, \$18 to \$32 per month, plus board; dry days only included.

- (b) Commissary bills. This method of payment is used in the South only, in connection with colored labor.
 - (c) Privileges (house, farm, pasture).
 - (d) Board. Expense at Biltmore, per capita, 25c to 30c; in Lake States, 40c to 50c per day. Wages of camp cooks in Lake States, \$50 and over per month; at Biltmore, \$15 to \$30 per month.
- Victuals required per capita, see "Lumber and Log Book," page 144.

II. Scale of remuneration.

Wages depend on the effect of labor or on the values created by labor.

Influencing factors are:

- (a) Density of population.
- (b) Human strength and technical skill required.
- (c) Silvicultural understanding required.
- (d) Hardships endured and risks taken.
- (e) Prices of the necessary victuals.
- (f) Length of day during cutting season. Compare page 162, "Lumber and Log Book."

Where contract work prevails, the following additional factors come into play:

- (g) Tools supplied by employer or employee.
- (h) Softwoods or hardwoods.
- (i) Amount to be cut per acre.
- (j) Configuration of ground and remoteness from roads.
- (k) Distance from home village.
- (l) Possibility of continuing work during rain.

Experiments have shown that workmen paid under contract per one thousand feet b. m. earn more money in big timber than in small timber, and that a system of payment according to the diameter of the log is far more just.

C. Method of employment.

In France the woodworkers are employed by the purchaser of stumpage; in Germany, invariably by the owner of the forest. In America, both systems are found, the former prevailing. Whether the German or French system is preferable is an open question.

I. Hands are usually recruited from farm laborers, hence advisability of locally combining agriculture and forestry. In addition, the employees of the building trades, unoccupied during winter, supply help for the lumber camp.

II. Day work is advisable in preference to contract work

- (a) Where quality (effect) of labor cannot be controlled, notably in nursery work;
- (b) Where experienced hands must be trained;
- (c) Where contract labor cannot be obtained (Pacific coast);

- (d) Where contract legislation is bad. (Lien laws in Minnesota; \$1,500 exemption clause in North Carolina.)

III. Contract work is generally preferable to day work because it is cheaper. Contract work is doubly advisable where employer's liability laws work against the employer. Contracts should always be in writing. The specification sheet should be kept apart from the paragraphs of agreement, so as not to encumber the contract.

The main clauses of a contract cover:

- (a) Time allowed to complete work;
- (b) Installments and payments;
- (c) Building of snaking roads, sleigh roads and skidways;
- (d) Scaling of defective logs and of sound logs;
- (e) Employer's liability;
- (f) Fines for fire, stock at large, fishing, hunting and drunkenness, and demand for discharge of culprits;
- (g) Shanties and log houses and commissary bills;
- (h) Supply of tools; deduction for loss and spoliation of tools;
- (i) Fines for cutting trees not marked or of too small a diameter;
- (j) Fines for leaving marked trees uncut;
- (k) Fines for poor work and unnecessary damage;
- (l) Possibility of speedy termination of contract in emergency cases;
- (m) Nomination of umpire to avoid suits in case of discrepancies.

The specifications cover the following points:

Height of stumps; peeling of bark; separating product according to quality; length, diameter, weight of product; nosing logs; cutting defects out (unsound knots etc.); placing the product on sticks (so as to allow it to dry) or on skidways; method of carrying or moving products; swamping (removal of branches); use of road poles (breast works); skidways; road building.

D. Subdivision of labor.

The leading principle is that one division gang must push the other.

I. Lumbering.

- (a) Cutting or felling crews, consisting usually of two hands; sometimes a third man to drive wedges and to make the axe cut.
- (b) Log makers, dissecting the bole into logs. A foreman should be an ex-sawyer or an ex-lumber inspector.
- (c) Swamping crew, to clear trees of branches and to open suspicious knots.
- (d) Snaking crew—at Biltmore five hands for a three-yoke team; three men to get the logs ready and to remove brush (debris) and two men to accompany the load.
- (e) Skidway crew—two hands rolling logs onto skidways.

- (f) Road crew—meant to prepare snaking or sleigh roads; to sprinkle and sand ice roads.
- II. Firewood or cordwood making (for pulp, distillation, cooperage etc.).
- a, b, and c are the same as in "I.—a, b and c."
- (d) Carriers or carrying crew—often with hand sleighs or rollers or grapple hooks.
- (e) Splitters—with heavy axes which have broader, thicker checks than cutting axes.
- (f) Piling crew—a very careful, honest man is required for piling the wood.

§ IV. ANIMAL LABOR.

A. Countries.

In Europe, even in virgin forests, practically none is required. In India and possibly in the Philippines, elephants are used.

In the United States, in the Southern and Pacific States, as also in the Appalachians, oxen are used. In the Lake States, Pacific States and New England States, horses are preferred. In the South, mules are used for small logs and especially on tram roads.

B. Horses.

- I. The numerical ratio between hands and horses in Northern camps varies from 2 to 1 to 6 to 1.

The standard amount of work for one horse is:

- (a) A haul of 1,600 lbs. inclusive of wagon, on a level road over 23 miles per day.
- (b) An output of $2/3$ horsepower per minute, equal to 320 horsepower per day of eight hours.

II. Horses are employed for

- (a) Skidding or snaking.
- (b) Rolling logs on skidways.
- (c) Sleighing, trucking (two wheels) and wagoning (four wheels).
- (d) Go-deviling.
- (e) Loading on railroad cars.
- (f) Supplying power for portable mills.

III. Food for horses.

- (a) Interdependence between feed and effect in foot pounds per 1,000 lbs. horse flesh during a day's work is:

Straw	2 lbs.	2 lbs.	2 lbs.
Hay	19 lbs.	15 lbs.	11 lbs. ✓
Oats	2 lbs.	6 lbs.	10 lbs.

Effect	3,000,000	9,000,000	15,000,000
--------------	-----------	-----------	------------

- (b) Food required.

After Thaer, per 1,000 lbs. of horse flesh, 25 lbs. of good hay and oats.

After the "Lumber and Log Book," 50 lbs. of oats and 40 lbs. of hay per team per day.

- (c) Feed values equivalent to 100 lbs. of good hay, after Haswell, are
- = 54 lbs. of barley.
 - = 57 lbs. of oats.
 - = 59 lbs. of corn.
 - = 275 lbs. of green corn.
 - = 374 lbs. of wheat straw.
 - = 400 lbs. of cornstalks.

C. Mules.

I. They are employed for:

- (a) Light logs on good ground and for long distances.
- (b) For wagoning lumber and provisions.
- (c) For hauling on rail tracks (wooden and iron rails).
- (d) For hoisting logs on inclines.
- (e) For plowing and scraping in road and railroad building.

II. Food for 1,000 lbs. mule flesh, as for horses.

Mules require less care than horses, taking care of themselves and resisting overwork. They are frequently not fed at noon. (Price per team at Biltmore, \$200.)

D. Oxen.

I. Price per yoke is from \$80 to \$120, weight from 2,000 to 2,500 lbs.

Ox yokes form the rule, although efficiency of oxen in harness is superior. Shoeing for each claw separately—difficult and risky, but necessary on hard ground.

Special training takes place from second year on. Fitness for hard work begins in the fifth year, when ossification of bones is completed.

Special training for leaders.

II. Employment.

In the South for snaking heavy logs—or log trains in Oregon; for hauling logs suspended underneath high two-wheel trucks in the pineries; rarely for loading cars or wagons.

III. Standard work.

An ox walks 14 miles per day with load. An ox yields in eight hours of work 270 horsepower, hence he produces only four-fifths of the effect of a horse.

After Thaer, an ox produces only one-half as much power as a horse of the same weight.

IV. Feed.

- (a) It is much cheaper to feed oxen per 1,000 lbs. living weight than to feed horses of same weight.

Ruminants have four stomachs and thus digest their food better. No feed is given in the middle of the day, and no expense is incurred during idle periods, where pasture is available.

- (b) Careful treatment and good stables required. Oxen must not be hurried. Soft yokes, proper salting and regular watering.

- (c) In the South, at the present time, cottonseed meal and hulls form the cheapest food. Food requirements per yoke per day are 25 lbs. of meal and 40 lbs. of hulls. Present prices of meal \$25 per ton and hulls \$8 per ton, delivered at Brevard, N. C.

CHAPTER II. CUTTING OPERATIONS.

§ V. WOODSMEN'S TOOLS AND IMPLEMENTS.

A. **Axe.** It consists of a handle, 32 inches to 42 inches long, made of hickory, ash, locust or mulberry, either straight or "S" curved, and of a blade or head forming a steel wedge of particular temper. The cheeks of the wedge are slightly curved in the midst, falling down gradually towards the upper and lower line. The weight lies either close to the bit or close to the handle, according to local predilection.

The best make is the Kelly axe.

Double bit axes, requiring straight handles, are largely used in the Northeast. Special splitting axes, of greater weight and broader cheeks, are rarely used (for sugar barrel bolts and retort wood).

For hardwood, a thin and light axe (a cutting axe) is preferred, while for softwood a broad and heavy axe is used (a tearing axe).

A box of axes contains an assortment of various weights. In Europe the bit is relaid with steel, after wearing off.

The axe is used

- I. For cutting trees entirely or partly.
- II. For swamping (axe to be $\frac{1}{2}$ lb. heavier).
- III. For splitting.
- IV. For nosing logs.
- V. For driving wedges.

Price of axes from \$6 to \$8 a dozen. Handles are \$1 a dozen.

B. **Adz and broadaxe.**

The adz and broadaxe are used for trimming and barking export logs, squares, ties and construction timber. The blade of the adz stands at right angles to the plane of the sweep and has such curvature as corresponds to the curve of the sweep through the air. The cutting edge is ground concave on the inner side.

The broadaxe is either right or left sided, the plane of the blade forming an angle of 5° to 10° with the plane of the handle. The handle is usually short, the blade very heavy and wide.

*C. **Peavies.**

The peavy is a typical American tool, not used elsewhere. The best make is Morley Bros.' line of blue tools.

The hooks are distinguished as round bill, duck bill and chisel bill hooks, made of hammered steel. The socket is either solid or consists of rings. The square pick (point) is driven cold into the round bored point of the handle. The handle is 4 to 6 ft. long, straight, $2\frac{1}{2}$ inches to 3 inches through and is made of hickory, ash, or usually hard maple. Price per dozen is \$10 to \$22.

A peavy must answer the following requirements:

I. Hook adapted to any size log.

II. Bill to be so constructed as to catch securely through any layer of bark.

III. Proper length, greatest strength and low weight.

D. Cant hooks.

The cant hook is a peavy, lacking the pick (point).

The socket consists of two rings only joined by a narrow bar.

Cant hooks are used more in the mill and yard, peavies more in the woods.

E. Cross-cut saws.

I. Radius experiments show a radius of 5 feet 2 inches to be best. The straight drag saws require excessive strength and are deficient in dust chambers.

II. Width of blade.

It is at the widest point about $8\frac{1}{2}$ inches. The hollow back saws, a very recent invention, have only about 4 inches width all through.

III. Thickness of blade.

The back of the saw is always somewhat thinner than the gauge of the teeth. Henry Disston gives the saw backs 4 or 5 gauges less thickness than the saw teeth. Atkins gives the teeth "14 gauge," the back at the handles "16 gauge" and at the center of the back "19 gauge."

IV. Uniformity of temper and proper temper are obtained by special processes. No hammering of blades. Cheeks are perfectly smooth.

V. Construction of teeth is very variable. Dust room between the teeth should be twice as large as the teeth.

For hardwoods more teeth are necessary than for softwoods. There are two kinds of teeth, namely:

(a) The cutting teeth, a couple or trio of which might be arranged on a common stock, to form "Tuttle or Wolf Teeth." Only the points of the cutters actually cut into the fibre.

(b) The raker or cleaner teeth, meant to plane off the fibre severed by the cutters and to shift the sawdust out of the kerf. European experiments prove the uselessness of cleaners. They simply occupy valuable dust room. The point of the rakers should recede by $\frac{1}{32}$ of an inch from the cutting line of the cutting points.

VI. Length of saw is from 4 ft. to 8 ft. At Biltmore $6\frac{1}{2}$ ft. and at Pisgah 7 ft. is preferred.

Local crews use the "diamond cross-cut," the "champion teeth" and the "hollow back" saw.

VII. Saw handles should be easily detachable. The material of the handle is maple, birch and hickory. Handles are fixed

(usually) vertically to back of saw. Sometimes, however, they are in the direction of the radius of the saw.

Large "bow" saws allow of a very thin blade and have a bow instead of handles. They are not used in America.

VIII. The effect of a saw is equal to the number of square inches cut by one man per minute. The effect is small in pole-woods, increasing gradually up to a diameter of $1\frac{3}{4}$ ft. and decreasing thereafter owing to increasing friction.

In cutting longleaf pine, the saw is continuously sprinkled with turpentine.

The effect of curved saws is from 40 % to 50 % higher than the effect of straight saws.

The saw overcomes

- (a) The resistance of the fibre by the sharp points acting as knives and planes;
- (b) The friction at both cheeks of the blade by smooth cheeks and by a gauge narrowing toward the back;
- (c) The friction of sawdust by deep teeth, curved line of teeth, perforation, large dust chambers and possibly by "cleaning teeth."

IX. Dressing of cross-cut saws.

- (a) "Jointing" means filing all cutting teeth down to exactly the same circumference.

The tool used is called a jointer. A file is placed in the joints and by a screw pressed into the proper curvature.

- (b) "Fixing the rakers" means filing them down with the help of a raker gauge. The rakers act as brakes if they project into the cutting line. Outside and forks of rakers are slightly filed to remove case hardening, and the point is sharpened to a planer edge.

A raker swage is being introduced to spread the points of the rakers and to give them a hook-like point, which is said to tear out long slivers instead of tearing out dust.

- (c) "Setting the cutter teeth" is done under the control of a "set gauge" with the help of a "set block and hammer," giving 3 to 4 taps (the best method when done by experienced men) or with the help of a "saw set." "Saw sets" are constructed either wrench-like or after the hammer and block principle.

Rules of setting are:

1. Setting should never go lower than half the length of the tooth.
2. It should never exceed twice the gauge of the teeth.

FOREST UTILIZATION

3. More set is required for long saws and for soft woods than for short saws and hard woods.
4. When hammering, strike tooth fully $\frac{1}{4}$ inch from point of tooth.
5. If teeth are badly set, take, to begin with, all set out of the teeth.
6. Apply side file inside file holder, to take away slight irregularities of set (after filing the teeth).

- (d) "Filing." Filing usually follows setting except in the case of saws spanned in a vise, when the set is afterward given by holding the set block on one side of the spanned saw and hammering from the other.

Rules of filing are:

1. File inside of tooth only.
2. File to a bevel or fleam of 45° .
3. Push the file away and do not draw it toward you.
4. Do not file point to a feather edge.
5. It is useless to sharpen tooth below the cutting point.

- (e) "Gumming." Gumming is usually done with the file; the lever (punch) gummier may be used for the purpose, however.

- (f) Remarks: A good, well-tempered saw holds sharpening and filing for six work days.

In California one man "cross-cut saws" up to six feet long are used in dissecting the bole into logs. The cross-cut saw file shows, on the cross section, a narrow triangle with curved back.

In Europe flat and triangular files are used for cross-cut saws.

The "spread set" of the cutting teeth has been tried and was found impracticable.

F. Wedges.

Wedges are used:

- I. To split wood. The "axe wedge" is usually made of iron and should have straight and not convex cheeks, which are often grooved to prevent wedge from jumping the cleft.

Wedges are sold by the pound.

Iron wedges are prevented from jumping by heating them, by putting dirt in the cleft, or else a rag (wet) over the wedge.

Wooden wedges are made of the butts of hard maple, hornbeam, black gum, dogwood and beech.

Iron wedges with wooden backs are frequently used abroad.

II. To prevent saw from pinching in the kerf.

Special saw wedges of oil-tempered steel are made by Morley Bros.

Frequently saw wedges and axe wedges are used alike.

Wooden wedges must be driven with the axe or hammer.

Iron and steel wedges must be driven with a wooden maul.

G. Mauls and maul bands.

Mauls are made of the butts of dogwood, beech, hornbeam, hard maple, gum and locust, and are held together by two iron hoops made of $\frac{1}{2}$ -inch by $\frac{3}{4}$ -inch flat iron.

H. Pickaxe and mattock.

They are used where the stumps are used together with the bole and in the preparation of forest roads. The points of both are relaid with steel after wearing out.

I. Brush hooks.

They are used in cleaning boles and in making fagots or fascines; further in clearing snaking roads in dense underbrush.

J. The krempe.

The krempe is used largely abroad and in India and resembles the picaroon or hookaroon used in America for handling ties, telegraph poles and pulp wood. It is used in rolling and moving logs down hill, the pick acting as a lever, the fulcrum of which lies at the heel.

K. Pike poles.

Pike poles are used with pike and hook or with pike only; are 12 ft. to 20 ft. long, made of selected white ash, the points consisting of cast steel. The points are either screwed into the wood or driven without heating. Pike poles cost \$10 to \$25 a dozen. They are indispensable in driving and rafting operations and at mill ponds.

L. Screws for blasting stumps. Such screws are used abroad, not to shoot stumps out of the ground but solely to split stumps where prices of firewood are high. The hollow screw loaded with blasting powder is inserted into an auger-made hole.

M. Grindstones.

Grindstones should not be exposed to the sun, should be kept equally round and even and should always be kept wet while in use. A water trough underneath the stone should be rejected, as the submerged side softens unduly and unevenly. Stones are sold by the pound.

A 70-lb. grindstone costs about \$4. The extra fixtures, consisting of hubs, shafts with nuts, crank etc. cost about a dollar.

N. Machine saws.

For cutting trees such saws have proven a failure. Similar was the fate of the "electric cutting machine" recently patented by Bayer. The expense of carrying machines from tree to tree is greater than the expense of cutting by hand.

O. Tree-felling machines.

They are largely used abroad to obtain the stump of a tree together with the bole.

- I. One of them is the "Nassau machine," consisting of a 4-inch board 10 inches wide into which regular steps are hewn, and of a pole about 25 ft. long, with a crooked pike at the small end and squarely bound in iron at the big end. Half a foot above the big end the pole is perforated so as to receive a 1½-inch round steel spike. The square base of the pole is placed on a step of the board, fixed flat on the ground, some 12 feet from the tree. The pole then forms an angle of about 50° against the board, while the spike is securely placed into the bole of the tree. By means of two crowbars the base of the pole is moved step by step toward the tree. This machine must be used in Hesse Darmstadt, under the employer's liability law.
- II. The "wood devil" has been used for centuries in Switzerland. A rope or cable is fixed in the top of the tree to be felled and a chain is fastened around a stump in the falling direction, which chain ends in two hooks. The lower end of the rope is secured to a chain, the links of which receive the hooks. By moving a long lever to and fro, the hooks are inserted alternately in the chain end of the rope, advancing two or three links at a time. The instrument is very cheap, simple and powerful; at an angle of 45° the rope has the maximum of power.
- III. To remove stumps alone the stump lifter might be used.
- IV. "Weston's differential hoist" lifts the maximum of weight with a minimum of its own weight.
A Weston hoist capable of lifting 1½ tons 8½ ft. high weighs only 81 lbs. and costs \$25.

§ VI. FELLING THE TREES.

Under "A" and "B" are described the chief methods of felling.

A. Obtaining bole without stump and roots:

- I. By exclusive use of the axe, handled from one side only in cutting small trees, in thinnings and in coppice woods.
- II. By exclusive use of the axe, cutting two kerfs on opposite sides. The first notch, on side toward which tree is intended to fall, made from 4 inches to 6 inches lower, must penetrate the center of the tree. Avoid felling toward the direction in which the tree leans.

Advantages of this method are the facts that one tool and one man only are required; that the bole is easily directed; that the logs obtain proper noses.

Disadvantages are loss of bole, amounting to from 4% to 8% and loss of time and labor in large timber. This method of felling is universally used in Maine.

- III. By hewing "out of the pan," a method used for valuable heavy boles. Uncertainty of fall is counterbalanced by a gain in the length of the bole. The bole thus obtained is said to show less heart shakes.
- IV. By using the two-handed cross-cut saw alone, without the help of the axe, a method not advisable for the reason that the fall of the bole cannot be directed.
- V. By joint use of cross-cut saw and axe. The axe cuts a kerf on the falling side, the depth of which is $\frac{1}{4}$ to $\frac{1}{5}$ of the diameter, and the innermost point of which lies on a level with the saw kerf. When the saw begins to pinch, drive wedges behind the back of the saw. Withdraw the saw when the tree begins to shake heavily and force it to fall by wedging. Advantages of this method are: the trees are easily directed at a small loss of timber. Disadvantages are: several tools and several men are required. In very thick woods and on very rocky, steep slopes, the use of the saw is not advisable or possible. Careless wedging may cause the bole to split at the butt. The saw and the wedge are said to be responsible for heart shakes.

B. Obtaining bole with stump and roots:

It is essential to thoroughly sever the main roots with axe, mattock and pick. The tree is then forced over by a tree-felling machine, or with a rope fastened to a high limb.

Advantages are: longer bole; gain of lumber 8% to 10%. Possibility of obtaining knees for ship building (tamarack and white oak). The tree falls gently, its fall being checked by the roots so that the bole shows less splits, cracks and wind shakes. The bole is less apt to break and can be allowed to dry out gradually. Further, root-breeding insects don't find any incubators and agricultural use is facilitated.

Disadvantages are: greater expense, more tools, axes ruined in cutting roots, extra saw cut required to sever the butt log from the roots and, above all, the delay in finishing the logging job.

C. Criteria of a good method:

- I. Danger to workmen.
- II. Total net value obtained.
- III. Wastefulness.
- IV. Possibility of throwing the tree in the desired direction.

D. Pollarding before felling:

The branches or the tree tops in European logging are frequently lopped off before felling, for the following reasons:

- I. The younger generation of trees surrounding the tree to be cut receives less injury.
- II. Lopped trees touch the ground all along the bole at one and the same time. Hence no danger of the boles breaking or splitting. In addition, a reduced crown causes the tree to fall with decreased force.

E. Felling rules:

- I. The trees must be thrown in such a way as to do least damage to themselves, to surrounding trees and to undergrowth.
- II. The felled tree should lie in a position allowing of easy dissection of bole and of easy removal of logs.
- III. Operations must be stopped during storms and blizzards.
- IV. Trees over 6 inches in diameter should be sawn down, coppice woods excepted.
- V. No more trees should be felled than can be worked up within reasonable time after felling.
- VI. The stumps should not be higher than the tree's diameter.
- VII. All trees marked for cutting, and none else, must be cut.
- VIII. The tops should be swamped so that they may come in contact with the ground.

§ VII. DISSECTING THE BOLE OF THE TREE.

A. Purpose of dissection.

- I. Reduction of freightage.
- II. Better adaptation to different methods of transportation required for different assortments.
- III. Better accommodation of buyers requiring different assortments.
- IV. Obtaining manageable size of logs and wood.

As much net value should be obtained from the bole as possible. Waste is advisable wherever it pays to waste.

In no forest on earth is all the woody substance produced marketable. The amount of offal (waste, debris) depends merely on the expense of transportation to markets within nearest reach. It is better to waste wood than to waste money. The modern lumberman gathering logs of 4 inches diameter and the modern forester objecting to any waste frequently neglect this rule.

B. Factors influencing the dissection:

- I. Requirements of the market governed by custom.
- II. Distance from market: the longer the distance, the better must be the quality of the product.
- III. Locality (f. i. steepness of slope; swampiness).
- IV. Local laws (f. i. in North Carolina relative to 8-foot firewood).
- V. Available means of transportation and their construction.
- VI. Freight rates varying with the degree of conversion.
- VII. Size of cars and wagons.
- VIII. Length of mill carriage and of feedworks.

C. The main divisions of woody produce obtained from dissected boles are:

- I. Piece stuff, i. e. logs, blocks, construction timber, sold by the foot, the standard, the pound.
- II. Numbered stuff, i. e. poles, posts, mine props, scaffolding poles and shingles, boards and staves, sold by the dozen, by the hundred, by the thousand etc.

- III. Space stuff, i. e. industrial cordwood (for insulator pins, bobbins, pulp, tannin etc.), tanbark and fuel, sold by the cord. In the case of bark, 2,240 lbs. are usually considered the equivalent of one cord.
- D. The specifications governing the dissection describe:
- I. The dimensions, i. e., the range of length and diameter desired for each section obtainable.
 - II. The quality of each section and the defects allowed and prohibited therein.
- (a) Saw logs for lumber.
1. Dimensions. Douglas fir on the Pacific coast used to be cut in logs 24 ft. long. The minimum diameter permissible was 30 inches.
Spruce in New England is often cut 13 ft. 4 inches long with a diameter of 6 inches and up.
For yellow pine logs, any length and any diameter over 8 inches are permissible.
Hardwood logs have a length ranging from 6 ft. 4 inches to 18 ft. 4 inches, arranged in intervals of 2 ft. Odd lengths are scaled down. A deficiency of $\frac{1}{4}$ ft. in length of board or less is, however, often disregarded.
Export logs of yellow poplar are 8 ft. and 16 ft. long.
Jack pine logs for cheap box lumber are often cut 6 feet 6 inches long, the diameters ranging from 4 inches upward.
 2. Treatment. Saw kerfs at either end of log should be made perpendicular. Branches should be swamped off, knots cut level and laid open. Bark in the case of conifers is frequently peeled off in Maine and in Europe. Bark rings are sometimes left at the ends. Defects of bole must be concentrated in one log, or must be sawn out. Nosing is required for loose driving and for snaking. Painting of end faces with red lead is prescribed for export logs. Very heavy logs are sometimes split in two. Putting logs on sticks to prevent spoliation of sap and to reduce specific gravity is often advised.
- (b) Blocks for woodenware.
- Poplar, for large bowls, must be entirely free from defects. White pine blocks are often cut between the whirls of branches.
- (c) Hub blocks must be butt logs, the length allowing to cut either two or four out of the block.
 - (d) Construction timber is hewn according to local requirements. Minimum diameter at small end most important. Construction timber abroad is sometimes whip sawn.
 - (e) Poplar and walnut squares run from 4" x 4" to 10" x 10". They are whip sawn in the backwoods of western North Carolina.

- (f) Telegraph poles. The smallest diameter, the diameter at or close to the big end, the length, crooks and treatment of bark must be considered. Sometimes pointing of the small end is specified.
- (g) Fence posts. Species, length, smallest diameter, straightness, method of manufacture etc. must be considered. Usual length is $6\frac{1}{2}$ feet.
- (h) Railroad ties. Specifications are very variable. Face is usually from $6'' \times 6''$ to $7'' \times 9''$. Sawed railroad ties are used, especially in the yellow pine section. Great waste in hewing ties from trees just too small to yield two ties. Specifications cover allowance of sap, wind shakes, wany edge and dote.
- (i) Shingle bolts. Lengths are multiples of $16''$ and $18''$, usually.
- (j) Mine props. Middle diameter from $3''$ to $8''$.
- (k) Stave and heading bolts. Basswood heading bolts used in Michigan. Length $18''$ or $37''$ and diameter not less than $8''$. If from $12''$ to $18''$, split into halves. If over $18''$, split into quarters. White oak bolts used at Wilmington measure $36''$ for stave bolts and $24''$ for heading bolts; core must be hewn out; minimum face at inner edge $4''$.
 Heading bolts for sugar barrels in the Adirondacks consist of spruce cut in lengths forming multiples of $22''$ with a diameter minimum of $6''$.
 Stave logs for sugar barrels consist of birch, beech and maple, the lengths forming multiples of $32''$, with a diameter minimum of $8''$.
- (l) Bolts for carriage spokes. Material is black or shellbark hickory, white oak, white ash and post oak strictly free from imperfections. Minimum diameter $12''$; length $6\frac{1}{2}$ feet, $7\frac{1}{2}$ feet, $8\frac{1}{2}$ feet and so on.
- (m) Paper pulp. Logs scale $6''$ and upwards; no dead timber. In the State of Maine pulp logs are peeled in the woods.
- (n) Veneering blocks. Hardwoods preferred, of the biggest possible diameter, but certainly over $18''$ diameter. Blocks from 2 to 6 feet long.
- (o) Tannin extract wood. Length of wood 5 feet, split from logs 10 inches and over in diameter. Wormholes allowed. Fibre must be absolutely sound. A cord consists of 160 cubic feet.

Higher price for peeled wood. Butt logs preferred. Cutting of saw logs out of same tree forbidden.

- (p) Fuel cordwood. Advisability for piles to contain one cord. Weight of pieces should be such that one man can lift them easily. Splitting facilitates the process of drying; in pine wood it also prevents rotting.

CHAPTER III. TRANSPORTATION.

§ VIII. TRANSPORTATION WITHOUT VEHICLES ON LAND.

The following methods of such transportation are en vogue:

- A. Carrying stove wood, pulp wood, extract wood etc. on men's shoulders, a method of transportation very largely used abroad and in India. Carrying distances abroad range up to one-eighth of a mile. In India railroad ties are carried by the Hindoos over much longer distances.

"Stretchers" are sometimes used where slope is not steep, or "timber carriers." Morley Bros.' lughooks are used in America.

At Biltmore firewood is carried to the roads over an average distance of 150 feet on men's shoulders.

- B. Dragging logs by human force where vehicles or water is near and where produce does not weigh over a ton. The front end of a log is placed on a tray (lizard) to prevent it from boring into the ground.

Barked or peeled and well trimmed logs are easily dragged. Silviculturally, dragging is, of course, inferior to carrying of wood products.

- C. Rolling logs by human labor is necessary almost everywhere. Peavy, cant hook and "krempe" are used for the purpose. On a slope of about 15 %, after removing obstacles, logs will roll easily.

Shingle blocks, stovewood blocks and other short round wood may be spanned in a frame. This method of transportation badly damages young growth and trees left standing.

- D. Shooting logs down chutes.

A dell in the slope of 30 % or more is often filled with (peeled) logs; then the top logs are shot down the dell over the other logs below.

Three kinds of chutes proper may be distinguished:

- I. Pole chutes;
- II. Board chutes;
- III. Earth chutes.

I. Pole chutes have been largely used in the United States, costing about \$300 a mile. They are said

FOREST UTILIZATION

to last from seven to ten years and should have the following grades:

	For long logs.	For short logs.	For railroad ties.
Dry chute	15-20%	25-35%	26%
Iced chute	4- 8%	8-12%	6%
Watered chute	3- 6%	5- 8%	

Heavy curves must be avoided and the outside of light curves fixed with a number of "saddle logs."

Pole chutes consist of a trough made of four to six poles. The pole chute is about three feet wide and requires cribs or yokes for a foundation where it is not laid on the ground.

- Water, ice and soap are used for lubrication. Chutes made of hardwoods are said to run smoother than those made of conifers, owing to the greater elasticity of conifers. Where the grade is light, poles should be peeled and hewn on the inside. The grade of inlet must be very steep; the outlet should open into a pond. Frequently, when the job of chuting is finished, the poles or ties composing the chute are shot down themselves, thus dissolving the chute.

II. Board chutes, which are frequently movable, consist of 1-inch or 2-inch boards. They are used in carrying firewood and other short stuff down slopes of 25% to 35%. The rougher the produce, the steeper must be the grade and the wider and smoother must be the trough. Sprinkling is required during dry weather, sanding during wet spells.

III. Earth chutes. These resemble snaking roads of a steady grade, which grade must be:

(a) Where snow or ice crust is available, 8 to 10%.

(b) Where split cross ties are used, laid about 5 feet apart; for logs 16 feet long or longer, from 10½ to 18%.

(c) Where dry earth is used, 25% and over.

Road poles must be used on the valley side, especially so in curves, and bridges must cross all the gullies.

E. "Roping" is a method employed for moving long and heavy logs in the "Black Forest." A rope is fastened at the small end of the log to a ring dog and swung once or twice around the stump of a tree nearby. The log is started by the "krempe," and its speed is controlled by loosening or tightening the loop around the tree. When the rope is run out

it is fastened anew, after stopping the log, to a tree lower down on the slope. The best slope is about 35%.

F. Snaking logs or skidding logs.

- I. Attachment by chains 12 to 16 feet long and $1/3$ inch to $1/2$ inch thick ending in dogs. When a chain link breaks, a "cold shut" is put in its place (cost \$3 per 100 for $1/2$ -inch chain). For smaller logs skidding tongs are used in place of dogs, attached to main chain by three rings, swivel and hook, and costing, per dozen, about \$50.

In the case of horses, stretchers are used to prevent the traces from hurting their legs.

On muddy soil, the nose of the log is frequently placed on a tray, or a lizard, or a triangle.

Snaking dogs are usually hand made and should be driven by a maul. Plain points on dogs seem to be preferred. Logging dogs 10 inches to 12 inches long are quoted at \$15 per dozen.

- II. Animals. For long distance hauling, mules or horses are preferred to oxen. Ox harness is rarely used. In the South three yokes form a "team" usually, the chains running from yoke to yoke. Leaders (oxen) require special training. The teamster manages the yokes of oxen by shouting, applying the whip as little as possible.

III. Roads for skidding or snaking.

- (a) Uphill grades must be strictly avoided; even level stretches are disastrous. The grade depends on the season of usage. Where ice and snow are available 1% or 2% are ample. On dry rocky ground 50% is the maximum. On the average, for "Biltmore" conditions, 20% seems best.

- (b) Curves must be strictly avoided, especially "inside curves" skirting a gully. Herein lies the greatest difficulty of snaking road building in sections where the mountain slopes are deeply gullied.

- (c) In the Appalachians the surface of the road is $2\frac{1}{2}$ to $3\frac{1}{2}$ feet wide and road poles laid on the valley side prevent the logs from jumping the road.

Swampy and moist places are corduroyed lengthwise with the road. Creeks must be bridged. It must be kept in mind that one bad spot in a snaking road requires the use of additional teams over the entire length of road.

Regular troughs made of two strong poles resting on cross ties are used in Pennsylvania, where grade is deficient and distance long. Out West cross ties 7 feet apart are placed on the road. In both cases long log trains are formed. It is claimed for such trains that the pull or strain on the animals is evened or equalized, some logs sliding down hill while other logs of the same train overcome impediments.

- (d) Means of lubrication are: Sprinkling with water; laying cross ties or length ties; peeling of logs; greasing the ties.

Means of braking the logs are: Sprinkling earth, sand, hay and branches on the road; throwing chains on the road, or tying chains around the logs.

- (e) Snaking distance. Snaking distances range up to one mile (usually), averaging about one-third of a mile. Where many logs, say 30,000 board feet of logs or more, must be transported on the same road over an average distance greater than one-third of a mile, other means of transportation are usually preferable to snaking.

In the Appalachian hardwoods the expense for 1,000 board feet snaked over $\frac{1}{2}$ -mile amounts to about \$4. In the Adirondacks skidding costs 40c to 50c per 1,000 board feet, the distances being short, since the logs are merely skidded to the skidways arranged alongside the sleigh roads.

G. Drums.

- I. Hand drums or winches are used for yarding logs and especially for hoisting logs up hill on steep inclines, the distances not exceeding 300 feet. G. B. Carpenter quotes single "drum grabs," weighing 275 pounds and having 2 tons power, placed in strong oak frames, at \$27. Power capstans might be used for the same purpose.
- II. Drums with horses as motive power are used in eastern Tennessee for hoisting logs up to the rim of the sandstone plateaus.
- III. Steam power is now universally used out West in connection with drums known as "Bull Donkey" and "Donkey" engines. Skidding or snaking roads are usually dispensed with. Steel cable ($\frac{3}{4}$ -inch plow steel) is used on the drums. The distance of haulage should not exceed 1,200 feet. The main cable is pulled out by a

$\frac{1}{2}$ -inch endless cable ("tripline") running into the district to be logged over a number of tackle blocks. Zig-zags can be made by using tackle blocks on the hauling line as well. One engineer and one fireman are all the crew required in addition to two loaders. Frequently the engine loads logs on railroad cars at the same time. The engine's cylinders are about 8 inches by 10 inches. Engines are moved from place to place by their own power. Price for an engine f. o. b. Biltmore is \$1,400. Boilers are of the upright type. The wire cable is usually made of 6 strands, each containing 19 wires, wound around a hemp center. Running cables should never be galvanized. The proper load of a cable is only one-fifth of the breaking strain in tons. Steel ropes (cables) have twice the strength of charcoal iron ropes. One-inch steel wire cable costs 19c a foot, weighs about $1\frac{1}{2}$ pounds per foot and has a breaking strain of 33 tons. Its proper load is 6 tons only. Silviculturally this method of steam logging is objectionable.

§ IX. WATER TRANSPORTATION.

Logs or lumber are driven loosely or floated in rafts.

- A. Loose driving is a method used in eastern America for short logs, pulp wood and firewood.

Specific gravity of material driven must be reduced below 1.00.

Heavy species might be deadened a year before driving, like teak in India, to attain this end, provided that attacks from fungi or insects, on the deadened trees, are not to be feared.

Under favorable conditions, where the creeks are narrow and well watered, no special arrangements for driving are required.

- I. Splash dams. The proper site for a splash dam is the rocky narrows of a water course below a broad bottom of little fall, or else at the outlet of a natural lake.

Large splash dams must be placed on rock foundations. The expense of building increases at a cubic ratio with the height of the dam.

Splash dams built in tributaries are preferable to dams in the main creek, provided that they can be filled quickly enough.

A system of dams of first, second and third importance is frequently formed.

The distance of effectiveness of a dam depends on the size of the water reservoir, the width of the water course below the dam, and the rapidity of its fall. On "Big Creek" in Pisgah Forest the distance of effectiveness was four miles.

Splash dams meant to be permanent must be built of stone and are exceedingly expensive.

The usual splash dam consists of timber cribs filled with rock and joined by logs laid crosswise. The front of the dam must be slanting and is covered with a double layer of boards. The gateway of the dam must allow of rapid drawing (or opening) of the basin. The gates are either constructed barn door fashion, held in place by a strong key and lever, or consist of (vertical) piling, the individual piles to be lifted by a crowbar or drum. Half-moon-shaped gates are used in the Lake States and in the Adirondacks.

The smaller the water supply and the greater the pressure the tighter must be the gate.

The expense of a splash dam of the first order is from \$1,000 to \$2,000. A timber splash dam lasts from six to ten years.

Frequently additional small gates are made to give a "fore-water," meant to loosen the logs in the creek below the dam. The actual splash rather presses the logs down the creek, instead of floating the logs.

- II. Dams in the creek bed itself are sometimes required to raise the water in a shallow section.
- III. Before driving begins, the creek bed must be cleaned out by removing old log jams, leaning trees and huge boulders. Sharp bends of the creek must be cut through, so as to straighten the creek bed.
- IV. Fixtures along the bank of the creek are required to prevent logs from getting smashed when striking a bluff; from being thrown on the bank in a curve of the creek; from destroying the banks, and further to prevent the spread of water and loss of force, where a splash is expected to overrun adjoining flats.

Such bank fixtures consist of:

Pole cribs filled with rock, the poles lying solid, pole to pole, toward the creek, or of inclines of poles laid horizontally, supported by strong uprights from behind, or of alternating layers of fascines and stone, joined together by strong piling driven into the ground; or, finally, of brush laid on the sloping bank and irregularly covered with rock.

- V. The bottom of the creek is sometimes paved with stone or poles laid lengthwise, where the bottom consists of clay. This is especially necessary in artificial channels or canals dug through sharp curves of the creek, or dug close to the connecting booms.
- VI. Booms.

- (a) European booms are rake booms, the teeth of the rake formed by strong palings.

The tops of the teeth are connected by strong

timber bars, which are held in place by stone cribs.

These booms are stretched diagonally across the river. The logs or wood are merely diverted by the boom and forced into an artificial side canal ending in a reservoir near the mill or depot.

A gridiron or sieve, filtering the river at a waterfall and retaining the wood on the gridiron, has been used in the Tyrol by the Bavarian Government for many decades.

- (b) The American boom consists of two sections, an upper shear boom spanning diagonally across the stream and a lower storage boom stretching for miles along the river bank, where the water is quiet and the current slow. Both booms are floating booms consisting of one or two strings of prime logs, the logs joined by anchor chain. The booms are kept in place either by wire cables $\frac{3}{4}$ -inch to an inch in diameter or by stone filled cribs. It is advisable to have the storage boom consist of independent sections so that the breakage of the boom empties one section only.

Frequently several mill concerns form boom companies.

The logs are lifted out of the booms by "jack works" or "log hoists."

VII. Driving and splashing must be considered a backwoods method, applicable to very cheap stumpage. It is not practiced on the Pacific coast, where we have very cheap stumpage, owing to the size of the logs and poor water facilities. Where there are plenty of natural lakes, in a coniferous country as in the Adirondacks, Michigan and Minnesota, the method continues to be practiced.

Splashing is the more advisable:

- (a) The smaller the specific gravity of timber.
- (b) The shorter the logs.
- (c) The lower the stumpage price.
- (d) The more reliable the rainy season and the gauge of the river.
- (e) The better the natural conditions are at the dam sites, in creek bed and at boom site.
- (f) The poorer the natural conditions are for railroad building and wagon road building.
- (g) The less land owned by other parties is traversed by splashed logs.

- (h) The more saw timber improves while being bathed in running water.
- (i) The longer the distance.
- (j) The more inclined the log owner is toward taking risks and the less affected he is by reduced fertility along the river bank.

Remarks: In the pine woods of the South in olden times ditches were dug about three feet wide, connecting stumpage with swamps and rivers.

The outlay per 1,000 board feet in splashing and driving is from 50c to \$1 (for manual labor only).

River driving of cord wood at Biltmore from the upper end of the estate to Asheville, inclusive of piling at the boom, costs 50c per cord.

B. Rafting.

Loose logs are tied into rafts at a place where the flow of the creeks and rivers begins to be more gentle.

Only rarely are rafts used in connection with splash dams on very rapid streams. (Black Forest.)

According to the size and species of logs, rafts are formed either with the logs lying with the stream (longleaf pine rafts etc.), or with the logs lying square to the stream. In this latter case the length of the logs should not exceed eighteen feet. Square rafts consist usually of hardwood logs.

I. Logs with the stream.

- (a) The logs are joined into raft sections, each section one log long; the narrow end of the log points down stream; joining usually by rope, cable or chain; ring dogs or eye dogs are used, or wooden pins in connection with auger holes.
- (b) At the tail section the rear ends of the logs are allowed to spread fan shaped.
- (c) The raft is directed by long rudders (sweeps), by brakes (poles which are pressed against the bottom of the river) and pike poles.
- (d) The width of the raft and the tightness of binding depend on rapidity of the stream, span of bridges to be passed, sharpness of bends of river and width of river bed.

Remarks: Ring dogs for rafting weigh about 1½ pounds, are four inches long and have a 2½-inch ring, through which rope is run. Price 10c apiece.

Eye dogs are made of ½-inch round iron, are six inches long and cost 6c per pound.

II. Logs square to stream.

- (a) The ends are joined by cross poles, sometimes imbedded in the logs and held in place by pins

driven into auger holes, or by chain rafting dogs, consisting of two small wedges joined by two rings and five links of chain. Weight $2\frac{1}{2}$ pounds. Price 12c.

- (b) The logs must have about equal length. Species not floatable otherwise are tied up with floaters of pine, yellow poplar, cottonwood and linden.

In the Mississippi two oak logs are floated by three cottonwood logs.

- (c) Such rafts are naturally stiff and cannot be used on rapid streams. The narrow and wide ends of the logs should alternate so as to keep the sections straight.

C. Flumes.

Flumes resemble chutes made of boards. They must be water tight. They are largely used on the Pacific coast.

- I. A V-shaped cross section has proven best. Side boards are equally long, about 16 feet, in double layers. Angle of the V = 110° . Top width is 3 feet to 4 feet.
- II. An even constant grade of from 1% to 3% is necessary, also slight curves and large water supply, which is often obtained from artificial reservoirs. High trestle bridges are sometimes required.
- III. The main flume has a number of tributaries. A crew is stationed along the flume; special attention is given to the inlets of tributaries. Patrol trails along the flume.
- IV. The fluming of logs is said to be unsuccessful. In the West, anyhow, the size and weight of the logs would prevent fluming. Nowadays either planks or heavy dimension stuff; to be resawn at the outlet of the flume, are sent down. Only coniferous lumber is flumed.

The lumber in the flume forms one continuous chain; this arrangement prevents the lumber from sticking and catching at the side walls of the flume.

- V. Famous flumes are those at Chico—Sierra Nevada range (40 miles of flume), the flume of the Bridal Veil Lumber Company and the Great Madeira flume, all in California. The last is 54 miles long and has a daily carrying capacity of 400,000 feet of lumber. It cost only \$5,000 per mile.

The scarcity of water in California is the greatest obstacle to the continuous use of flumes.

D. Water transportation over lakes and sea is effected in the following way:

- I. In the "fjords" of the Pacific coast, logs standing upright are chained together so as to form a stockade in which the other logs are similarly placed, filling it tightly. Such stockades hold about half a million board feet of

lumber at a time and form a seaproof raft, pulled to the mill by tugboats.

- II. Logs chained together in the form of a cigar-shaped raft after various patterns have proven a failure. These rafts were taken from the Oregon and Washington coast to San Francisco, being launched like a steamboat and towed by tugboats. To judge from newspaper reports cigar-shaped rafts of boards have proven a success.

The steamship companies consider cigar-shaped rafts a great danger to navigation.

- III. In carrying logs across the lakes in the Adirondacks and Lake States, light ring booms are used. The logs are placed in such booms at "the landing" and are rafted (driven) to the outlet of the lake either by wind, current or tugboat.

§ X. TRANSPORTATION ON LAND WITH VEHICLES.

A. Sleighs and sleds.

- I. Hand sleighs, home made, very light, are frequently used abroad at grades of 10% and more. Man sits in front of load and directs with legs and side brake. On steep slopes such sleighs are used in summer as well. Fifty cubic feet is an average load for one man. The workman carries his sleigh back uphill on his shoulders for the next load.

Sleighing roads for summer sleighing frequently have cross ties at short intervals to be kept greased at slight grades.

- II. The American sled has nothing in common with the European sled. A team of horses is always used for motive power.

The sleigh, or sled, consists of two sets:

The front set has a tongue of rock elm or oak and a front roller in which the tongue is set. Runners are 7 feet to 9 feet long, 3 inches to 4 inches wide, shod with $\frac{1}{2}$ -inch steel shoes or cast iron shoes either below only or both above and below; they are either slightly convex or flat. The front of the runner should be of a natural curve or crook, not hewn. Material is white oak. The cross beams, either ironed or plain, rest in saddles or nose plates with knees.

The "back roll" of the hind set is coupled to the front set by chains attached to the center of the front cross beam. There is no tongue to the hind set.

- III. Log binders are used on loading chains to take about half a foot of slack out of the chain, unless the same end is secured by poles and the twisting of the binding chain.

- IV. The usual load of a sleigh is five tons, while a wagon carries only two tons on an average.

The actual load depends on distance, grade and condition of road. In the Adirondacks about 2,000 board feet form a load; in Ontario 1,500 feet of white pine or spruce.

- V. Sledding roads are constructed in the Adirondacks at an expense of \$25 to \$150 per mile. The sledding distance is said not to exceed three miles, usually. The teaming expense is about 10c per 1,000 board feet per mile.

The relative distance of snaking and sledding depends on configuration and density of stand. Sledding roads are preferably built on swampy soil. Heavy grades require a heavy outlay for sanding; insufficient grades a heavy outlay for icing. Carelessness in surveying sleigh roads is extremely expensive in short, mild, snowless winters. The modern lumberman surveys his roads with instrument in hand, completing them before snow-fall.

To begin with, an empty or lightly loaded sleigh is run over the road to mark and set the track.

B. Transportation on two-wheelers.

- I. High wheelers, wheels 7 feet to 10 feet high, are used in the pineries of the South, in California, and to a certain extent in the Lake States for hauling coniferous logs of 1½ feet average diameter and of extra long length.

Logs are loaded underneath the axle, either by using the tongue as a lever or with the help of a second axle having the form of a winch (Southern method).

Logging distance in the South not to exceed half a mile, average one-quarter of a mile. Expense \$1 per 1,000 board feet.

The best makes are:

Bodley Wagon Co., Staunton, Va.; Snyder Wagon Co., Shreveport, La.

Prices from \$100 to \$150.

- II. Low wheelers, usually called "Bummers," the wheels consisting of a solid tree section held by iron rims 1½ feet in diameter. The top of the axle is even with the top of the wheels. The tongue is only six feet long and merely used as a lever in loading. The bumper is pulled by chain attached to point of tongue and is loaded by placing axle parallel to log close to center of log, with the tongue standing perpendicular, the log being fastened to the axle by short chains and dogs.

FOREST UTILIZATION

High and low wheelers are used on undulating ground for downhill pull on soil free from rock, swampy places, debris and brush.

- C. Log wagons. Log wagons are entirely used for transportation in the old country, where the forests are traversed by a network of well graded stone roads. Wagons are always hand-made, of light weight and carry up to 17 tons of logs. In carrying long boles, the front and hind trucks are separated. Steep curves can be made if the rear ends of the logs are fastened underneath the axle of the hind truck.

The American wagon has a track width, from center to center of tire, of 4 feet 6 inches or 5 feet.

Wheels are usually made entirely of white oak. The wood is well seasoned. The tire is 3 inches, 5 inches and over. Front and hind wheels usually equally high—2 feet to 3½ feet. Eight wheelers are now widely advertised.

Skins are preferably made of welded steel instead of cast, 3 inches to 5 inches in diameter.

Steel axles have not proven a success, owing to difficulty of repairs in the backwoods. Bolsters should reach to or over the top of the wheels.

The reach should allow of changing distance between front and rear set.

Main requirements are:

- I. Strength.
- II. Possibility of repairs in the woods.
- III. Low point of gravitation.
- IV. Ease of loading.
- V. Ease in turning.
- VI. Light weight of wagon itself.

Prices for log wagons range from \$80 to \$200 according to carrying capacity. Weight from 800 to 1,800 pounds. Carrying capacity 1½ to 5 tons.

- D. Traction engines. Traction engines are largely used abroad and have proven very successful recently in the South African war. In freighting lumber from mill to city or depot they are used in the United States on a small scale, since stone roads seem to be a prerequisite; loose sand, deep mud or swamp are impracticable for traction engines. In Pennsylvania four-wheelers costing \$1,500 for a 16-horsepower compound engine and able to climb 12% grades and to turn 30 feet curves have proven a failure, since the use of traction engines plows the roads during rain.

In the California mountains, where drouth prevails during six months of the year, the three-wheelers manufactured by the Best Company, of San Leandro, Cal., have been largely and successfully introduced. Very high wheels and broad tread cause little injury to the route traveled. The boiler is a com-

bination of upright and horizontal, concentrating weight on the driving wheels and preventing water and fuel from dropping back from the pipes on steep grades. Engines are said to be able to climb 30% grades and to climb over logs, brush, stone etc. Front wheel is for steering only, with front drum for skidding logs by wire cable.

- E. Pole roads. A statistic of 1886 finds in the United States over 2,000 miles of pole roads, using over 400 locomotives and over 5,000 trucks.

- I. The rails are made of straight, preferably coniferous poles, sufficiently trimmed to fit the double flange of the truck wheels. On suitable soil no ties are required, the rail being gradually pressed into the ground.

Sawn rails, preferably consisting of several layers of boards, must be used in curves of the pole road and are still largely used near mills on steep and short grades.

- II. Trucks. The wheels should not turn with the axle. An oval concave rim said to be inferior to a flat rim with heavy flanges.

Each wheel has about 2 inches room for side play. The reach should turn like a swivel in hind and front set, allowing all wheels to stay on the track.

- III. All lumbermen now agree that pole roads are impracticable for locomotives. On sawn rails locomotives are still used, however, when prices of steel are high, grade steep, distance short and use intended for a short while only. Sawn wooden rails do not allow of heavy loads and, consequently, seem unadvisable just for logging by steam engines.

- F. Forest railroads.

- I. Portable forest railroads.

In American lumbering portable railroads are little used. The sections of which portable railroads consist are necessarily light and, consequently, unfit for the heavy traffic of American lumbering. In Europe the sections are usually $6\frac{1}{2}$ feet long, have $2\frac{1}{2}$ feet gauge and weigh 80 pounds. Steel ties are preferable at the ends so as to have the joints supported by ties. The sections are joined by a hook arrangement without being bolted together.

Usually the sections are merely laid on wood roads. Motive power is supplied by gravity, men or horses. Wheel flanges usually on both sides of the rail. Rail sections of trapeze form are sometimes used in building curves. Bridge switches are preferable to split switches.

In the wood yard at Biltmore sections of wooden rails were used, the ties being replaced by iron rods. The

top of the rail was shod with a strip of $\frac{1}{4}$ -inch iron, the ends joined by hook and pin, and by hole and pin. Steel sectional tracks of $2\frac{1}{2}$ -inch gauge are manufactured by the C. W. Hunt Co., New York. The trucks used have the wheel flange outside. Curves and switches are ready made. Straight sections are 6 feet to 20 feet long.

II. Stationary track.

- (a) Grade. A proper survey is very essential. For steep grades (over 7%) a soft rail is required. Grades of 11% are feasible on straight track for locomotives having eight drivers.

High percentage for very short distance is, however, permissible.

Logging roads in the South have grades running up to 15% for uphill traffic, obtaining the necessary impetus by a corresponding downhill grade. The expense of maintaining the track and the frequency of accidents render steep grades highly expensive.

The standard railroads have never over 4% grade.

- (b) Curves. The minimum radius of curves depends on gauge of track; distance between axles of front and hind trucks; length of timber to be carried and grade in the curve. Curvature is measured by the subtended angle, the (secant) chord of which is 100 feet. Standard railroads do not allow of an angle exceeding 10%.

In curves, to relieve the increased friction, and, further, to prevent the trucks from jumping the track, owing to centrifugal force, three remedies are required:

1. Lessened speed and reduced grade.

In practice for standard gauge of 56 $\frac{1}{2}$ inches, for each degree of curvature the grade is released by 0.02%; for narrow gauge by 0.03%.

2. The outer rail is elevated for standard track by $\frac{1}{2}$ -inch for every degree of curvature; for 36-inch gauge (usual narrow gauge) by 1-3 inch for each degree of curvature.

3. The track is widened in curves by 1-16 inch for every $2\frac{1}{2}$ degrees of curvature.

- (c) Rails. The form is usually the T rail. Grooved rails, flat rails, rails inclined toward center of track etc. are freaks merely. In logging rail-

roads the rails are often fastened lengthwise on sawn or hewn stringers, which arrangement allows of light rail. The gauge is measured inside the tops of the rails if the flange is inside, and outside the rails if the flange is outside. If the wheel has a double flange, measure from center to center of rails.

In lumbering operations, the standard gauge (56½ inches) is generally preferred, since heavier loads can be taken and since the rolling stock can be disposed of more readily at the end of operations. Of the narrow gauges 36 inches is best, since the odd gauges prevent ready exchange of addition to and sale of rolling material.

In mountainous sections narrow gauge is preferred. Here the expense of wide gauge track is too high, since it requires flatter curves, smaller grades and largely increased outlay for roadbed.

In standard lumbering operations a heavy (56 pounds) rail is now preferred, the up-keep of track being cheaper, the bed for the track being less expensive and fewer ties being required for the heavy rail. Light rails are so twisted, after short use, that they cannot be sold at second hand. For 36-inch gauge a rail weighing 16 pounds to 20 pounds is best.

Rule for number of tons of rail required per mile:

1. Tons of 2,000 pounds.

Multiply the weight of the rail by $7/4$ and you obtain the number of tons required per mile. For example, 20-pound rail $\times 7/4 = 35$ tons.

2. Tons of 2,240 pounds (after which rails are usually sold).

Multiply weight of rail by $11/7$ instead of by $7/4$.

The price per ton of rail (steel) varies from \$25 to \$35.

The interdependence between locomotive's weight and minimum weight of rail permissible is given by the following equation:

$$\frac{w}{n} \times 8 = r$$

wherein w stands for weight of locomotive in tons; n stands for number of

FOREST UTILIZATION

drivers; *r* stands for minimum weight of rail in pounds.

Estimates of cost of track, exclusive of rolling stock and bridge arrangements, vary from \$1,300 to \$4,300 per mile for easy grading. One-half of the expense in this case is for rails, spikes and splice joints (fish plates).

The grading and laying of track costs from \$300 to \$1,000 per mile for easy grading; and cross ties cost about as much.

Estimate of cost per mile for

1. Sixteen-pound steel rail, requiring

25 tons of rail @ \$32 per ton.	\$ 800.00
1,780 pounds of $3\frac{1}{2} \times \frac{3}{8}$ in. spikes	
at 2c per pound.....	35.60
357 splice joints at 20c.....	71.40
2,640 cross ties at 15c.....	396.00
Grading and track laying.....	500.00
Total	\$1,803.00
2. 40-pound steel rail, requiring 63

tons of rail at \$30 per ton.....	\$1,890.00
4,690 pounds of $4 \times \frac{1}{2}$ in. spikes at	
2c a pound.....	93.80
357 splice joints at 40c each.....	142.80
2,640 cross ties at 25c each.....	660.00
Grading and laying track.....	1,000.00
Total	\$3,786.60

(d) Cars.

Cars consisting of two trucks, of two axles each, form the rule.

The trucks should be very low and should have short distance between axles where curves are heavy. For narrow gauge tracks, special trucks are constructed costing from \$50 to \$80. While steel trucks are more satisfactory in the old country, in America trucks with wooden framing and wooden bolsters are usually preferred, owing to greater ease of repair far from factory.

The bearings are frequently outside as well as inside the wheels, so as to have the frame supported at eight instead of at four points of the two axles. The bolsters, swiveled on the frame, are very frequently much longer (wider) than the axles.

The weight and capacity of logging cars should be as follows:

	<i>Weight in lbs.</i>	<i>Capacity in board feet.</i>
4 wheel cars	3,000 lbs.	1,000 b. ft.
4 wheel cars	4,000 lbs.	1,500 b. ft.
4 wheel cars	5,000 lbs.	2,000 b. ft.
4 wheel cars	6,000 lbs.	2,500 b. ft.
8 wheel cars	6,900 lbs.	2,000 b. ft.
8 wheel cars	8,400 lbs.	3,000 b. ft.
8 wheel cars	9,600 lbs.	4,000 b. ft.
8 wheel cars	11,000 lbs.	5,000 b. ft.

(e) Locomotives.

Logging locomotives are manufactured by the Baldwin Locomotive Works, Philadelphia; H. K. Porter, Pittsburg, Pa.; Climax Mfg. Co., Corry, Pa.; Stearns Locomotive Co., Erie, Pa. (for Heissler geared locomotives).

The price is practically independent of the gauge, being influenced more by horsepower.

Four driving wheels are usually sufficient. On steep grades, six wheels and, on very steep grades, eight wheels are used.

The resistance to be overcome by the tractive force is:

1. Gravity, which increases in exact proportion to steepness of grade expressed in per cent. Thus it is always 20 pounds per ton for each per cent.
2. Friction of the journals and of the wheel flanges against the rails, which depends, aside from curvatures, on quality of the track and of rolling stock. It is at least 5 pounds per ton; it amounts to $6\frac{1}{2}$ pounds for first class equipment; to 20 pounds to 40 pounds for bad equipment, and in extreme cases it rises to 100 pounds.

Tractive force is understood to be one-fifth of the weight, in pounds, on the driving wheels, expressed in tons.

For instance:

Weight on driving wheels 25,000 pounds, divided by 5=5,000 pounds; and 5,000 tons is therefore the tractive force of the engine.

$$F = L(FR + GR)$$

$$= 300 + (.01 + .07)$$

$$= 200 \text{ tons}$$

$$= \text{weight of loco}$$

5.

The hauling capacity of an engine is: tractive force divided by the sum of the frictional and gravity resistance, both expressed in pounds, deducting the weight of the locomotive from the quotient. For example:

Weight of locomotive on 4 driving wheels = 20,000 pounds. Tractive force is 4,000 tons.

First case—Frictional resistance 8 pounds per ton, grade level. Then the hauling capacity equals 4,000 tons over 8 (friction) plus 0 (gravity) minus 10 = 490 tons.

$$\frac{4000}{8+0} \text{ minus } 10 = 490 \text{ tons.}$$

Second case—Frictional resistance same as above, grade 1%.

$$\frac{4000}{8+20} \text{ minus } 10 = 133 \text{ tons.}$$

Third case—Frictional resistance 8 pounds, grade 2%.

$$\frac{4000}{8+40} \text{ minus } 10 = 73 \text{ tons.}$$

The cost of hauling logs on a standard railroad, per carload of 40,000 pounds, amounts to \$5 for distances of one to fifty miles, and to \$6 for distances of fifty to one hundred miles.

Porter's catalogue gives the cost of hauling as ranging from 30c to 60c per 1,000 b. ft. for a logging distance of from five to ten miles. At Chicora, Ala., two standard trains provide daily, together, 100,000 b. ft., coming from a distance of about eight miles.

Small (narrow gauge) locomotives haul from 60,000 to 120,000 b. ft. per week over distances of from five to ten miles.

Where grades are not excessive, a locomotive should cover daily 60 to 80 miles, the hauling distance varying from 2 to 10 miles.

G. Mono rail.

The mono rail portable railway is a French invention (Caillet) and has been tried to a limited extent in India.

It consists of one rail only, resting on steel sole plates at intervals of a few feet, and is laid down direct on the surface of the ground. Rails are joined together by scabbard fish plates. The trucks have two low wheels, grooved

at the rim, the carriage hanging between the wheels a few inches above the rail. Cars are balanced by a telescopic rod and kept in balance, like a bicycle, by the motive power itself, which consists of an animal hitched in a frame alongside of the carriage.

The mono rail system might be applicable in the transportation of bark, cordwood and minerals.

H. Cable way logging.

The logs are suspended from a cable and are not dragged on the ground.

- I. On steep slopes, the grade being 35% to 50%, the logs slide down by gravity, being suspended from two trolley blocks held apart by a strong rod or pole, about 15 feet long. At the upper end of the cable, curved iron rails lead, like a bridge switch, onto the cable. The cable is kept tight by heavy drums, over which the cable runs at the ends. It is said to wear out in about eight years.

The speed of the block carriage is regulated by manila rope, wire or light wire cable, and the empty block carriage is carried backward by the same rope without any motive power other than that of a loaded block carriage going down hill. Proper switches allow the empty block carriage to pass the loaded one at a half-way point. The price of 1-inch wire cable is about 19c per foot.

In Switzerland lines two miles long are found, without any supports. In the Hartz Mountains supports are given every 700 feet and the expense is \$800 per mile for entire equipment.

In Oregon and western North Carolina short cable conduits of this character are in successful use, and in India (in the Himalayas) the most extensive plants of this character are said to exist.

- II. In swamps of the Atlantic coast, where railroading is difficult, the system of the Trenton Iron Co. and of the Lidgerwood Manufacturing Co. have been tried which move the block carriage holding the logs in suspense over a cable either by steam power or by electricity.

- (a) In case of steam power, the engine is placed either on a scow swimming in the swamp, in the river, in the logging canal cut by powerful dredges, or on a railroad car, the logging outfit costing about \$7,500 per mile (including lateral rig), consisting of:

One-inch carrying cable and double traction rope;

FOREST UTILIZATION

Double block carriage with differential hoist and log grip;

Brackets, supporting the cable;

Steam engine with hoisting drum;

Lateral hauling-in rig, by which logs are dragged to the main carrying line over distances running up to 1,000 feet.

(b) In case of electric power, the outfit, costing \$6,200 per mile, consists of:

One-inch carrying cable and ½-inch single current rope, which is swung thrice over a grooved sheave;

Generating machines and 20-horsepower steam engine;

Carriage, including the log support and the motor with sheave, which has a speed of six miles an hour.

I. Loading arrangements are required, wherever vehicles are used, except for bummers.

I. Loading on wagons.

(a) Sliding logs from a higher bank onto vehicles.

Only one layer can thus be loaded conveniently.

(b) Rolling logs up an incline, either with peavies or rope, the top of the incline resting on the tops of the wheels.

(c) A (drum) winch in front of wagon, incline behind wagon, pulling logs up by rope.

(d) Tackle block attached to a tree, the wagon standing between the tree and log; the end of rope attached to outside wheel and the free end pulled by animals.

(e) The skidway scheme. Trained horses running on prepared track opposite the skidway. Two poles leading from skidway to wagon; rope running from outer wheel of wagon under and around the log and back over the wagon to the horses.

(f) A jack, consisting of a gear wheel and a toothed iron rod.

(g) German lever arrangement.

II. Loading on railroad cars.

Additional methods.

(a) A huge tripod and Weston's differential hoist.

(b) A drum and wire cable rig, the loading cable running over a tackle block suspended over track.

(c) Cranes or derricks as used on the harbor docks, a special make of which is known as the

"Decker log loader." There is some mechanical difficulty in constructing loaders of a sufficient angle of leverage.

§ XI. CHOICE BETWEEN THE VARIOUS SYSTEMS OF TRANSPORTATION.

Conditions governing the selection of means of transportation are:

- A. Topography. Steep grades make it advisable to send products down by their own weight, so that animals and vehicles need not reascend the grade.
- B. Periodicity of rain and snow fall (West Virginia for spring rains, Lake States for snow fall, California for spring drouth) invite the use of means relying on water supply, on layers of snow, on dry soil.
- C. Rocky soil entails blasting expenses and thus bars railroading and road building, Wet or swampy soil requires an artificial surface on which means of transportation are placed.
- D. Existence of drivable creeks and rivers, their grade, rockiness, curves, steadiness of flow, the spans and number of bridges crossing them, the danger or help expected from freshets are factors bearing on the advisability of water courses used as means of transportation. Electric power derivable from water falls might be used as motive power in days to come.
- E. Availability of building material in the forest, especially the price of rails and ties and quality of stone etc.
- F. Total amount of stumpage, and stumpage per acre to be carried away from a given locality annually, periodically or once only.
- G. Maximum weight and size, also average weight and size of pieces to be handled.
- H. Price and effect of day labor and prospects of changing prices under the influence of labor laws and socialistic legislation.
- I. Relative price of team labor and of manual labor. The ratio between price of hand labor and team labor abroad is 1 to 8. In this country it is 1 to 2½; in Lake States even less, viz., 1 to 2.
- J. Condition of existing public means of transportation; roads, railroads and navigable rivers.
- K. Laws relative to rights of way and relative to damage inflicted on outsiders in the course of transportation, i. e., by splashing logs; raising water level of lakes and thus destroying trees etc.
- L. Mileage of the various links forming the chain of transportation and speculation as to the building of additional public links of transportation.
- M. Silvicultural considerations, or choice between conservative and destructive lumbering.

Donkey engines are the destroyers of any second growth left on the ground and should be used only in clear cutting.

High two wheel logging carts are used abroad to save young growth.

FOREST UTILIZATION

- N. Possibility and amount of damage to logs and loss of logs in course of transportation. Loss of bark. Loss of sap-wood. Deterioration by fungi and insects. Theft. Loss of interest on value of logs.
- O. Regularity and reliability of means of transportation.
- P. Possibility of using the means of transportation for purposes other than carrying forest products (access to mines and farms; passenger traffic; supplies for lumber camps; use of snaking roads as fire lanes, patrol trails, sport trails).
- Q. The general political and economic condition of the country (settled or unsettled); the possibility of financial surprises.

Part II. Manufacture of Wood Products.

CHAPTER IV. FOUNDATIONS OF MANUFACTURE.

§ XII. THE AMERICAN FORESTER AS A LUMBERMAN.

In the old country, a large portion of the products grown in the forest go to the holders of prescriptive rights (easements). The balance is sold either under private contract or at public auction or under sealed bids.

In France, standing stumpage is sold, while in Germany the trees are dissected, at the owner's expense, into assortments required by the local manufacturing trades.

Usually, in the old country, the raw products of the forest are not refined by the forest owner. The forest industries are in the hands of parties who do not own or control an acre of woodland.

In Canada, timber leases or timber limits are sold at public auction. The purchaser pays, aside from the auction price, an annual rental (so called ground rent) and, further, for every 1,000 feet b. m. cut, a specified royalty. Neither ground rent nor royalty is object of the auction sale.

On the forest reserves of the United States auction sales are meant to form the main method of disposal of forest products, exceptions being made only in the interest of local residents.

The private owner of woodlands in the United States, and his forester, is and will be compelled to be a wood manufacturer for many a year to come.

The lumberman need not be a forester; but the forester must be a full fledged and experienced lumberman. Woe to conservative forestry in the United States if the forester, satisfied to give theoretical advice, fails to devote to lumbering and manufacture the larger part of his energy!

§ XIII. MOTIVE POWER.

Motive power is supplied by:

- A. Actual animal power said to be used in Texas for running portable saw mills.
- B. Wind-mills, which furnish an insufficient and unreliable power.
- C. Water-mills. The horse power of falling water is:

$$\frac{v \times h \times 62.5}{33000},$$

wherein stands: v for volume of discharge in cubic feet per minute;

and h for height of fall in feet; and

wherein 62.5 represents the weight of a cubic foot of water and 33,000 equals one horsepower per minute.

For example, if cross section of a race is = 2 sq. ft., water velocity = 660 ft. per minute, height of water fall 30 ft., then the power is:

$$\frac{2 \times 30 \times 600 \times 62.5}{33000} = 75 \text{ H. P.}$$

Water wheels are either vertical, i. e., overshot, breast or undershot wheels, or horizontal wheels, i. e., turbines.

- I. Overshot wheel. Effective power is 60% to 70% of possible power. The proper velocity at the circumference is 5 feet per second and at best if it is equal to 0.55 of velocity of water.

In falls of 20 feet to 40 feet and over, overshot wheels are more effective than turbines.

The buckets, framed by the shrouding, should be curved or elbowed and not radial. They should have a capacity three times as large as the volume of water actually carried, a depth of 10 inches to 12 inches and a distance apart, from center to center, of 12 inches.

Ventilated buckets, having holes in the bottom and allowing air to escape, are said to have a better effect.

It is difficult to transform the slow speed of an overshot into the rapid speed required for a circular saw. Transformation is either by countershaft or by cog wheel.

- II. The breast wheel has an effective power of from 45% to 65%, is best applied to falls of from 5 feet to 15 feet and to a discharge of from 5 to 80 cubic feet per second. While in the overshot the water works by weight only, it works in the breast wheel largely by impact.

The velocity of wheel should be such as to fill the buckets to 0.5 or 0.6 of their volume. The buckets here are usually called blades and must be ventilated.

The wheel runs in a curb or mantle, formed by the inclined and cased end of the sluiceway.

The distance of the blades, from center to center, should equal the depth of the shrouding, both being from 10 inches to 15 inches. The clearance between the curb and the shrouding must be at least half an inch.

"High breast" wheels are semiovershot and "low breast" wheels are semiundershot wheels.

The "flutter" wheel is a low breast wheel of small diameter and high speed. It is largely used in western North Carolina for saw-mill purposes where water is plentiful and fall about 12 feet.

- III. Undershot or current wheels have an efficiency of from 27% to 45% only and are usually kept anchored in rapid streams, so as to be independent of water gauge. No buckets, but long blades instead.

The diameter of the wheel is from 13 feet to 16½ feet; usually 12 blades, the depth of which is 3 feet to 4 feet. The blades should be completely submerged when passing underneath the axle.

- IV. Turbines have an efficiency of 60% to 80%. The water does not work by weight, but by impact, pressure, reaction and suction.

The speed is much higher than in vertical wheels and hence is well adapted for circular saw mills.

A turbine, however, is badly affected by variations of water supply and suffers from debris and sand and ice. The effect of the water is greatest when the turbine is entirely under water, the flow of water filling the curved channel completely.

Turbines are:

- (a) Outward flow turbines, water fed from near the center.
 - (b) Downward flow turbines, water fed and pressing from above.
 - (c) Inward flow turbines, water fed from the perimeter.
 - (d) Reaction turbines, working after the principle of a lawn sprinkler.
 - (e) Impulse turbines, principle of flutter wheels.
- Modern turbines are worked both by impact and reaction and, if possible, by suction.

A 9-inch turbine, furnishing 14 horsepower, costs \$250, plus \$100 for setting it in masonry.

The advantages of water mills are: no fuel, no fireman, no engineer, no explosion, less insurance, possibility of using dust and slabs for stable bedding, laths etc.

Disadvantages are: usually small power, small speed and small capacity. Power less controllable, less reliable than steam power and not portable.

Small capacity does not justify a large outlay for good saw-mill machinery.

D. Steam mills.

For circular saws, the number of horsepower required is about $\frac{1}{3}$ the diameter of the saw. For example, a 48-inch circular saw requires 16 horsepower. Ten horsepower are said to manufacture 5,000 b. feet daily in circular saw-mills, and 30 horsepower will cut 30,000 b. feet daily. Every additional horsepower should increase the capacity by 1,000 b. feet.

In large mills each horsepower ought to manufacture 1,000 b. feet; in small mills only 500 b. feet.

FOREST UTILIZATION

Boilers in common use are designated as:

I. Internally fired boilers, when firebox and waterbox are comprised by one and the same steel shell; so all portable boilers and all locomotive boilers.

- (a) Cornish boiler: large flues below and return flue above water through entire length of boiler.
- (b) Lancashire boiler: divided flue below and divided flue above water through entire length of boiler, so as to even the draft when firing, and so as to strengthen the broad heating surface.
- (c) Galloway boiler: like Cornish but V-shaped tubes beset the boiler proper, thus increasing the heating surface and strengthening the flue.
- (d) Locomotive boiler: firebox surrounded by a waterleg on all sides, excepting at the grate below. A bank of small tubes carries gases to an "extension" or "smoke box" in front of smoke stack.

II. Externally fired boilers: masonry firebox underneath boiler which is traversed by a large number of tubes. Gases pass first to combustion chamber at rear end and then through tubes back to front.

To II belongs the water tube boiler, with inclined tubes, a horizontal top vessel and vertical tail tubes, creating a continuous circuit of water.

(a) Pointers about boilers.

- 1. Twelve square feet of heating surface of boiler furnish one horsepower.
- 2. Each nominal horsepower requires one cubic foot or $7\frac{1}{2}$ gallons of water per hour.
- 3. Mud drum at base of boiler to receive impurities deposited by water. Where no mud drum exists, boiler should be blown off weekly through a bottom valve (mud cock).
- 4. Steam and water capacity must be sufficient to prevent any fluctuation in pressure or water level.
- 5. A large water surface (horizontal versus upright boilers) prevents steam from bearing water particles along. Usefulness of dome is doubtful as a means to secure the return of watery particles to the boiler.
- 6. Water should occupy three-quarters of boiler space.

Water space should be divided into sections, an arrangement improving the circulation of water and reducing the severity of any explosion.

7. Modern boilers are tubular boilers, which have the largest heating surface. Diameter of tubes is measured outside, including metal.
8. Combustion chamber should allow of full combustion of fuel and gases. Draft area should be one-eighth of grate area. Return flues pass the gases to the entrance of the combustion chamber.

Heating surface should be as nearly as possible at right angles to the current of escaping gases.

9. Very best water gauges, safety valves, injectors and steam gauges are prerequisites. All boiler fixtures should be readily accessible.
 10. Safety valves must be tried once daily. The water level should be controlled by gauge cocks, glass gauges alone being unreliable.
 11. Cold water should not be fed directly into boiler and should never come in direct contact with the boiler metal. Steam injectors will not lift hot water as well as cold water.
 12. Steam pressure gauge must stand at zero when pressure is off.
 13. In case of low water and danger of explosion, cover fire with wet earth.
 14. If fire is fed from mill refuse, steady heat can be retained only with boilers of large water capacity. The larger the boiler the greater the fuel economy.
- (b) Pointers about engines.
1. Horsepower of engines is:
Sectional area of piston in square inches
times pressure times velocity in feet
over 550.
Deduct 10% to 20% for friction.
Pressure on the piston is not much
over one-half of pressure in the boiler
(60%).

2. Interdependence between size of cylinder and horsepower actually developed is approximately:

Diameter, inches	8	9	10	12	12	12	14	16
Length, inches	15	15	15	15	20	24	24	30
Horsepower	12	15	20	25	30	35	50	85

These figures hold good for single cylinder engines and are much lower than the usual catalogue figures. A new engine develops more power than an old one.

3. The flywheel should weigh 600 pounds for every inch of cylinder diameter.
4. Double cylinders are more effective than single cylinders, especially if not hitched tandem fashion, which arrangement, however, allows of using one piston rod.
5. Center crank engines are preferable for small portable saw-mills, since they allow of exchange of flywheel and main driving pulley.
6. Machines cannot get along any better, without care, than horses. Repair and watch the smallest defects. Have the firmest possible foundations. Saw-mill engines are put to the severest possible tests owing to frequent and rapid change of strain.

§ XIV. TRANSMISSION OF POWER.

A. Belts.

Belts in woodworking establishments are always dry and dusty and are kept at a high and often irregular rate of speed. Dust materially decreases the transmitting power of belts.

The heavier the belt the more powerful; use light belt on small pulleys, however, for high speeds.

I. Pointers about belts.

- (a) Belt tighteners are required where a belt itself is not heavy and not long enough to cause sufficient sag.
- (b) The sag should always be on top and not on the bottom.
- (c) The angle of belt against the horizon should not exceed 45°.
- (d) Placing one pulley above another requires tight belt, which causes heating in the bearings and destruction to the belt.

- (e) Belts should run off a shaft in opposite directions to relieve one sided friction of shaft in bearings.
- (f) The pulley must be wider than the belt.
- (g) The larger the pulley the greater the tractive power of the belt.
- (h) Be sure that the belt does not rub against any beam or other solid object.
- (i) Long belts have greater adhesion than short belts because they have more weight.
- (j) Belt dressing, to prevent slipping off of belt, is objectionable, because it gathers dust and dirt, except perhaps linseed oil used on rubber belts.
- (k) Belts will slip if:
 - 1. The pulleys do not run in one and the same plane.
 - 2. The shaftings are not parallel.
 - 3. The pulley is not as wide as the belt.
 - 4. The belt ends are improperly joined.
 - 5. The speed is too high for the weight of the belt.

II. Kinds of belts:

(a) Leather belts.

Leather belts are either single or double. They come in rolls of from 200 feet to 300 feet, are run with the grain side in and are preferably joined with studs—not by leather laces requiring holes; belt cement is now largely used, laps being joined to a fine edge.

Leather belts must be very well protected from moisture, grease, lubricating oil etc.

Transmitting power of a single belt is only 70% of that of a double belt.

The price of a 7-inch single belt per running foot is \$1. For double belt \$2.

(b) Rubber belts.

Rubber belts withstand moisture better than leather belts. They are cut from $\frac{1}{8}$ inch to $\frac{1}{4}$ inch shorter per foot than the circuit on which they run and are run with seam side out.

They are sold as 2, 4, 6 or 8 ply rubber belt, the 4 ply being equivalent to single leather belting and the 6-ply to double leather belting.

The price of 4-ply 7-inch rubber belting is 70c per running foot; of 6-ply, \$1.

The ends are joined either by belt cement or by lace leather. The laps are strengthened by a strip of leather on the outside.

Never use metal studs in rubber belts.

B. Pulleys.

Pulleys are made either of iron or of wood.

The adhesion of leather to wood is much greater than to iron, hence greater transmitting power of wooden pulleys.

Split wood pulleys are preferable. The best make is the Dodge split wood pulley, costing for 24-inch diameter and 10-inch face \$11.20.

The so called clutch pulleys consist of two wheels wedged one into the other, the inner one loose, the outer one fastened onto the shaft.

Iron pulleys must be absolutely symmetrical

Pulleys for stationary belts are slightly crowning, while those for shifting belts are straight faced.

Pulleys for heavy work should be placed close to bearings of shaft. The main driving pulley must stand between bearings not over four or five feet apart.

The ratio between the speed of driving and driven pulley is inverse to the ratio of the diameter.

Remarks relative to starting and stopping machinery:

I. Machinery is started by belt tighteners, the belt running over flanged pulleys, by clutch pulley, by tight and loose pulley with shifting belt, by eccentric boxes and by friction pulleys.

II. A rotation is reversed by crossed belts (belt turning 180°) or by paper friction pulleys or by forcing the belt against a driven pulley remaining outside the belt circuit.

III. A rotation is turned at right angles by giving the belt a quarter-twist (90°), or by gear and pinion or by beveled friction.

C. Shafting.

Cold rolled shafting is said to have a torsional strength 30 % greater than that of hot rolled shafting.

The usual diameters of shafting in saw mills are from $1\frac{1}{2}$ inch to $3\frac{1}{2}$ inch. The proper speed for shafting is 300 to 400 revolutions

and its transmitting power is given as $\frac{D^3 \times R}{80} = \text{horsepower.}$

Herein stands: D for diameter of shafting;

R for revolutions of shafting per minute;

80 for a constant factor.

Couplings by which the sections of shafting are joined should be close to a hanger or a support. They should be easily detachable without driving keys.

Shafting comes in sections usually 12, 14, 16 or 18 feet long.

The section closest to the main driven pulley is often stronger than the other sections.

The bearings should be long, say four times as long as the shafting is thick, and should have self-lubricating devices.

Hangers for 3-inch shafting and of 3-ft. drop cost about \$20.

Bearing-boxes are lined with an anti-friction alloy melting easily and offering little friction even under severe pressure. A space of $\frac{1}{8}$ inch to $\frac{1}{2}$ inch is left between the cast-iron box and the shafting (journal) to be supported. The box is held in a "bab-bitting jig" while the melted alloy is poured from a ladle. Bab-bitt metal (invented by Isaac Babbitt) consists of about 96 parts tin, 4 parts copper and 8 parts antimony.

Rules for shafting are:

- I. Be sure that line of shafting is parallel to axis of driver.
 - II. Place all heavy work on the main shaft and close to the main driver.
 - III. Oil freely and watch bearings constantly. Oil after stopping work, while bearings are still warm.
 - IV. Drive only minor machinery from gear wheels.
- Price of shafting is about 5c or 6c per lb.

§ XV. TECHNICAL USE MADE OF THE TREES, BY SPECIES.

A. Hardwoods.

Cucumber tree: Ox yokes; pump logs; water troughs; cabinet making; ceiling; flooring; invariably mixed with and substituted for yellow poplar.

Tulip tree or yellow poplar: Panels; flooring; molding; clapboarding; sheathing; shingles; siding on railroad cars; interior finish of Pullman cars; coffins; cheap furniture; bodies of carriages and sleighs; sides and bottoms of farm wagon beds; woodenware; bungs; slack barrels and tobacco hogsheads (staves and heading); backing for pianos and for veneers; boxes, especially biscuit boxes and cigar boxes; scroll saw work; wood carving; wood burning; matches; excelsior; paper pulp.

Linden or basswood: Mirror and picture backs; drawers and backs of furniture; molding; woodenware; panels and bodies of carriages; ceiling; wooden shoes abroad; inner soles of shoes; cooperage heading; slack barrel staves; butter churns; laths; boxes; grape baskets; excelsior; parts of pianos and organs; fine carving; papier mache; paper pulp. The flowers are used for tea; the inner bark for coarse cordage and matting.

Holly or ilex: Mallets; edging and engraving blocks; fine cabinet work; painting on wood; tool handles; mathematical instruments.

Buckeye: Artificial limbs; woodenware; paper pulp; wooden hats; fine wood carving.

Maple (western): Furniture; axe handles; frames of snowshoes.

Maple (eastern): Furniture (curly and birdseye); flooring; sugar barrels; mantels; runners of sleighs; peavy handles; ox yokes; axe handles; sides and bridges of violins; wooden-

- ware; wooden shovels; shoe pegs and lasts; gun stocks; saddle trees; teeth of wooden gear wheels; piano keys and hammers; wood split pulleys; framework of machinery; ship building; maple sugar; surveyor's implements; plane stocks; wooden types; faucets; clothespins; charcoal; acetate of lime; wood alcohol.
- Sumach: Tanning; dyeing and dressing skins; Japanese lacquer work.
- Black locust: Police clubs; fence posts; insulator pins; construction work (bridge); turnery; wheelwright work; tree nails (pins); ship building (ribs); hubs of wheels; house foundation.
- Mesquit: Fence posts and rails; used extensively for fuel (destructive to boilers).
- Black cherry: Fine furniture; cabinet work; interior finish; tool handles; surveyor's implements.
- Crabapple: Pipes, mallets; wooden measure rules; tool handles.
- Witch hazel: Pond's extract.
- Dogwood: Tool handles; spools; bobbins; shuttles; mauls; wheel hubs; machinery bearings; engraving blocks.
- Black gum: Heavy (wagon) hubs; rollers in glass factories; mangles; ox yokes; stock of sledge hammers in steam forges; veneers for berry baskets and butter dishes; slack barrels; in cheap furniture, for backing and drawers; barn flooring.
- Tupelo gum: Chemical paper fibre; slack barrel staves (rotary veneer cut); wooden shoes and woodenware; the corky root is used under the name of corkwood for bicycle handles and floaters of fishing nets.
- Sweet gum: Known in Europe as satin walnut and used for fine furniture and cabinet work, in America for cheap furniture; cheap building lumber; flooring; plug tobacco and cigar boxes; wagon beds; slack barrels; strawberry boxes; veneer cut dishes; coiled hoops; street paving.
- Sourwood: Tool handles; machinery bearings; sled runners.
- Rhododendron: Bruyere pipes; tool handles; turnery; toys; rustic furniture.
- Persimmon: Bobbins; spools; shuttles; tools; golf club heads; plane stocks; shoe lasts; wood engraving. The black heart is cut into veneers and used for ebony.
- White ash: Wagons and carriages (poles, shafts, frames); interior woodwork; inner parts of furniture; mantelpieces; sporting goods (bats etc.), oars and gymnastic bars; lances; agricultural implements; tennis racquets; snowshoes; skis; wooden pulleys; barrel hoops; pork barrel staves; baskets; dairy packings (firkins, tubs etc.); tool handles.
- Catalpa: Fence posts; railroad ties; telegraph poles.
- Sassafras: Light skiffs; fence posts; rails; cooperage; insect-proof boxes; ox yokes. Roots used to make sarsaparilla.

California laurel: Ship building; cabinet work and interior finish.

Elms: Wheel stock, especially hubs; fence posts; ribs of small boats; top spans in covered railroad cars; railroad ties; tongues for sleighs and sleigh runners; saddle trees; flooring; exported for inner lining of boats; butcher blocks and churns (butter); cheese boxes; imitation oak furniture; sugar and flour barrel staves; patent coiled hoops for slack cooperage; agricultural implements; bicycle rims; basket making; gun stocks; frame timber of piano cases; wheelbarrows; hockey sticks.

Hackberry: Fencing; occasionally for cheap furniture; hames.

Mulberry: Fencing; cooperage; in the South for boat building; axe handles.

Osage orange: Fencing; paving blocks; railroad ties; wheel stock; toothpicks; fine mallets.

Sycamore: Furniture; plug tobacco boxes; butchers' blocks; interior finish; beehives (hollow log sections); butter and lard trays; wooden bowls.

Walnuts: Interior finish; furniture; gun stocks; tool handles; cabinet work; boat building.

Hickories: Axe handles; wagon stock, especially whiffletrees; neck yokes; spokes; tongues; felloes; skeins; buckboards; rustic furniture; barrel hoops; screws; mallets; parts of textile machinery; farm implements; wooden rails (top); baskets; bows of ox yokes; boat building; hickory bark for flavoring sugar (to imitate maple syrup).

Oaks (white and burr): Furniture; wagon and carriage stock, especially spokes, felloes, hubs, tongues, hounds, bolsters, sandboards, reaches, brake bars, axletrees, whiffletrees; railroad ties; freight car building (framework); ship building; house building and interior finish; shingles; agricultural implements; bridge building; mining timber; wine, beer and whisky barrels; parquet flooring; staircases; split wood baskets; hogshead and barrel hoops.

Post oak: Fencing; railroad ties; construction; staves; carriage and wagon work; farm implements.

Basket oak: Baskets; cooperage; wheel stock; fencing; agricultural implements; construction.

Chestnut oak: Bark used for tanning; fencing; bridges; railroad ties; substitute for white oak, but objectionable in tight cooperage.

Live oak: Ship building; furniture.

Red oak: Shingles; furniture; interior finish; tight and slack cooperage.

Texas oak: Same as red oak. Said to check less than red oak.

Black oak: Plow beams; furniture; lumber; bark for tanning and quercitrin.

Tanbark oak: In California bark used for tanning.

Chestnut: Tannin extract; coffins; furniture; interior finish; shingles; fencing; railroad ties; sheathing; jacob staff for com-

passes; bridge building (trestles); telephone poles; backing of piano veneers; slack barrel hoops and sawn staves.

Beech: Wood alcohol; wood ashes; charcoal; shoe lasts; plane stocks; clothespins; handles; wooden bowls; horse collars (hames); parquet strips; flooring; street paving; railroad ties; sugar barrels. Beech furniture made out of veneers of three or four thicknesses, or bent after steaming.

Hop hornbeam: Posts; levers; tool handles; wagon brake; shoes; wedges.

Hornbeam: Used for same purposes as above, and teeth of gear wheels.

White birch: Toothpicks; shoe pegs and lasts; wood pulp; spools; clothespins; screws; flooring; veneers; furniture; bobbins and spindles; wooden skewers; hand-made barrel hoops.

Gray birch (yellow): Furniture (usually mahogany finish); match boxes; wheel hubs; tool handles; buttons; brush backs; shoe pegs; clothespins; sugar barrels; dry distillation for wood vinegar; wood alcohol; charcoal etc.

River birch: Furniture; woodenware; wooden shoes; ox yokes.

Cherry birch (sweet birch): Imitation cherry furniture; ship building; bark distilled for oil of wintergreen.

Oregon alder: Furniture; cigar boxes; mining props and water conduits; charcoal in gunpowder.

Black willows: Osier culture (imported species); pollarded for fascines; the Missouri species for fence posts after thorough seasoning; bats for baseball; a drug, salicylic acid, made from the bark; charcoal for smokeless powder.

Cottonwoods: Boxes; wood pulp and fibre; slack barrels; woodenware; flooring; excelsior; backing for veneers in organs and pianos; matches; cheap building lumber; cheap furniture; wagon beds; turnery; woodenware; fence boards.

B. Conifers.

Incense cedar: Water flumes; fencing; furniture; interior finish; laths and shingles.

White cedar (northern): Posts; fencing; telegraph poles; railroad ties; tanks and buckets; shingles; street paving; boat lining.

White cedar (Southern): Woodenware; tanks; buckets; barrels; telegraph poles and fence posts; shingles; railroad ties; boats; lampblack.

Red cedar (Pacific): Canoes of Indians; interior finish; fencing; shingles; cooperage; tanks; buckets.

Port Orford cedar (Lawson's cypress): Lumber; inside finishing; flooring; railroad ties; fence posts; matches; ship building. The rosin is a powerful insecticide.

Western juniper: Fences.

Red cedar (of the East): Tanks, posts, buckets; telephone poles; cigar boxes; chests; pencils; interior finish.

Bald cypress: Tanks; shingles; doors; house building; interior finish; sashes; blinds; molasses barrels; railroad ties; posts; car siding; flooring and covering; wharf piles.

Big tree: Lumber; fencing; shingles; construction; water conduits.

Redwood: House building and finishing; shingles; fencing; telegraph poles; vineyard stakes; railroad ties; car lining; tanks; coffins.

Yew. In Oregon for bows and fishing rods.

White pine: House building and finishing; boxes and crates; sash, doors and blinds; shingles; backing of fine veneers; excelsior; matches; laths; woodenware; slack barrels; framing of machinery; furniture; patterns for casting metals; ship masts; baled shavings for filtering gas, bedding for horses, packing for crockery.

Sugar pine: Same uses as white pine; cooperage; shakes (large board shingles).

Lodge-pole pine: Cheap lumber; mining timbers; railroad ties; used where other timber is not available.

Loblolly pine: Common lumber and cheap veneers, usually mixed with "echinata"; shingles; house building purposes altogether; mining timber; boxes; rice and potato barrels; laths.

Shortleaf pine (echinata): Same use as above; boxes for naval stores.

Table mountain pine: In Pennsylvania used for charcoal.

Longleaf and Cuban pine: House building; dimension stuff; shingles; tanks; flooring; interior finish; railroad ties; railroad bridges; car sills and framework of cars; furniture; sash, doors and blinds; framework of machinery; mining timber; ship building; masts; wagon tongues and beds; naval stores.

Scrub pine (Virginiana): In Kentucky, for lumber.

Jeffrey's pine: Coarse lumber; mining timber.

Bull pine (ponderosa): Lumber; railroad ties; mine props; shingles; boxes; slack barrels.

Jack pine (divaricata): Ties and piling; cheap lumber; boxes; laths.

Norway pine: Lumber generally; ship building; construction; flooring; masts; piles of wharves; covering; lining; siding; flooring and sills of railroad cars; railroad ties.

Eastern spruce: Chemical fibre and paper pulp (down to 5"-diameter); matches; excelsior; construction; posts; railroad ties; fresh-water ship building; clapboards; flooring; ceiling; stepladders; sounding boards (from butt logs); oars; spars; wharf piles; telegraph poles; toys; wood type; butter buckets; slack cooperage; wooden thread (for mattings); chewing gum; vanillin. In Europe spruce bark is used for tanning.

Engelmann's spruce: Used in Colorado for common lumber.

Tideland spruce: Lumber; construction; outer finish; woodenware; paper pulp.

Hemlock: Coarse rat-proof lumber; dimension stuff and construction; shingles; railroad ties; fencing; paper pulp; bark for tanning.

Douglas fir: All building lumber; construction; railroad ties; trestle bridges; piles; car sills; ship building; masts; mining timber; bark sometimes used for tanning.

Firs: Paper pulp. In the East for corduroying. In the West for local lumber; packing cases; cooperage; interior finish; mine props.

Tamarack (Eastern): Fence posts; telegraph poles; ship's knees; railroad ties.

Tamarack (Western): Posts; railroad ties; car construction; dimension stuff.

C. Tropical and subtropical timber.

Yucca: Paper pulp and fibre for ropes; pincushions.

Eucalyptus: Street paving; railroad ties; mine props; piles; ship building; wagon making; orchard paling.

Mangrove: Bark very rich in tannin.

Palmetto: Wharf piles; pincushions; brushes.

Lignumvitae: Bowling balls; blocks for pulleys; fine interior finish and furniture; railroad ties in Panama.

Teak: Ship building and flooring; railroad cars; street paving.

West India cedar: Racing boats; cigar boxes.

Olivewood: Turnery; inlaying; furniture; backs of hair brushes; wood carving. The fruit yields the best oil for table use.

Quebracho: Tanning; paving; railroad ties.

Lancewood: Fishing rods.

Mahogany: Furniture; ship building; pianos; fine interior finish.

§ XIV. TECHNICAL QUALITIES OF THE TREES.

A. Botanical structure of the trees.

I. Botanical structure of hardwoods.

The cells forming the woody tissue are:

- (a) Ducts (pores, vessels) formed by the resorption of the partition walls in a vertically running string of cells. Such ducts are characteristic of hardwoods.
- (b) Sclerenchyma, cells of heavy walls and small lumina, usually forming long fibres.
- (c) Parenchyma, cells of thin walls and large lumina, frequently containing grains of starch.

Medulla or pith is found in the central column, in the primary, secondary, tertiary rays and (rarely) in medullary spots (birch). The central pith is:

Heavy in ash, maple, elder, catalpa;

Triangular in birch, alder;

Quinquangular in hornbeam.

Broad leaved species are called "ring porous," if the spring wood of the annual ring contains strikingly

large pores, or else "diffuse porous," if the ducts are evenly distributed over the entire ring. Sapwood and heartwood are merely distinguished by a difference of color, caused by incrustations of pigments, lignin, tannin etc., in the walls of rings formed a number of years before. The number of years elapsing before incrustation takes place is small in catalpa, chestnut, locust; and larger in yellow poplar, white oak, walnut where it is about thirty or forty years old. Beech, maple, basswood etc. do not form any heartwood.

GENERIC STRUCTURE OF HARDWOODS.

Medullary Rays.	Ring-porous always with heart.	Inner pores more numerous, always with heart.	Diffuse porous.	
			Pores absolutely even With heart.	Without heart.
Scarcely visible.	{ Castanea Robinia Fraxinus Hicoria	{ Rhamnus Rhus Syringa	Juglans Pyrus malus Sorbus Salix Liriodendron	Alnus Pyrus communis Crataegus Betula Aesculus Populus
Visible.	{ Ulmus Morus Allanthus	Prunus		Tilia Acer Corylus Carpinus Ilex
Broad.	{ Quercus Vitis Rosa	Sambucus		Platanus Fagus

II. Botanical structure of softwoods.

- (a) The tissue of softwoods is more homogeneous than that of hardwoods. It is mainly formed by tracheae. The cell walls formed in early spring are thinner and the lumina formed in early spring are larger than those formed in summer.
 - (b) Parenchyma is found in the medullary rays and around the rosin ducts.
 - (c) Ducts of the form found in hardwoods exist only close to the central pith column.
 - (d) The medullary rays are very fine (microscopic), usually only one cell wide and about a dozen cells high. The lowest string of cells in the ray is usually formed by tracheae (exception—red cedar).
 - (e) Rosin ducts are not cells merely, but, unlike the ducts of hardwoods, hollow tubes, the walls of which are formed by parenchymatic cells. These ducts are running horizontally as well as vertically in picea, pinus, larix, pseudotsuga.
- The tissue of the genera abies, taxus, juniperus, thuja, tsuga, chamaecyparis etc. lacks the ducts.

- (f) Heartwood and sapwood of conifers are distinguished merely by a difference in color, due to incrustations of rosin in the inner heartwood rings. *Pinus echinata* has, usually, about thirty sapwood rings. Spruces, firs and hemlocks have no heartwood. Heartwood is conspicuous in the pines, red and white cedars, lawson cypress, yew, larches and douglas fir.

B. Chemical qualities of wood.

- I. The walls of the tissue are formed by cellulose ($C_{12}H_{22}O_{10}$) and by lignin ($C_6H_{12}O_5$).

Cellulose transforms, entirely or partially, in the very year in which the cell is built, by incrustation and reduction into lignin. If a branch or a seedling does not enjoy enough light during summer to allow of thorough lignification, then that branch or seedling is necessarily killed by the winter frost.

- II. Wood and bark contain on an average 45 % (weight) of water. Conifers contain less water than broad-leaved species. The percentage varies irregularly with the seasons and with the precipitations.

- III. Other substances found in the woody tissue are:

- (a) In the sap and medulla—albumen, starch, sugar, oils.
- (b) In the cell walls—tannin, rosin and pigments.

- IV. The specific gravity of pure wood fibre is 1.56.

C. Outer qualities, or qualities discernible by eye, touch or scent.

- I. Texture. The texture is fine or rough according to the ease with which parts composing the tissue can be distinguished.

The texture is:

- (a) Very fine—yew, box, holly, persimmon.
- (b) Fine—pear tree, hornbeam, black gum.
- (c) Pretty rough—spruce, fir, magnolia, cottonwoods.
- (d) Rough—cherry, sycamore, maple.
- (e) Very rough—oak, elm, locust, beech.

- II Color. Color is an advantage in the furniture trade and a disadvantage in the manufacture of paper. The heart of seasoned wood is always darker than the sapwood.

Tropical species are particularly rich in color.

Wood exposed to air changes its color more or less visibly.

The heart of yellow poplar changes to a dark brown. Alder changes from white to red. Ash from white to light violet. Mahogany from brown to black. Walnut similarly.

- III. Gloss. Gloss is due to evenness, number and size of medullary rays.

Shining species are maple, ash, elm, beech.

Medium shining are oak, alder, hornbeam.

Dull are peach, pear, conifers.

Quarter sawing increases the gloss.

- IV. Odor. Odor is important for the use of wood in the package industry. The strong odor of wood is usually lost in the course of seasoning. The following species retain, however, a characteristic odor: Cherry, birch, sassafras, red cedar.

D. Inner qualities, or qualities discernible by mechanical tests.

I. Specific gravity.

- (a) Pure wood fibre forms in fresh wood, with broad leafed species of temperate climates, about 35 % of the entire weight, while conifers show an average of about 25 %.
- (b) Air dried wood still retains from 10 % to 15 % of water. If the dry kiln reduces the percentage of water below that figure, the hygroscopicity of the wood will speedily cause it to return.
- (c) Factors influencing specific gravity of air-dried wood within the same species are:
 1. The width of the rings, in ring porous hardwoods and in conifers forming heartwood.
 2. The incrustations of rosin, tannin and pigments in the heart.
 3. The age of the tree.
 4. The decay of the fibre.
 5. The section of the tree, since roots are very light, butt logs heavy, bole fairly light and branches fairly heavy.

In the case of the diffuse porous hardwoods and of conifers destitute of heart, no rule can be given relative to specific gravity of inner and outer layers, of wide and narrow rings.

- (d) Air dried lumber has, on an average, the following weights:

Species—	Specific gravity.	Weight of 1,000 ft. b. m.
Turkey oak, hickory, service-bush.	over 0.75	over 4,000 lbs.
Ash, white and red oak, locust, beech, hornbeam, hard maple, pear tree	0.70-0.75	about 3,750 lbs.
Elm, soft maple, apple tree, sycamore, birch	0.60-0.70	about 3,400 lbs.
Horse chestnut, chestnut, tulip tree, alder, larch, longleaf pine	0.55-0.60	about 3,000 lbs.
Yellow pine, douglas fir, spruce, fir, willow, cottonwood.....	0.45-0.55	about 2,600 lbs.
White and sugar pine.....	under 0.45	about 2,200 lbs.

(e) Rules.

1. Specific gravity times 5,200 equals the weight of 1,000 feet b. m. of sawn lumber. Reason—1,000 superficial feet of water one inch deep weigh 5,200 lbs.

2. Specific gravity times 8,000 times cordwood reducing factor equals the weight of a cord of wood. Reason—128 cubic feet of water weigh 8,000 lbs.; a cord of wood contains from 20 % to 85 % of wood, the balance being air.
3. Specific gravity air dry times 5,200 times 23 equals the weight of 1,000 feet b. m. in the log. Reason—a green log has about 10 % bark, about 27 % of water, to be removed by drying, and loses 33 % for slabs and kerf in band sawing. Hence the weight in 1,000 feet b. m. air dried and band sawed lumber is only 0.9 times 0.73 times 0.67 of the weight of a log scaling 1,000 feet b. m. Doyle. The weight of a green log is 2.3 times the weight of air dried lumber obtainable from it by the band saw. For broad-leaved species and for circular saws the figure is higher than for conifers and band saws.

(f) Heavy planks do not dry as thoroughly as thin boards.

(g) Weight determines freight and customs charges. Also adaptability to packages, floatability in flumes and rafts and possibility of loose driving.

Lumber freight rates from Asheville, N. C., are:

29c per 100 lbs. to New York.

23½c per 100 lbs. to Philadelphia.

12½c per 100 lbs. to Atlanta.

18c per 100 lbs. to Washington.

14c per 100 lbs. to Norfolk.

Lumber freight rate from Portland, Ore., to Chicago is about 50c per 100 lbs.

Steamer rate to Europe from Norfolk is 14c per 100 lbs. of lumber.

The freight rate on logs for 50 miles is at least \$5 per carload; for 100 miles at least \$6.

II. Hardness.

By hardness is understood the resistance of the fibre to axe and saw worked vertically to the fibre.

Factors of hardness are:

- (a) Density; wide rings in oak and narrow rings in pine increase the hardness.
- (b) Incrustation; heartwood is harder than sapwood.
- (c) Moisture contents; dry wood is, on the whole, harder than green wood. With some broad-leaved species of loose tissue (willows and cot-

tonwoods), however, moist wood is tougher and therefore harder as well.

(d) Frost increases the hardness.

SCHEDULE OF HARDNESS.

Hard.	Medlum.	Soft.	Very soft.
Hickory	Ash	Chestnut	White pine
Dogwood	Oak	Tulip tree	Sugar pine
Sugar maple	Elm	Sweet gum	Sequoia
Sycamore	Beech	Douglas fir	Paulownia
Locust	Cherry	Fir	Willow
Hornbeam	Mulberry	Yellow pine	
Persimmon	Birch	Larch	
	Sour gum	Linden	
	Longleaf pine	Horse chestnut	
		Hemlock	
		Cottonwoods	
		Spruce	

III. Cleavability or fissibility.

Cleavability is the resistance of fibre to axe, saw and wedge, worked lengthwise in the direction of the fibre. Radial cleavage is usually by 50 % to 100 % easier than tangential cleavage (except in black gum).

Factors of cleavability are:

- (a) A straight, long, elastic fibre.
- (b) Heavy and high medullary rays.
- (c) Straightness of growth.
- (d) Branchiness.
- (e) Moisture (very green and very dry wood splits best).
- (f) Frost (reduces the cleavability).
- (g) Hardness and softness (extremely hard and extremely soft wood splits badly. This rule holds good only in hardwoods).

SCHEDULE OF CLEAVABILITY.

Hard to split.	Medlum to split.	Easy to split.
Black gum	Oak	Chestnut
Elm	Ash	Pines
Sycamore	Larch	Spruce
Dogwood	Cottonwood	Fir
Beech	Linden	Cedar
Holly	Yellow poplar	
Maple	Hickory	
Birch		
Hornbeam		

IV. Pliability.

Under pliability we combine flexibility and elasticity.

- (a) Flexibility: wood which is easily bent without breaking is flexible (flexible). Softwoods are naturally less flexible than hardwoods.

Flexibility depends on:

1. Toughness and cohesive force of fibre.
2. Moisture, which increases it very much.
3. Heat, which increases it.
4. Age of tree, inasmuch as young shoots are tougher than old wood.
5. Impregnation, natural as well as artificial,

FOREST UTILIZATION

checks flexibility. (Heartwood less flexible than sapwood.)

6. Root wood more flexible than stem wood.

Remarks: Heat and moisture as a means to increase flexibility are applied in these industries:

Cooperage; for bending staves and hoop poles.

Carriage works; for bending poles, shafts, felloes, top frames, seats etc.

Furniture; bent wood furniture.

Ship building.

Veneer peeling.

Basket work.

Manufacture of musical instruments.

- (b) Elasticity and flexibility are not always found in the same piece of wood. On the contrary, qualities which increase flexibility frequently reduce elasticity, and vice versa. Elasticity is the force with which an object resumes its old shape when pressed out of shape and released.

The factors of elasticity are:

1. Long and straight fibre.
2. Narrow rings in conifers.
3. Dryness (moisture reduces elasticity).
4. Frost (which destroys elasticity).
5. Excessive contents of rosin (which increases the elasticity).

SCHEDULE OF ELASTICITY.

Very elastic are:

Yew
Larch
Fir
Locust
Chestnut
Hickory
Osage orange
Red cedar
Lancewood
Spruce
White pine
Ash
Oak

Less elastic are:

Cottonwood
Birch
Maple
Elm
Alder
Walnut
Yellow pine
Yellow poplar
Beech

V. Strength.

Strength is resistance to:

- (a) Tension; to which timber is usually not exposed.
(Yoke of oxen pulling the cart by the pole.)
- (b) Compression (arches, pillars, scantling).
- (c) Torsion (shafts, screws, axles).
- (d) Shearing.
- (e) Transverse straining (beams, girders, joists).

Factors of strength are:

1. Specific gravity.
2. Soundness of tissue.
3. Freedom from branches.

Timber, like any other material, should never be

loaded to over one-fourth of its indicated strength.

Transverse strength is always proportioned to length of girder; to width of girder; and to the square of the depth of girder. It is *the* quality of timber which is most required in timber used for building purposes.

VI. Hygroscopical qualities.

- (a) Timber changes form, coherence and volume with greater or lesser ease under the influence of moisture, applied in gaseous or liquid form. Hence shrinking, swelling, warping, checking, cracking, casehardening and working.
- (b) Water invariably saturates the cell walls; in addition, it may or may only partially fill the lumina.
- (c) Sapwood invariably contains more water than heartwood.
- (d) Rate of dryness depends on the species, looseness of tissue, dimensions of object to be dried, presence or absence of bark cover in logs, preceding treatment by floating, deadening, steaming, prevalence of sapwood or heartwood, season of year, exposure to wind, climate etc.
- (e) Boiling and steaming reduce the hygroscopicity and produce, consequently, a more even shrinkage.
- (f) The evaporation from the cross section bears to that of the tangential and to that of the radial section the ratio of 8 to 1 to 2.
- (g) In the dry kiln, temperatures of 160 degrees to 180 degrees Fahrenheit are gradually produced. Drying is accomplished by hot air, steam and moving air.

Conifers stand the dry kiln process much better than hardwoods. The better qualities of hardwoods undergo air drying before being kiln dried, especially so in wagon, furniture and barrel factories.

The dry kiln saves insurance and interest on large stocks of lumber and allows the lumberman to rapidly fill pressing orders for lumber.

- (h) Wood is least permeable for water in the direction of the tangent or vertically to the medullary rays—a fact important for tight cooperage.

i. Shrinkage.

It is least along the fibre; it is up to 5 % along the radius and is up to 10 % along the tangent.

Shrinkage of over 5 % of green volume

occurs in wainut, linden, beech, elm, chestnut, birch.

Shrinkage of 3 % to 5 % occurs in oak, maple, sycamore, ash, cottonwood, yellow pine.

Shrinkage of 2 % to 3 % occurs in spruce, larch, fir and white pine.

A large percentage of rosin, narrow annual rings and light specific gravity reduce shrinkage within the same species.

2. Checking.

It depends on the rapidity of the drying process; on size and dimension of object; on peeling of logs; on homogeneity of tissue.

Checks are often of a temporary nature, disappearing when the inner layers are as dry as the outer layers.

Hardwoods check much worse than softwoods; and rift sawed or quarter sawed lumber checks less than bastard sawed lumber.

Remedies against checking of logs are: Winter cutting; strips of bark left near the end of peeled logs; felling with the roots and leaving the crown on the undissected bole; deadening; "S" shaped iron clamps driven into logs; boards nailed onto the ends of the logs; earth cover at the ends of the logs; red lead painting for export logs.

Remedies against checking of lumber are: Quarter sawing; slow air drying under sheds; veneer sawing; steaming or boiling; sticks placed close to the ends of tiers in lumber piles.

Checks are radial since the tangential shrinkage is greatest. The so-called wind (or ring) shakes are not caused by the hygroscopicity of the timber; they are merely a form of disease of timber, due to frost, heat, fire or insect plagues interfering with the radial cohesion of adjoining rings.

3. Swelling, warping and working.

These phenomena are due to reabsorption of water after drying. The swelling is greatest tangentially. Heartwood warps

less than sapwood, and conifers warp less than hardwoods. Boards obtained from close to the slab warp worst of all. Remedies against working are steaming; varnishing; forming boards by gluing fine veneers one upon another; allowing framework of doors to be sufficiently grooved for receiving the panels.

VII. Duration of wood.

(a) Duration of wood depends on:

1. The surrounding conditions; i. e., tropics or arid deserts; presence of insects (ants and fungi); contact with clay, limestone or sandy soil; immersion in water (toredo); exposure to atmosphere; moisture conditions; presence of preserving matter (salt water, copper mine water).
2. The natural qualities of wood, especially the presence or absence of rosin, tannin and other preservatives; the specific gravity; the percentage of sapwood; the susceptibility to fungus and insect diseases. Locust, red cedar, sequoia, bald cypress, are less subject to such diseases when dead than when alive.

(b) Remedies against destruction are: Impregnation or painting; charring the part imbedded in the soil; winter cutting; change of species when replacing ties; kiln drying and steaming and smoking; raising buildings high above ground.

(c) Bulletin No. 10 gives the following data for the average "life" of ties:

White and chestnut oak,	8 years
Chestnut,	8 "
Tamarack,	7-8 "
Cherry and walnut,	7 "
Elm,	6-7 "
Longleaf pine,	6 "
Hemlock,	4-6 "
Spruce,	5 "
Red and black oaks,	4-5 "
Ash, beech, maple,	4 "
Locust, cypress,	10 "
Red cedar,	10 "
Redwood,	12 "

FOREST UTILIZATION

(d) Schedule for lumber:

<i>Very durable.</i>	<i>Durable.</i>	<i>Short lived.</i>
Walnut	Ash	Beech
Locust	Larch	Sycamore
Sequoia	Yellow pine	Birch
Cedar	Spruce	Linden
White oak	Fir	Cottonwood
Catalpa	Yellow poplar	White pine
Sassafras	Douglas fir	
Chestnut		
Longleaf pine		

VII. Heating power.

Heating power or fuel value bears a direct ratio to specific gravity air dry. All wood fibre having the specific gravity 1.56, equal air dry weights of our common species furnish equal heat. On the other hand, light weight means greater inflammability and a quicker heat, which naturally lasts for a short time only. The heating power of hard coal is to that of lignite and to that of wood as 5.2 : 4.3 : 1. In other words, 5.2 lbs. of dry wood yield as much heat as 4.3 lbs. of lignite or as 1 lb. of coal.

Influencing factors are found in the following moments:

- (a) Presence of rosin increases the heating power by about 12 %.
- (b) A cord of wood containing 45 % moisture has, after German experiments, the heating power of half a cord of air dried wood. After Sargent, the discrepancy is not as great. One cord of green wood contains 250 gallons of water, and the calories of heat required to convert this large amount of water into steam are lost for heating purposes.
- (c) Unsound wood has a reduced heating power, the cell walls being decayed.
- (d) Chestnut, and to a certain extent larch and spruce, are despised in open fires owing to crackling and emission of sparks. Black gum is despised because it is difficult to split and therefore difficult to season. Hornbeam, birch and alder are said to furnish a particularly quiet flame.

(e) Schedule of the heating power of wood per cord:

<i>Best.</i>	<i>Good.</i>	<i>Moderate.</i>	<i>Bad.</i>
Hickory	Oak	Spruce	White pine
Beech	Ash	Fir	Alder
Hornbeam	Birch	Chestnut	Linden
Locust	Maple	Hemlock	Cottonwood
Heart pine		Sap pine	

IX. Miscellaneous technical qualities of wood.

- (a) Adaptability to planing and molding; varnishing and polishing; painting and gluing.

- (b) Nail holding power, which is said to be excellent in chestnut, white pine and hemlock.
- (c) Twisted growth, which is frequent in chestnut, Italian poplar and horse chestnut. Certain twists are due to a hypertrophical growth of the tissue and are highly prized by the trade under the names of birdseye maple, curly poplar, curly walnut, curly cherry and curly ash etc. It is impossible to say whether a standing tree is "curly" or not. Sap-sucking woodpeckers may start the "freak."
- (d) Knots check the value of lumber. A standard knot is a sound knot, the diameter of which varies according to local inspection from $1\frac{1}{4}$ " to $1\frac{3}{4}$ ". Dry, dead and unsound knots throw a board into the mill cull pile. Usually, the knotty part of a log is sawn into dimension stuff. The core of a log, even in yellow poplar, necessarily shows knots, since there is no height growth without simultaneous formation of side branches.
- (e) The discoloration of the inner layers of certain species which are not classed as heartwoods (beech and maple) is a disease often found in old trees and causes rejection for certain applications in the trades (impregnation).

CHAPTER V. MANUFACTURING INDUSTRIES.

§ XVII. THE SAW MILL.

A. The saw.

Three kinds of log saws are used:

I. Straight saws, viz:

- Vertical straight saw;
- Gang saws;
- Horizontal frame saw.

II. Circular saws, viz.:

- Solid tooth single saw;
- Solid tooth double saw;
- Inserted tooth saw.

III. Band saws, viz.:

- Single cutting band saw;
- Double cutting band saw.

I. Straight saws.

- (a) Single vertical straight saw. At the toothed edge this saw has a thickness of from 5 to 10 gauges. Its blade is 8 inches wide and at least twice as long as the log diameter.

A short blade yields the finest work, since it can be spanned more tightly.

The gauge along the back should be finer than the gauge along the cutting line.

The saw can cut any thickness of trees.

The saw cuts only by the down stroke while the log is moved against the saw during the up stroke.

The saw is spanned in a guide frame and is given as many inches inclination toward the log as the feed of the carriage per stroke amounts to. If the saw were not inclined all the work would be done by the lowest teeth.

The usual set is still the spring set and not the swage set, although the latter is sure to be superior.

Usually the ends of the boards are not sawn through but are held together by the "comb," which is finally split with the axe.

In filing mill saws, obtain sufficient pitch of teeth to prevent saw from kicking out of the cut. Too much pitch, however, causes chattering.

Gullets must be kept carefully rounded.

- (b) Gang saws. They are used in large mills for inferior logs.

The best make is Wickes Bros., Saginaw, Mich. Enormous stone foundations are required.

The saw frame has an oscillating motion which presents the saw to the cut in an easy raking sweep, forcing each tooth to do its full share of the work.

Gang saws are not fed from a carriage. The logs are run through feed rolls, feeding the logs into the saws.

Blades are 6 to 10 inches wide and of 8 to 16 gauge.

Horsepower required is said to be for friction, 3 horsepower; for first blade 4 horsepower, and for every additional blade $\frac{1}{2}$ horsepower more.

Where log heaps (up to 12 logs) are run through the gang saw, the logs are slabbed by a "rosser" or "log siding machine," so that the logs can be placed one upon another.

- (c) Horizontal frame saw. It is used to cut fine veneers and valuable timber. Its advantage lies in the fact that very little weight rests on the saw, that the saw can cut on both trips (to and

fro), that high speed may be applied and that a thin gauge can be used.

The best make is Kirschner's, Leipzig, Germany.

II. Circular saws.

(a) Power.

Ten horsepower should manufacture 5,000 b. feet per day; 20 horsepower should manufacture 10,000 b. feet per day; 30 horsepower should manufacture 30,000 b. feet per day, and each additional horsepower should add 1,000 b. feet to amount cut. This amount depends on size of logs.

Five horsepower is required for a 20-inch to 30-inch saw; 12 horsepower for a 30-inch to 40-inch saw; 15 horsepower for a 48-inch to 50-inch saw; 25 horsepower for a 50-inch to 62-inch saw.

(b) Right hand and left hand mills.

If the carriage is to the left of the observer while the saw runs towards him, the mill is a left hand mill, and vice versa. A right hand saw is screwed to the arbor by a left hand nut and is usually driven by a left hand steam engine.

Center crank engines can be used for either right or left hand mills.

(c) Speed.

The proper speed at the rim of any circular saw is 9,000 feet per minute.

There should be a speed indicator to control the saw's speed. It costs 75c.

If the power is too light to run the mill at standard speed, portable mill men usually increase the speed of the engine, putting a larger receiving pulley on the saw mandrel.

(d) Proper qualities of a saw.

1. The usual thickness is 7, 8 or 9 gauge. Frequently the center is one gauge heavier than the rim.

2. There should be a sufficient number of teeth for the amount of feed.

Each tooth should cut as much as is offered to it at a revolution.

To cut one inch of lumber one may use either:

Eight teeth, cutting $\frac{1}{8}$ inch each at a revolution, or

Sixteen teeth, cutting $\frac{1}{16}$ inch each at a revolution, or

Thirty-two teeth, cutting 1-32 inch each at a revolution.

The number of teeth for one inch of feed should be, in hard timber, 16 teeth; in medium timber, 12 teeth, and in soft timber, 8 teeth.

The usual feed is from 1 to 6 inches per revolution. The quicker the feed the more teeth are required to do the work.

3. The saw must be perpendicularly hung; must slip on the mandrel against the fast collar easily, so as not to twist the saw out of true, thus causing it to buckle when the loose collar is tightened up.

The loose collar is hollow at the center (small saws excepted) and has about 6 inches diameter and $\frac{3}{4}$ inch rim.

By pressing a layer of writing paper between the collar and the saw the saw may be slightly bent toward or away from the carriage.

4. The saw must be evenly set (either spring or swage set). The teeth, filed square (not to a point but to a cutting edge), must form an exact circle and must retain that form in the course of operation.

5. The teeth must have the proper pitch. A shallow tooth cuts the smoothest lumber, but forbids of rapid feeding.

The modern shape of teeth is such as will facilitate filing and as will preserve the original pitch.

A tooth gets dull over as much of an inch as it cuts.

The gullet of the tooth must be larger for soft wood than for hard wood. Large gullets weaken the saw, small ones increase the friction very badly.

A tooth should be filed two to four times a day. The backs of the teeth must never protrude beyond the point.

Gullets must be kept circular carefully. Any sharp edge in a gullet is sure to cause a crack.

6. The mandrel must not heat in the journals. The boxes require frequent reabbutting. The stem of the mandrel must be exactly level and perfectly straight.

Mandrels run hot owing to excessive friction in bearings, to excessive tightness of belts, insufficient lubrication or heating of the saw in the center.

A hot mandrel expands the saw in the center, causing crooked sawing.

- (e) Lining of the saw with the carriage into the log.

The saw must "lead into the cut" just sufficiently to keep the saw in the cut. The proper lead is $\frac{1}{8}$ inch in 20 feet. Too much lead into the cut causes the saw to heat at the rim. A lead out of the cut causes the saw to heat at the center.

The $\frac{1}{8}$ inch lead in 20 feet is obtained by sighting over the saw and fixing the saw plane for a radius of 10 feet. This may be done by putting two staffs vertically into the ground 10 feet from the saw center behind and in front of the saw; that done, a horizontal stick is fastened to a head block so as to just touch the forward staff. Then the carriage is gigged backward to the other vertical staff where the horizontal stick must lack exactly $\frac{1}{8}$ inch from touching.

- (f) Filing room.

Automatic sharpeners and gummers are required for mills having over 15,000 feet daily capacity. Setting instruments for spring set are similar to those used with cross cut saws, constructed either after the wrench principle or after the block and hammer principle.

The spring set is gradually discarded for the swage set.

In swaging use oil on the point of the tooth, after filing to a sharp point. Swaging should draw the tooth out and should not shove it back.

The set or swage of teeth should increase the gauge at the rim by at least $\frac{3}{32}$ of an inch.

The pitch of the tooth might be controlled by a so-called trammel.

Gumming is required to preserve the original hook or rake of the tooth as well as the original roundness of the gullet.

Gumming as well as sharpening are usually done with emery wheels.

Emery wheel rules are as follows:

1. Do not put too much pressure on emery wheel so as not to change the temper of the tooth (bluing and casehardening and consequently crumbling of the tooth).

2. Do not try to fix a tooth fully at one time. Treat it gradually at five or six revolutions of the saw.
3. Proper speed for emery wheels at the rim is 4,500 feet per minute.
4. After gumming remove the irregularities at the edges with a side file, since cracks in saw are apt to start from them.
5. Hammering becomes necessary when the use of emery wheels has caused the saw to expand ("let down") at the rim.

For small mills gumming with a file or a butt gummer is preferable to the use of emery wheel.

Soft wood requires more set or spread and less pitch than hard wood.

Swaging is also called upsetting or spread setting.

(g) Inserted tooth circular saws.

1. The insertion into each socket of the rim consists of a holder and of a chisel point. These points are extremely hard; still they can be filed and swaged with the help of specially constructed files. It does not pay, however, to spend much time in filing since new points are cheap, and since they are readily inserted with the help of a special wrench.

Points are oiled before being inserted.

When renewing one individual point be sure to have it dressed down to correspond to the line of old points.

If the saw guide is not properly adjusted it may touch the holder and smash the saw.

2. Advantages of inserted tooth saw are:
Less experience is required for dressing a saw.

Less filing and gumming.

Less saw repairs in backwoods.

Diameter of saw remains unchanged during its use.

3. Disadvantages of inserted tooth saw are:
The saw kerf is very heavy.
The teeth are large and hence few, so that feed must be comparatively slow.
The price of the inserted tooth saw is higher than that of the solid tooth saw.

The best makes are the Atkins and Disston saws.

(h) The double circular saw.

For big logs and high speed a double circular saw must be used.

The width of the widest board which a single circular saw may cut equals radius minus three inches. Hence much valuable material is wasted in the common circular saw mill sawing heavy logs.

The double circular saw shows an under or lower saw of 56 inches or 60 inches and an upper saw of 30 inches or 36 inches diameter. The top saw should have a reversed motion (so as not to throw sawdust into the lower saw), an arrangement which it is difficult to secure.

A hanger top saw can be added readily to any single saw. Both saws should have the same speed at rim.

The top saw should remain inactive so as not to use up power when small logs are sawn.

Inserted teeth are not used at the double mills.

The advantages of the double saw mill are:

1. Less chattering and truer cut than would be possible for one big saw.
2. Thinner kerf.
3. Faster feed.
4. Less expense for saws.
5. Less repairs.

(i) Remarks relative to "putting up" portable circular saw mills:

The minimum yard required is 50,000 board feet.

The expense of tearing down and putting up again is about \$50.

For foundation timbers, place two pieces 8 x 10 inches x 11 feet long on either side of the saw pit (3 feet deep) and underneath the "husk." One piece 4 x 6 inches x 7½ feet long is saddled into the two big pieces, spanning the saw pit underneath the far rail of the track.

Construct the carriage track absolutely straight and level on the track ties (16 to 25 in number) and on the saw pit span.

Place carriage with rack shaft, feed and gig works in place and fasten the track by cleats and nails solidly to the foundation timbers. Then place the husk on them at a distance of about 6 inches from the track, putting wedge blocks between the

husk and track. Then spike the husk to its foundation—to begin with in two places only, viz.: at the sawyer's corner and at the middle of the opposite side, so as to enable the sawyer to change the lead by wedging the blocks. Then fix or hang the saw, set the saw guide and fire away.

III. Band saws.

(a) The blade.

The blade material is steel. The width of the blade for log band saws is from 10 inches to 16 inches—14 inches being usual.

Gauge of blade is from 19 gauge to 13 gauge.

Under tension of blade is understood the curvature across the width, which is increased or decreased by hammering at center or at edge. The tension gauge with curved edge guides the filer.

(b) The tooth.

Its width is from $1\frac{1}{4}$ inch to $2\frac{1}{4}$ inch.

The hook or pitch is from 40° to 65° .

The depth should be as shallow as possible, with gullets kept round, since cracks usually start from a corner in the gullet.

For sharpening the tooth, a medium soft emery wheel should be used and should not be crowded too hard against the saw, so as to prevent case-hardening.

The teeth are swaged—never spring set—like gang saws. The full amount of set should not exceed 9 gauge in a 14 inch saw.

Side filing or side dressing, after swaging, is usually practiced, although objected to by the saw makers.

For gumming, either a gumming press or the emery wheel is used.

(c) The filing room.

Every band saw mill has a separate filing room equipped with automatic dressing machines, i. e., automatic sharpener, automatic swage, automatic swage shaper, saw stretcher etc.

In the band saw mill, the filer is considered more important than the sawyer for the success of the mill.

Saws are changed three or four times a day.

"Brazing" of a band saw means joining the loose ends, uniformly beveled or ground to a feather edge $\frac{3}{4}$ inch long. A strip of silver solder is placed between the cleaned laps, which are then taken between the cheeks of the brazing clamps heated to a bright red heat. After pressing the

clamps together for several minutes and allowing them to cool, the braze is dressed down with a file to the proper thickness.

The filer arrests cracks by punching a small pin hole or dot at extremity of crack.

(d) The wheels.

The band saw runs, belt like, over two wheels weighing from 1,500 to 3,000 pounds (the lower heavier than the upper); the lower wheel driving the upper by the band saw.

The strain on the saw, which should not exceed 5,000 pounds and by which slipping off is prevented, is obtained by raising the upper wheel. The diameters of the wheels are 8 to 10 feet, the face about 11 inches, the teeth overlapping the wheel.

The crown of the tire is up to 1-64 inch.

The entire length of the log band saw varies from 30 feet to 70 feet.

The saw guides, lined with wood or babbit metal, prevent the cutting part of the blade from bending toward the carriage or toward the wheels, while the guard rolls, standing about 2 inches back of the saw, prevent it from slipping backward at the approach of the log.

The maximum diameter of logs that can be handled by band saws is about 90 inches.

The weight of a band saw mill complete is 20,000 to 40,000 pounds.

(e) The "Allis" double cutting telescopic band saw.

The saw blade has teeth on both edges, so that a board is obtained at each trip of the carriage.

The entire mill is raised or lowered by hydraulic pressure with a view to bringing the top of the logs immediately underneath the upper wheel.

IV. Conclusions.

- (a) The superiority of the band over the circular saw lies in a saving of 1,000 board feet in every 16,000 feet of $4/4$ inch boards obtained. In heavier planks the saving is less, in lighter boards more. The boards obtained have a better width. Logs over four feet through cannot be handled by circular saws. Further, the band saw allows of a more rapid feed. Hence it is used preëminently for valuable logs, for big logs and for high output.

Frequently mills of large output employ simultaneously band, circular and gang saws, allotting the logs according to their quality, the best to

the band saw and the poorest to the gang saw.

Two edgers and one trimmer can take care of such a combined output.

- (b) Mammoth mills are now considered uneconomical, since it is difficult to take care of the output of boards at the outlet from the mill floor.

The output per mill hand in big concerns is up to 7,500 board feet daily.

Four acres of mill pond hold up to 1,000,000 board feet.

Two standard gauge trains supply an output of 100,000 board feet from an average distance of 10 miles, daily.

B. The carriage.

I. The composing parts are:

The truck with head blocks, knees, dogs, set works, and the driving machinery.

The carriage is subject to the roughest treatment. Still, its proper alignment is as essential as that of the saw.

- (a) The truck is made of timber at least 6 inches square, thoroughly seasoned and strongly braced and bolted.

Construction material is:

Up North—Norway pine, birch and maple.

Down South—Yellow pine and white oak.

The length should correspond with the maximum size of logs.

So called screw block trailers may be added, increasing the length (in longleaf pine mills) up to 72 feet.

- (b) The head blocks, iron with steel face, are let into the timbers of the truck and form a groove for the tongue of the knee, which slides on the head blocks, being moved forward and backward by the set works.

The head block and knee form a right angle into which the log is firmly pressed.

- (c) The knee is either solid or hollow and carries the dogs.

The dogs are hooks or clamps or teeth, meant to grasp the log. They are fastened either inside or outside of the knee.

Two tooth bars, playing inside the hollow knee and pressed by a powerful lever, replace the original dogs in modern mills.

"Underdogs" are used in quarter sawing.

The number of head blocks, knees and dogs is variable. The minimum is two of each.

(d) The set works consist of:

The set beam, a shaft running underneath the carriage from head block to head block, with a pinion at each head block. This pinion corresponds with a rack forming the tongue or basis of each knee.

The index disc and ratchet.

The set lever, handled either by the sawyer, in small saw mills, or by the setter, in larger mills. The set works are usually double acting, so that the knees advance with the to and fro motion of the set lever.

In addition, each knee can be moved individually on its rack by the so-called taper movement.

The knees, before a new log is loaded, are receded either by a spring device or, on the gig motion of the carriage, by a friction device.

The brake wheel on the setshaft acts as a buffer when logs are loaded on the car.

(e) The wheels.

The wheels are attached either to the carriage or to the floor. The near wheels are flat on the tire and the far wheels, called guide wheels, are grooved on the tire.

In band saws, an automatic off-set is required to prevent the face of the log from striking the saw on the gig motion.

The steel rails are invariably placed on stringers.

II. Driving machinery.

The to and fro trips of the carriage are known as feeding and gidding.

In small mills the motive power is derived from the saw arbor by:

(a) Rack and pinion device.

(b) Chain, rope or cable running over one or several sheave drums.

The speed is regulated either by so-called cone pulleys (two, three or four on the same shaft) or by a paper friction device.

The so-called Reamy Disc Friction allows of freely varying the speed.

The usual feed, with the cone pulley, is from $\frac{3}{4}$ inch to 3 inches per revolution of saw.

In large saw mills the piston of a steam cylinder pushes the carriage to and fro (so-called shot-gun feed). In that case the carriage usually runs on three rails (center guide rail).

C. Additional parts of high grade saw mills:

- I. "The log haul up" (elevator) consists of a flanged foot wheel and an inclined trough, on the bottom of which runs a strong endless chain driven by sprocket wheels. The chain has steps (called welds) at intervals of about 6 feet.

The haul up is driven by a separate engine or from the main shaft by double gear wheels. It consumes a great deal of power.

At the upper end of the haul up, a log flipper "boxes" the logs out of the trough onto the log deck, which is usually inclined toward the carriage.

On the log deck, the logs are freed from dirt and bark by hand.

- II. "The nigger," handled by the sawyer, throws the logs on the carriage and turns them by a boxing movement.

- III. "The hog" is a steel box within which the edgings and trimmings are cut into small slices by very strong knives rapidly rotating.

- IV. "Dust conveyors" convey the output of the hog and the sawdust automatically to the boilers.

D. The edger.

The boards, falling from the log, are conveyed automatically or by hand to the edger.

- I. Parts of the edger are:

(a) One or several circular saws of 12 inches to 28 inches diameter.

(b) Feed works, either power or hand driven, consisting either of a carriage or of feed rolls or of barbed chains by which the boards are fed into the saws.

(c) Edger table.

- II. Task of the edger is:

(a) Removal of defects, knots, bark edge at the side of a board.

(b) Splitting boards into pieces of different quality.

(c) Rapid sawing to proper width required for special purposes.

- III. Kinds of edgers.

(a) Hand feed edger, with one or two saws.

(b) Power feed edger, usually with a single saw.

(c) Gang edger.

- IV. Pointers.

(a) The distance between the various saws in gang edgers is regulated by overhead levers or by hand wheels.

(b) Several boards can be fed at one time.

(c) The attendant of the edger must be a lumber in-

spector at the same time, so as to turn out the maximum value of edged product.

- (d) The boards are taken to the edger from the live rolls onto which the board drops from the log, either by hand or automatically, by chain conveyors.
- (e) The boards are conveyed from the edger to the trimmer by hand.

E. The trimmer.

In large mills, trimming follows edging. In small mills, edging follows trimming.

I. Parts of the trimmer are:

- (a) One or several circular saws about 18 inches in diameter. A one saw trimmer is called a "cut-off."
- (b) Feed works, viz.: live rolls or carriage or barbed chains running over sprocket wheels.
- (c) Table.

II. Task of the trimmer is:

- (a) The shortening of boards to standard lengths of 6, 8, 10, 12 and up to 20 feet, allowing 2 inches extra for shrinkage.
- (b) The removal of defects at either end, so as to raise a board into a higher grade.
- (c) The cutting of straight ends.

III. Pointers.

- (a) Where two saws are used, the distance between them is changed by a lever or by a screw wheel, shifting one of the saws, while it is in motion, along the shaft.
- (b) Chain power fed trimmers are used in all large mills. The saws are either jump saws, easily pushed from below the table in pairs, or swing saws, hanging above the table and, similarly, pressed down by the attendant in pairs by a touch on hand or foot levers.

F. Yard work. (Sorting and piling.)

I. Sorting.

The board after leaving the trimmer is taken up by a chain or cable conveyor and passes by the lumber inspector, who pencil-marks its quality.

The various qualities are either at once thrown into parallel gutter conveyors, leading to separate chutes, below which a wagon or truck is in waiting, or are transferred to the piles by endless chain conveyors, by hand trucks and wagons. Frequently elevated roads traverse the yard on which and below which such conveyance takes place.

II. Piling.

Strong, high, horizontal ground sills are of the utmost importance. The front sill should be higher than the middle and back sills, except in shed drying.

In some yards the front of the piles is given an overhanging "batter," to protect it from rain, an arrangement feasible only in low piles. The usual pitch of the pile is 1 foot in 10 feet or more.

The tiers of boards are kept apart by three or four well seasoned cross pieces called sticks—sawn 1 inch square and placed directly one over the other.

The usual width of the piles is from 6 feet to 10 feet.

The distance between the piles is at least one foot and should be three feet.

In order to prevent end cracks, the sticking should be placed exactly at the ends, slightly projecting over the ends.

Each pile must contain equal lengths, as "overlaps" are sure to get spoiled.

Valuable wide boards are often painted at the ends.

Oak, ash, hickory and elm require at least four months for air drying; lynn, poplar and pine about two and a half months.

Slow drying involves a loss of interest, large yard room, large insurance and slow filling of orders. Still in the case of high grade hardwoods, the use of the dry kiln is disastrous to the lumber.

Thin lumber does not check as badly as thick lumber. Squares check worst of all.

A fermentation and incidentally a discoloration takes place where two fresh sawn surfaces touch one another.

Each pile should have a roof 12 inches high in front and 6 inches high in back, projecting in all four directions over the pile.

Proper curing of lumber is as important as proper sawing of lumber.

III. Dry kiln.

A dry kiln consists of
shed with gates closing tightly;
lumber conduit;
heating apparatus.

The heat is supplied—slowly—
either by a hot air fan;
or by a system of steam pipes;
or by steam admitted into drying room.

The air in the dry kiln must be kept in constant movement, so as to prevent unequal drying of the lumber in the piles.

Lumber can be more evenly dried by steam than by hot air.

Sapwater heated to boiling point expands 600 times. Consequently, wood at 212° F. contains only 1/600 of the water originally found therein.

Before building a mill be sure to consult insurance companies, submitting mill plans.

The insurance company prescribes the distance between the yard, boiler house, engine house, mill and dry kiln. The rate of insurance on a mill is 5% and over.

§ XVIII. WOODWORKING PLANT.

A. Planing (surfacing, dressing or sizing).

The planer consists of cylindrical cutter heads carrying two to four knives and making 3,000 to 5,000 revolutions per minute. It is preferably belted at both sides.

The smaller the diameter of the cylinder with its knives, the smoother is the planing.

The feeding is done either by two to four feed rolls (above) and friction rolls (below) or by a traveling bed. The entire cutting length of the knives should be uniformly used.

The top cutter should do the heavier work in double surfacers. The knives are usually sharpened automatically.

Lumber is fed into the machine at the rate of 20 feet to 150 feet per minute. Hardwoods more slowly than the soft woods.

The chip breaker is merely a front pressure bar preventing long splinters from being torn off.

Price of single planers is \$100 to \$400; of double planers \$400 to \$800.

No machine should have wood in its construction.

B. Flooring.

The flooring machine is a surfacer having an additional outfit of two side cutters revolving on ratchet spindles, cutting tongues and grooves.

The machines weigh 5 tons and more.

The usual flooring made is hard maple.

Planers and flooring machines must be provided with a folding hood connected with an exhaust fan, so as to prevent the shavings from clogging up the machinery or from pressing themselves into the planed surface.

C. Resawing.

Resaws are either circular or band resaws.

The use of a resaw involves a great saving, since it takes a very fine kerf and at the same time relieves the work of the main saw.

The feed is automatic and consists of four rolls.

Circular resaws have as low as 19 gauge at the rim and are frequently built as segment saws.

D. Ripping.

The rip saw is a circular saw running on a bench and allowing, by a gauge arrangement, to cut any desired width of board or strips. It is usually hand fed.

A power fed gang rip saw is merely an edger.

E. Cut off saws.

Cut off saws are either swing saws, jump saws, stationary saws with carriage moved by hand or automatically, or traveling railway cut off saws when the saw is moved horizontally against the timber.

F. Sand papering.

I. Belt sand papering, for carriage spokes, axe handles, buggy poles etc.

II. Disc sand papering, notably for boxes.

III. Spindle sand papering, for small tool handles.

IV. Cylinder drum sand papering.

The object to be sand papered is always fed onto the machine by hand.

G. Scraping.

Under "scraping" is understood the removal of an extremely thin (not over 1/64 inch) layer of tissue from a planed surface. It is meant to replace and to cheapen the process of sand papering, and is not intended to reduce the thickness. The scraper consists of power driven, smooth feed rolls and of one stationary knife, over which the boards are passed. Corky or stringy lumber cannot be scraped.

H. Mitering.

In mitering the stock is run along the so-called "fence" against a circular saw, the plane of which forms a variable angle with the plane of the saw table.

I. Moulding.

Mouldings are either one, two or four sided.

Cutter heads, into which cutters of variable size and form are inserted, secure any variety of patterns of moulding. Moulders are often called "stickers."

J. Miscellaneous.

Under "matching" is understood the cutting of a tongue and groove into the edge of box boards, flooring boards etc. The work is done by a knife and cutter head.

Under "gaining" is understood the ditching across a piece.

Under "plowing" is understood the ditching along a piece.

"Tenoning" is especially required for doors and blind slats—single and double tenons being distinguished.

Door panels go through a "panel raising" machine.

Sash and door "relishing" means the biting or sawing of large teeth into the tenon.

§ XIX. VENEERING PLANT.

Veneers are either sawn or peeled (sliced). The furniture factory and the package trade use veneers, with entirely different ends in view, on a daily increasing scale.

The thickness of sliced veneers ranges down to 1/120 inch; veneers less than 1/40 inch thick, however, are rarely used.

Sawn veneers are 1/20 inch thick or thicker.

A. Veneer saws.

Any saw of a fine gauge is a veneering saw. Largely used are the:

- I. Horizontal mill saw;
- II. Fine band saw;
- III. Circular saw ground to a fine gauge (19 gauge) at rim, strong (5 to 10 gauge) at center; there is only one collar, to which saw is screwed. Veneer saws consisting of sections screwed to a common centerpiece are common.

B. Veneer cutting machines.

Logs are boiled or steamed (in exhaust) for several hours beforehand. Usually, logs 3 to 5 feet long are used, the length of the log almost equaling the length of the knife.

I. The rotary machine peels any log of, say, over 18 inches diameter, notably poplar, lynn, gum and cottonwood, into thin layers by revolving the log slowly against a sharp stationary knife. A clipper cuts the roll into pieces of proper size for strawberry boxes, staves, potato barrels, box boards, furniture backing etc. The core of the log, some 6 inches in diameter, does not allow of peeling.

II. The stationary log cutter consists of a knife set in a sash frame removing at each stroke a thin slice or board.

C. Advantages of veneering.

- I. There is little or no loss of timber for kerf and sawdust. Valuable logs (for furniture, cigar boxes) are invariably veneered nowadays. Logs too short for lumber are fit for peeling.
- II. Veneers show little shrinkage and little checking. Hence they allow of rapid seasoning. For that purpose, the veneers are frequently passed between heated rollers.
- III. The rotary machine yields very large veneers often entirely free from knots which are merely contained in the core left unpeeled.

§ XX. BOX FACTORY.

A. Kinds of boxes.

- (a) Planed or unplaned.
- (b) Knocked down or set up.
- (c) Nailed, lock-cornered or dovetailed.

B. Material.

Wood as light as possible—readily planed, nailed and treated.

The best is white pine; next are spruce, basswood, poplar and, more recently, yellow pine, hemlock, gum, cottonwood. Elm and sycamore are used for special purposes.

C. Machinery.

A well equipped plant contains planers, resaws, rip saws, cut off saws, box board matchers (which tongue and groove composite sides), lock corner machine (or nailing machine or dovetailing machine), sand paper machine and printing machine (drum pattern).

D. Business side.

The skill of the box maker is shown by working up, without waste, the proper proportions of widths and thicknesses. Careful piling of lumber in the yard, separating according to width and thickness, is very essential.

The interdependence between crop prospects and box prices is easily felt by the box makers.

For large boxes the nailed pattern is preferred, being the strongest. Box shook fasteners and box strapping increase the strength.

The lock cornered box is preferred for starch, plug tobacco and small boxes. Lock cornered boxes are required either by the bad qualities of the lumber or by the quality of the stuff packed. Locked corners demand gluing. "Bevel locked" corners and "inclined locked" corners are scarcely used. The dovetailed box does not require gluing. The mechanical process for stamp locked corners (dovetails stamped into thin boards) is not yet perfected.

E. Expense of manufacture.

I. The manufacture of 1,000 feet of lumber into shooks involves a bill of \$4 for labor and \$1 for wear and tear.

II. One thousand small lock cornered boxes—9x6x3 inches, $\frac{1}{4}$ inch thick for frame and $\frac{3}{16}$ inch for top and bottom—require 700 board feet of lumber worth \$8.50 in case of white pine; \$5.10 for labor; \$2.72 for glue, wear and tear; \$2.50 for ten packing crates.

§ XXI. BASKETS.

A. Willow baskets.

They are hand made, mostly from cultivated shoots of *Salix viminalis*, *amygdalina* and *caspica*. Shoots 1 to 2 years old are used, being cut either in fall or in spring. In the first case, the bundles of shoots are kept in water over winter. The shoots are peeled after the rising of the sap by being passed through an iron or wooden fork; then rapidly dried to retain the white color. In this condition the material may be stored away for years. The shoots are bathed in water before weaving to restore flexibility and toughness. The bottom of the basket is made first, and then, frequently with the help of a

model, the standards or uprights of the wall are fixed. The manufacture has been introduced into New Jersey and New York.

B. Wooden baskets.

They are used for picking and transportation of bulky farm produces. Sizes $\frac{1}{2}$ bushel to 2 bushels.

- I. The hand made basket, from thin strips split and shaved from basket oak and white oak (sapwood).
- II. The Briggs stave basket consists of radial ribs cut from $2\frac{3}{4}$ inch oak planks; cross cut into lengths varying from $12\frac{5}{8}$ inch for $\frac{1}{2}$ bushel to 18 inches for 2 bushel baskets. The ribs are jointed and pointed to an exact fit for a round center plate and then bent over a model form having grooves indicating the proper position for each rib and for the strong elm hoop clasped around the rim.
- III. The common wood basket is made of straight long ribs up to $\frac{1}{4}$ inch thick, cut on a rotary veneer machine. No center piece, no pointing and no jointing are required. The ribs are bent over a model form. A workman is said to make about 300 baskets in a day.

§ XXII. COOPERAGE.

A. Terminology.

- I. "Slack" cooperage turns out barrels for packing lime, vegetables, cement, salt, nails, crockery, sugar, flour, etc.
- II. "Tight" cooperage deals with barrels for liquids and for meat (pork).

B. Material used:

Any species may be used for slack cooperage. Alcoholic liquors must be cased in white oak (*Quercus alba*, *michauxii*, *prinus*, *macrocarpa*, *minor* etc.). Red oak will not hold whisky, but is used for other staves, flour barrel heading, sawn and coiled hoops.

White ash is used for pork staves and butter tubs.

Elm yields the best coiled hoops and the best slack staves.

Cottonwood and gum are cut for staves on a large scale.

Chestnut is used for cheap slack barrel hoops; yellow poplar for tobacco hogsheads; basswood for flour barrel headings; beech and maple for sugar barrels; second growth of hickory, birch and ash for hoops.

For buckets, red and white cedar; for tanks, cypress and redwood are preferred.

C. Specifications:

- I. Flour barrels contain 196 pounds, or 3.57 bushels, or 32 gallons of flour.

The diameter of the head is 17 inches; the length of the staves 28 inches.

The forms preferred in slack cooperage, either locally or for given goods, vary to such a degree that figures descriptive of the forms cannot be recorded.

II. The "Tight Coopers' Union" specifies:

- (a) Whisky barrel staves—length 34 inches to 35 inches, thickness $\frac{7}{8}$ inch, width $4\frac{1}{4}$ inch after jointing, measured across bilge on the outside.
- (b) Wine barrel staves—length 34 inches, thickness $1\frac{1}{16}$ inch after drying and planing, width $4\frac{1}{2}$ inches.
- (c) Oil, tierce and pork staves have similar dimensions, allowing, however, of sap, one or two sound worm holes and knots showing on one side only.

Variations of $\frac{1}{8}$ inch in length and $\frac{1}{16}$ inch in thickness are permitted in all staves (so called equalized staves).

Pipes, butts and puncheons contain over 100 gallons and are used for port, rum etc.

A hogshead of claret is 46 gallons.

D. Statistical notes:

- I. One thousand feet board measure in logs—Doyle's rule—yield 2,500 sawed flour staves, 3,200 veneered staves, 4,000 cut hoops or 3,000 sawn hoops.
- II. One cord of bolts, with the bark, will make 1,000, or, without bark, 1,200 slack staves.
- III. In Tennessee, eight white oaks (of over 18 inches diameter) are said to average 1,000 half barrel beer staves.

E. Prices and their tendency:

Staves—	Apr. 1, 1901.	Feb. 10, 1904.
No. 1, flour barrel, per 1,000.....	\$ 9.00	\$11.00 to \$13.50
No. 1, cottonwood, per 1,000.....	6.00	
No. 1, gum, per 1,000.....		10.00 to 12.00
Memphis white oak, without sap.....	26.00	44.00
Heading—		
No. 1, flour barrel, per set.....	.05½	.08 to .08½
No. 1, gum, per set.....	.04	.07½ to .08
Hoops—		
Colled elm hoops, per 1,000.....	7.00	9.00 to 10.00
Hickory hoops, per 1,000.....	6.00	6.25 to 6.75
Barrels—		
Flour, 12 hickory hoop barrel.....	.41	.45 to .48½
Flour, 8 patent hoop barrel.....	.39	.46
Flour mugwump (10 hickory hoops).....	.39	.45
Oil (52 gallon)		1.45

The price of white oak material has risen rapidly and must continue to rise indefinitely, substitutes for white oak being impossible.

In slack cooperage, on the other hand, raw material continues to be plentiful, and new, cheaper forms of packages enter into daily competition with the barrel.

The cost of making tierces at Chicago is: Staves (\$21 per 1,000), 39 cents; heading, 16 cents; hoops, 20 cents; wages, 25 cents; total, \$1.

F. Manufacture of heading, staves, hoops and barrels.

I. Heading.

Heading for tight cooperage is sawn from split bolts. These bolts are obtained in the woods by halving, quartering and splitting (by hand and always with the grain) round blocks which slightly exceed in length the diameter of the heading. The heart of the bolt is not removed. The bolts are wagoned or sledded to the heading plant, where they are inspected, sorted, piled and air dried.

Twenty-five horsepower are said to be required at a heading plant. The output at a "setting" of the plant averages 200,000 sets of heading.

The tight heading plant usually contains a sawing machine, an equalizer and jointer.

- (a) The heading sawing machine consists of a vertical circular saw (44 inches diameter) screwed to the arbor without a loose collar; a pendulum swing with "grate" and "dogs" to receive the bolt; a slide guiding the swing; a gauge, adjusted by screws; a separator throwing the sawed slats to the side. Price \$300.
- (b) The equalizer contains a tilting table or a carriage, which is forced against a pair of circular saws.
- (c) The jointer edges the slats. It consists of a strong wheel carrying on its side 4 to 6 straight knives. The wheel is covered by a hood. Price \$140.

For tight cooperage the joints are made secure by blind wooden nails and by coopers' flag (*Typha latifolia*) glued into the joints.

Two more machines are required to finish the heading prepared by the apparatus mentioned under a, b. and c, viz.:

- (d) The heading planer carries knives 16 inches to 24 inches wide and has a capacity of 8,500 headings a day.
- (e) The heading turner cuts the heading circularly and carves the required bevel edge. It usually carries a concave saw, to cut through the boards, and on the same mandrel a small, thick circular saw which gives the bevel.

The heading, held in clamps, rotates obliquely against these saws. Price \$235. Capacity 5,000 a day. Heading is usually kiln dried.

For slack heading, quarter sawing is usually not required. Ordinary lumber can be used. The slack heading plant may or may not contain all of the machines enumerated under a, b, c, d and e.

The tight heading plant of the woods contains the machines a, b and c, while the machines d and e are usually combined with the cooper works, unless they form a separate establishment.

II. Staves.

- (a) Staves for barrels containing the more valuable beverages are hand made (rived staves). The riving of staves wastes timber. Proper bilge and curvature are obtained either by hewing (Germany) or in the finishing plant (America).

The white oak timber used must come from straight trees of over 18 inches diameter. Such trees are found in clumps only. Hence the necessity of a portable finishing plant, using from 15 to 35 horsepower. At each set or site—now usually 15 miles from the railroad—at least 100,000 staves are manufactured. Six hundred rough staves have the weight of 1,000 finished staves. Hence it is wise to bring the plant close to the timber.

The felled tree is sawed (by hand) into blocks of two inches more than stave length, which are placed on their larger ends. Then the sap line is demarked with a pencil, and inside the sap line, with the help of a pattern showing the cross section of a stave, as many staves are pencil-marked as possible.

By axe, wedges and wooden mauls the block is then halved and quartered (and rehalved and requartered in case of heavy blocks), the clefts following the pencil marks. The sectors are then split, along the annual rings, into rough staves—always following the pencil marks.

The core of at least four inches diameter, containing the small limb-stubs, is thrown away.

The rough staves are inspected and sorted and piled hogpen-fashion for air drying, either before or after sledding or wagoning to the finishing plant. It might be added here that this finishing plant is—contrary to expectation—never combined with a heading plant.

- (b) The "stave buckler," by which three-fourths of all rived staves made in the United States are refined, dresses and planes both sides of the staves to proper curvature and bilge. A rack forces the rough staves through the narrow passage left between two knives (either straight knives, or

curved to correspond with the periphery of the finished barrel) which are fastened in a rocking frame.

- (c) The "stave dresser" frequently takes the place of the buckler. It carries knives on two cutter-heads, dressing and hollowing the stave on both sides to proper thickness and leaving either an abrupt or a gradual shoulder
- (d) The stave saw yields staves of equal form, but greater permeability, more economically than the hand. Stave bolts must have the following minimum dimensions: thickness with grain 5 inches; width close to heart 3 inches.

The bolts are barked and hearted in the woods, being split from logs having at least a diameter of 15 inches inside the bark.

The stave saw consists of:

1. A hollow steel cylinder, having the diameter of the barrels to be made and carrying saw teeth at one end.
 2. A carriage with clamps passing the saw cylinder.
 3. A stave holder running into the cylinder and removing the sawed staves. Capacity 12,000 staves per day.
- (e) In slack cooperage, a stave cutter is often used, consisting of a circle (20 inches for fruit barrels) with one knife attached, making 150 revolutions per minute. The stave bolts are steamed beforehand. The knife separates at each revolution of the circle, or by each single stroke, a stave from the bolt.
Capacity 140,000 per day. Price \$130. Horsepower, 4.
 - (f) The rotary veneer machine is now also used to cut 4 inch or 4½ inch gum staves.
 - (g) The stave equalizer trims the ends and gives the staves the proper length. It consists of two circular saws and a tilting bed or a carriage.
 - (h) Stave listers or jointers edge the staves in such a way that the edges coincide with a plane through the axis of the barrel.

Staves for export are straight listed and without bilge.

The stave jointer is either a circular swing saw or it consists of two circular saws; or of a number of inclined knives held by cutterheads; or of one knife running in a sash frame; or it resembles a heading jointer (starjointer).

- (i) In the "stave planer," a steel pattern passing through the machine with the stave lifts the cutters in such a way as to allow the shoulders of the staves to retain a greater thickness than the middle of the staves.

III. Hoops.

In tight cooperage, steel or iron hoops are used, driven over the barrel by hoop drivers or trussing machines and sometimes fastened by hoop fasteners.

In slack cooperage, wooden hoops are still preferred and wire hoops are only occasionally used. Wooden hoops are either hand made, especially the long white oak hoops used on tobacco hogsheads, or sawed from plank by a hoop machine, or finally knife-cut on a rotary machine or a sash frame machine.

A machine by which sawed hoops are obtained directly from logs does not seem to be much used. By special machinery hoops are planed, pointed, lapped and punched.

A hoop coiler rolls the hoops into bundles; usually the outfit of a "sawed hoop" plant consists of a saw bench, a saw machine and a coiler.

IV. Barrels.

Putting up a barrel requires:

- (a) Heating, in order to increase the flexibility of the staves held together by an iron form and by one or two hoops.
- (b) Bending in an apparatus consisting of screw and rope, windlass and rope, or of a funnel press.
- (c) Crozing, i. e., making a groove for the insertion of the heading, either by a hand planer or by a power groover.

The finished barrel is automatically planed on the outside; if it does not assume the exact form of a doubly truncated paraboloid, it is pressed into shape by a barrel leveler.

§ XXIII. WAGON WORKS.

- A. The raw material must be tough and strong and, above all, air dry. The dry kiln often follows after two or three years of air drying.

Second growth of black or shell bark hickory is used for tongues, shafts, spokes, rims, axles, neck yokes, whiffletrees and eveners.

White oak or burr oak is used for spokes, tongues, bolsters, hounds, reaches and axles.

Black birch, rock elm, white oak and locust are used for hubs.

Wagon beds are made of yellow poplar, pines, cottonwoods, the composing boards being either ship lapped or tongued and grooved.

White ash, bending easiest and best of all woods, is used for rims, bent seats, bent bows, shafts etc.

B. The manufacturing machinery is usually supplied by the Defiance Machine Works, Defiance, Ohio.

- I. Hubs are cut direct from log to proper length by double equalizing saws and are turned on outside automatically on a lathe; bored for boxes (thimbles); chisel mortised for spokes; and set with two to four iron rings.
- II. Spokes are obtained from bolts by rip sawing into squares which are turned on a lathe; tenoned at the big end; equalized in length; sandpapered and polished; and driven into hubs by automatic hammers.
- III. Rims and felloes are either bent to proper form or sawn from straight bolts. In the first case, the bolts are steamed or boiled; then bent and pressed in an iron pattern when hot; then cased up and dried; then bored to receive the spokes; rounded on the inside with a slight elevation left around the hole; planed and finally sandpaper polished.
- Very wide plank is required for sawn felloes, which are obtained either by a set of concave saws, having the required curvature, or by a narrow band or scroll saw which follows the pencil marks of a pattern made for each piece on the plank.
- IV. Axles are turned on a lathe according to a steel pattern spanned in the lathe; are gained to receive bolsters and hounds; and have the thimble skeins driven on by hydraulic pressure.
- V. Shafts and poles are sawn from plank $1\frac{1}{2}$ inch to $2\frac{1}{2}$ inch thick and $8\frac{1}{2}$ to 12 feet long; are heated and bent, cased, dried, rounded and belt polished.

C. Few establishments make entire wagons. Usually shafts, spokes, rims, axles etc. are made in factories close to the woods, while other factories closer to the cities or to railroad centers put the wagons together after buying their component parts.

§ XXIV. SHINGLE MILLS.

A. Material.

Breasted, shaved, rived or rifted shingles (meaning hand made) are used in the backwoods only. At Biltmore, shaved shingles made of chestnut cost \$2 per M., while so called boards, two feet long and six inches wide, split from white oak, cost \$3 per M. Shaved shingles cannot be laid so neatly as sawn shingles.

For machine made shingles are used:

On the Pacific coast, red cedar;

In the Lake States, white pine, white cedar, spruce, norway pine and hemlock;

In the South, cypress, longleaf pine and shortleaf pine.

B. Durability.

The durability is said to be for:

White pine rived, 20 to 35 years.

White pine sawn, 16 to 22 years.

White pine (sappy) sawn, 4 to 17 years.

Chestnut rived, 20 to 25 years.

Cedar sawn, 12 to 18 years.

Spruce sawn, 7 to 11 years.

C. Specifications.

The usual size of sawn shingles is: 16 inches or 18 inches long; 4 inches wide; 1-16 inch thick at small end; $\frac{1}{2}$ inch thick at butt end. A bundle of shingles contains 250 pieces, is 20 inches long and has 24 tiers.

A carload of white pine shingles, weighing 22,000 pounds, contains 70,000 16-inch shingles; a large car of red cedar shingles contains 170,000 pieces.

One thousand shingles cover 100 square feet of roof, each showing 14.4 square inches to the weather.

A rule for the number of shingles required for a roof is: ascertain number of square inches in one side of roof; cut off the last figure, and the result is the number of shingles required for both sides of the roof. In this case, each shingle shows 20 square inches to the weather.

Shingles are usually laid to show 4 inches of their length, which arrangement yields, in 16-inch shingles, a quadruple layer of shingles on the roof. The higher the grade of the shingles, the larger is the weather face permissible.

D. Machinery.

The machinery used in a shingle plant consists of:

- I. Drag saw, either driven from a countershaft or acting directly from the piston, cutting the logs into shingle lengths.
- II. Bolter, a circular saw cutting the round blocks into bolts, the thickness of which equals the width of the shingle. Bolts split with an axe yield a better grade of shingles but cause a large waste of timber. A knot saw may be used after bolting to remove knots, rot, sap etc.
- III. Shingle machine, constructed in a variety of forms:
 - (a) A knife is spanned in a sash frame moving up and down and severing a shingle at each stroke from steamed bolts. This system, furnishing "cut shingles," is not much used.
 - (b) The shingle saw machine uses a circular saw lacking the loose collar and screwed onto the fast collar. The gauge at the center of the saw may be very heavy while the gauge at the rim is from 15 to 20 only.

The shingle blocks are fastened into either a slid-

ing frame or a rotating frame and are tilted continuously, so as to alternate edge and butt cuts. The sliding frame is either hand fed or power fed. A machine takes from one to ten blocks at a time.

- IV. The jointer is meant to give a rectangular shape to the shingle. It is either a single or a double rip saw (two saws 4 inches apart) or a wheel jointer consisting of a steel wheel carrying, close to the circumference, 4 to 8 knives radially or almost radially set and of a hood covering the machine and connected with a blowpipe to remove shavings. The shingles are placed opposite an opening in the hood and pressed by hand against the knives, which make about 500 to 800 revolutions per minute.
- V. The shingle packer, used for 16 inch and 18 inch shingles, consists of a bench and two slotted and overhanging steel rods. The attendant pressing the rods down by hand or foot packs the shingles tightly with their fine ends overlapping.
- VI. Shingle planers, fancy butt shapers and dry kilns are found in up to date plants. After dry kilning, bundles require tightening up.

§ XXV. LATH MILL.

The usual length of laths is 4 feet; the weight per 1,000 is 500 pounds. One thousand laths cover 70 square yards, and a cord of slabs yields 3,000 laths.

All softwoods, further yellow poplar, cottonwood and linden form the raw material for lath.

The machinery used consists of:

- A. Slab resaw, by which the last board is cut out of the slab. It contains a circular saw and feed works pressing the slab in to the saw.
- B. Lath bolter, consisting of a single or double cutoff.
- C. Lath machine, which is either an ordinary rip saw having up to six small circular saws and an automatic feed, or a cutter-head and knife machine. The latter machine makes the so called "grooved" lath.
- D. Lath bundling machine, which presses the laths together by a foot or hand lever and facilitates binding.

§ XXVI. CLAPBOARD MILL.

The cross section of clapboards is either square or, more usually, beveled, with the big edge from $\frac{3}{8}$ inch to $\frac{5}{8}$ inch thick.

They are manufactured either from boards 1 inch thick fed through a resaw, the feed rolls of which are inclined toward the saw, or by special clapboard machinery directly from the log. Logs, in the latter case, are cut in pieces of proper lengths (4 feet to 6 feet) by a drag saw;

are turned on a lathe and then spanned into a sliding frame (between pins). Frame and log pass a circular saw with and not against the rotation of the saw. After passing, the log is automatically turned by an angle corresponding with the bevel of the clapboard.

This process leaves a four inch core unused.

A planer, molder or jointer dresses the sides and a butter or trimmer dresses the ends.

§ XXVII. NOVELTY MILL.

Novelty mills have sprung up, in recent years, all over the Northeast, manufacturing trays, wooden dishes, wooden wire, rules, pen-holders, flasks, skewers, toys and thousands of playthings of the hour.

The variety of the raw material used is as great as the variety of the goods manufactured. Still, birch seems to be the acknowledged leader for novelty makes.

Wooden dishes and wooden wire may deserve particular mention.

A. Wooden dishes.

I. Material.

Yellow poplar is used for large wooden trays. Second growth white pine (cuts taken between whirls) is said to be used in New England. Maple is preferred for small oval wood dishes, turned out by a special machine automatically.

II. Manufacture of oval dishes.

These oval dishes are obtained from sawn blocks, scaling from 6 inches by 8 inches to $7\frac{1}{4}$ inches by $9\frac{1}{2}$ inches.

The dishes are cut with the grain from the side face. Blocks are thoroughly boiled. The cutting knife, revolving circularly, makes 25 dishes to the inch and 75,000 per day.

Two facing knives shave the block clean between every two cuts, carving out true edges.

A screw fed carriage automatically feeds the block into the knives. No skilled labor is required. The attendant merely removes the remnants of a spanned block and places a new block in the carriage.

B. Wooden wire.

Wooden wire is used for mattings, screens, inner rack of ladies' hats etc.

The raw material consists of willow, basswood and poplar plank.

A series of planing knives, in the form of sharp rimmed, fine steel cylinders, plies in a sliding frame over the plank, severing at each stroke a series of wires having the length of the plank.

A straight planer knife follows in the wake of the fine cylinders, removing the irregularities left on the plank.

§ XXVIII. MATCHES AND THEIR MANUFACTURE.

Wooden matches are either round or square.

- A. Round matches are made on a machine resembling the wooden wire machine described in Section XXVII.
- B. Square matches are made from blocks 16 inches to 24 inches long which, after steaming or boiling, are peeled on a rotary veneer machine into layers having the thickness of a match.
 - I. The veneers are automatically clipped into sheets having a length of 6 feet and width equaling 5 to 12 match lengths. These sheets are heaped up in packs containing 50 to 60 tiers.
 - II. A knife system, with vertical spur-knives, plays in a vertical sash and cuts from each tier, at each stroke, 5 to 12 matches. The pack, after each stroke, is moved forward the thickness of a match. The machine has a daily capacity of 25,000,000 matches.
 - III. The matches are then dried and cleaned by sifting.
- C. The treatment thereafter is identical for round and square matches, consisting of the following operations:
 - I. Causing the match pegs to lie parallel, by rocking them in an oscillating drawer.
 - II. Fixing about 2,250 matches at a time in a clasp or frame.
 - III. Dipping the clasp (for fine matches) wholly into paraffine and the tips thereafter into a chemical compound (mastic) which forms the inflammable head. The mastic consists of one or more oxidizing substances (chlorate or bichromate of potash), often mixed with a particle of some explosive, so as to allow of ignition by friction on any rough surface.
- D. The raw material for matches is derived from cottonwoods, linden, sapwood of yellow poplar, white pine, spruce. A white, soft and long fibre is required.

§ XXIX. SHOE PEGS AND THEIR MANUFACTURE.

- A. Wooden shoe pegs are used to fix the "uppers" to the shoe sole and to construct the heel. The pegs are automatically fed from a pegging machine.

Pegs are $\frac{3}{8}$ inch to $\frac{7}{8}$ inch long, square with a prismatic head. The raw material consists of birch and hard maple.
- B. Manufacture.
 - I. The blocks are cut into discs, $\frac{3}{8}$ to $\frac{7}{8}$ inch thick, by a circular saw.
 - II. The discs are pointed in a pointing machine, which plows parallel grooves, lengthwise and crosswise, into the discs. The distance between two furrows equals the width of the peg.

III. The splitting machine severs, by the gradual strokes of a knife (first stroke down to $\frac{1}{2}$, second stroke down to $\frac{3}{4}$ of thickness of disc), the disc into strips of pegs and, playing crosswise, into individual pegs. After each stroke of the knife the disc is moved toward it by the width of one furrow. During the operation the disc is held in a leather frame.

IV. The wet, red pegs are then bleached by applying sulphuric acid; then dried in heated drums; then cleaned from splinters and irregularities by sifting.

§ XXX. EXCELSIOR MILL.

A. Grades of product.

First Grade—Fine wood wool, thickness from $\frac{1}{500}$ inch to $\frac{1}{64}$ inch.

Second Grade—Common fine wood wool.

Third Grade—Mattress stock.

The greatest demand is for stock $\frac{1}{100}$ inch thick and from $\frac{1}{32}$ to $\frac{1}{8}$ inch wide.

B. Usage. Excelsior is used for upholstering and for packing (glassware, furniture, confectionery etc.). It is preferred to straw owing to its greater elasticity and to its lack of dust. It is easily colored. A limited amount of excelsior is woven into mattings and rugs.

C. Kinds of wood.

Basswood is best; balm of gilead, cottonwood and yellow poplar come next. Pine and spruce also are used. One cord of wood will yield 1,500 pounds of excelsior.

D. Process of preparation.

The wood is peeled, cut into 38-inch blocks, and the blocks split into slabs 5 inches to 6 inches thick. These slabs are thoroughly air seasoned under cover, and finally cut into two lengths of 18 inches each.

Frequently the core of blocks peeled on the rotary veneer machine is used for excelsior.

E. Machinery.

Excelsior machines are small, upright knife machines, or carry the knives on a disc set in rapid rotation. The modern machine, however, is an eight block horizontal machine consisting of:

- I. Two sliding steel frames carrying eight tool heads into which the knives and the comb-like spurs are spanned. The sliding frames are moved by powerful cranks and pitmans on maple slides.
- II. Two stationary frames, above the sliding frames, each having four sets of rolls, each set pressing a block by its rotation downward against the knives.
- III. The shavings, falling through the sliding frame, are carried out by broad belts.

- IV. The daily capacity of an eight block machine is 4,000 pounds of fine wood wool, or 10,000 pounds of mattress stock.
- V. Additional machinery consists of automatic knife grinders, baling presses, cut off saws etc.
- VI. The price of the machinery for a modern plant is about \$2,000. About 30 horsepower are required.

§ XXXI. GROUND WOOD PULP AND CHEMICAL FIBRE AND THEIR MANUFACTURE.

A. Historical remarks.

Up to 1854 paper was made from cotton, linen and hemp fibre, precipitated from a mush in the shape of a matting.

Wood grinding was invented in 1854. Since 1867 the ground wood is refined by chemical processes which separate the wood into thinner strings of cells and free it from rosin, tannin, albumen, gums etc.

In the United States there were, in 1890, 82 mills producing \$4,600,000 worth of wood paper, while the value of the output in 1900 approximated \$20,000,000.

Rags, manila, straw and waste paper used as raw material for paper still outrank in value (in 1900) the wood used as raw material.

In 1900, close to 2,000,000 cords of wood were consumed, worth nearly \$10,000,000; three-fourths being spruce and one-fourth poplar and miscellaneous.

If the United States shall conquer the Swedish and German export and supply the entire consumption of wood paper at home, 6,000,000 acres of well managed wood lands will be required to produce the raw material.

B. Statistical remarks.

One cord of wood yields one ton of ground pulp wood (mechanical fibre) or $\frac{1}{2}$ ton of chemical fibre. In the so called "news grade" 80% of pulp is mixed with 20% of chemical fibre.

Japanese paper is made of the inner bark of a mulberry tree (*Brussonetia*).

For highest grades of writing paper, cotton and linen are used.

An average mill produces 25 tons a day.

A modern pulp plant requires annually, at least, 6,000 cords of wood; a modern fibre plant at least 25,000 cords.

The price of the product loco factory is about:

For ground wood pulp, \$13 per cord;

For soda fibre, \$20 per cord;

For sulphite fibre, \$25 per cord.

C. The plant.

The plant requires an outlay of about \$10,000 per ton of daily production. Unlike a saw mill, a paper mill cannot be shifted when the nearby supply of raw material is exhausted.

A plant must be located:

- I. Close to water; water is not so much used for motive power as for the dissolution of the fibre in the washing process.
- II. Close to cheap wood supply; wood must be plentiful and uniform, of a long, straight fibre, readily interlacing and white. Spruce is considered best, the price at river fronts being about \$3.50 per cord and at mill from \$4.50 to \$5.50. Cottonwoods and poplar are next in importance. Price at river fronts \$2. Hemlock and balsam are mixed with spruce in a daily growing proportion. Birch, beech and maple can be used only for wrapping paper and cardboard, the fibre being short, brittle and unbleachable.

The use of pine is handicapped by the expense of the removal of the rosin.

The Pacific spruces and cottonwoods may have a great future.

- III. Close to cheap coal, since the coal consumption per pound of paper amounts to 5/16 of a pound of coal. So much coal is required for heating, drying and bleaching, that all excepting 15% of the machinery can be driven free of charge.

D. Process of manufacture.

The manufacture is either purely mechanical (ground wood pulp) or also chemical. In the latter case, distinguish between the soda process, the sulphite process and the sulphate process. The electric process, though very promising, is still in early infancy.

The principle of manufacture is:

Grinding and beating of wood in water until it forms a fluid pulp; allowing water to run off leaving a matted stratum of wet fibre; bleaching; drying; pressing.

I. Ground wood fibre.

- (a) The wood is cut into bolts one foot long and five inches thick. The bark is removed, and the knots are usually bored out.
- (b) The bolts are pressed against stone mill-wheels which turn slowly under constant influx of water. Bolts must be ground in the direction of the fibre.
- (c) The fluid pulp is carried through sieves retaining the long splinters, which are transferred to a pulp engine for mechanical refining.
- (d) The fibre is ground a second time both in stampers and rotary mills.
- (e) The fluid is separated according to fineness by sieves of different mesh which allow the water to run off. The filtered mass is taken up by

endless belts of cloth which carry it as a thin matting through a series of heated rolls.

- (f) The mattings are dried by superheated steam, by pressure or in the air. Pulp is shipped in rolls about 3 feet long and $1\frac{1}{2}$ feet in diameter. It is not paper but merely the leading raw material for ordinary paper.

II. Soda process.

This process consists of:

- (a) Sawing wood into discs about 1 inch thick.
- (b) Grinding and dissecting the discs into fragments about $\frac{1}{24}$ inch by 1 inch in size.
- (c) Packing the material into perforated iron boxes which are placed in digestors containing a solution of caustic soda.
- (d) Boiling the wood for four hours under a pressure of 125 pounds.
- (e) Grinding between stones.
- (f) Repeated washing and sifting.
- (g) Bleaching with chlorate of lime and washing.
- (h) Taking up mass by endless rolls of cloth and drying it between heated rollers.
- (i) Reclaiming caustic soda by boiling and melting.

III. Sulphite process.

Same as the soda process, excepting points "c," "d" and "g."

The wood fibre is first cooked without chemicals and then boiled for 60 hours with calcium sulphite—a cheap chemical usually prepared at the mill itself.

No or only little bleaching is required, the fibre being free from color when leaving the digester.

The expense of manufacture per ton of sulphite fibre is said to be as follows:

Two tons of spruce.....	\$ 9.00
Coal	3.00
Sulphur	3.30
Lime	.70
Labor inclusive of office force.....	7.00
Wear and tear	2.50
Total	\$25.50

These figures may seem to be unusually high.

The sulphite process offers the following advantages:

- (a) It is cheaper (no bleaching, cheap chemicals).
- (b) It does not interfere with the strength of the fibre.
- (c) It yields a larger output of fibre per cord.

Hence the sulphite process is rapidly superseding the soda process. Exception in poplar.

IV. Sulphate process.

It is adopted in mills originally arranged for caustic soda process. The chemical used is sodium sulphate, the price of which is only one-third that of caustic soda. It is reclaimed out of its watery solution by evaporating and melting. This process gives the old soda mills a new lease of life which were about to be forced to the wall by the superiority of the sulphite process.

V. Electric process.

The electric current is used to obtain from an 8% solution of common salt (Na Cl) its composing parts, viz., caustic soda and hydrochloric acid.

These substances, alternately acting upon the wood prepared in the manner described under II, a, b, and c, dissolve the lignin and destroy the incrustations of the fibre, so that pure cellulose remains in the digestors.

Two digestors are used, connected with the positive and the negative electrode of the current respectively.

The process is said to be faster and cheaper than the sulphite process. No bleaching required.

§ XXXII. TANNING MATERIALS AND TANNERIES.

A. Tanning materials.

Tanning materials used in the United States were in 1900:

Hemlock bark, 1,170,000 cords.

Oak, 445,000 cords.

Gambier, 128,000 bales.

Hemlock bark extract, 13,000 barrels.

Oak bark extract, 54,000 barrels.

Quebracho bark extract, 20,000 barrels.

Sumac bark extract, 8,500 barrels.

Chemicals, \$2,225,000 worth.

In the sole leather, belt leather and harness leather industries, vegetable tanning material is still preferred. Mineral or chemical tannage, however, has been developed during the last ten years to a degree threatening to entirely supplant the old methods.

Since 1900, extracts obtained from chestnut wood have gained both favor and importance.

B. Tanbark in particular.

I. Notes on tanbark.

(a) The corky layers of bark do not contain any tannin and are usually shaved off. In Europe, young oak bark not having any cork is preferably used.

(b) Fresh bark contains on an average 45% water and shrinks heavily during the drying process.

- (c) While oak bark must be peeled in spring immediately when the sap begins to rise (April-May), hemlock bark may be peeled at any time from May to September.
- (d) Bark peeling season for oak is from early April to the end of June. Trees in the bottoms peel earlier than those higher up.

The bark on the uphill side of a tree is thinner than the bark on the downhill side.

Trees exposed to the weather, isolated, on unprotected slopes, have short boles but a heavier bark than those growing under the reverse conditions.

Dying trees will not peel.

II. Peeling process.

- (a) Girdle the tree about four feet above the ground; remove bark from stump and roots; fell the tree in such a way as to leave the bole well raised above the ground.
- (b) Notch (with axe) a line along the tree and rings around the tree every four feet. Have two men with "spuds" peel the ringed sections, and see that the pieces peeled are as wide as possible and, as near as possible, four feet long. Large pieces will dry well and will save expense in handling. Handling costs more than peeling.
- (c) Lean the peeled pieces against the felled bole, preferably flesh side out, as high above ground as possible, and see that the air circulates freely around them.
- (d) See that the bark is as little shaded as possible. Peel before leaves are out. Never leave bark to dry in a moist gully.
- (e) Toward evening, turn the flesh side of the bark toward the object supporting it so as to protect it from dew. The expense of "curing" is so high, however, and the danger of spoliation by rain so great, that bark is now usually placed at once "bark side out."
- (f) Pile the bark after two to three days, provided it is not wetted, close to the tree in loose piles. These piles are left for weeks in the woods. Bark is sure to mold if a rainy season sets in. Free access of air greatly reduces the danger of damage.
- (g) Finally sled the bark, by hand sleds, cattle or mules, over rough trails (best grade is about 20%) to the wagon roads, to be removed to tannery or railroad.

III. Remarks.

(a) The minimum diameter of trees and branches peeled depends on the price of bark and the price of stumpage. At the present time, far from the tannery, it does not pay to peel pieces of less than 10 inches diameter.

(b) The expense of the harvest of oak bark is per cord:

Roads, 45c; felling, 27c; peeling, 57c; piling, 72c.

On the average a man will peel per hour from 0.3 to 0.38 cord.

(c) Tannin percentages of dressed bark are, after Sargent:

Mangrove	30 %	Burr and red oak...	4.6%
Sumac	18 %	Chestnut	6.7%
Sassafras root.....	58 %	Douglas fir.....	13.8%
German oak.....	14 %	Eastern hemlock....	13.1%
Cal. Chest. oak.....	16.5%	Western hemlock....	15.1%
Live oak.....	10.5%	Eastern spruce.....	7.2%
Chestnut oak	6.2%	German spruce.....	8 %
Spanish oak.....	8.6%	German fir.....	6 %
Black oak.....	5.9%	Larch	7 %
White oak.....	6 %	Birch	4 %

C. Wood extracts in particular.

I. Tannin extracts are manufactured from bark, chestnut wood, quebracho, mangrove and oak. Quebracho wood contains 24% of tannin; chestnut wood 14% (?) of tannin.

II. The wood is shredded in a chipper and the tannin extracted (not entirely) by steam or hot water under pressure. The liquid obtained is condensed.

III. While in France the sappy branches and young shoots of chestnut are preferred, in America the heart wood and especially the butt is preferred.

IV. The wood is cut 4 feet to 5 feet long. The leather trust uses a cord of 160 cubic feet = $1\frac{1}{4}$ cords of 128 cubic feet.

V. Clear water, cheap transportation and cheap fuel are required for successful manufacture.

Only sound wood is used; wormholes in chestnut, however, do not interfere with its value.

VI. Extracts exposed to air or exposed to heat spoil rapidly.

VII. Extracts are shipped in barrels of 56 gallons capacity or in tank cars.

VIII. The price of chestnut extract is $1\frac{1}{2}$ c to 2c per pound. At

a price of $1\frac{1}{2}c$, extract is cheaper than oak bark at \$6 per cord.

- IX. One cord of chestnut wood yields 500 pounds of extract containing about 25% tannin. *500 gallons / barrel*

D. The methods of tannage employed nowadays are:

- I. Tanning by means of aluminum salts.
- II. Chamoying by means of certain oils or acids of oils.
- III. Tanning by salts of chromium.
- IV. Vegetable tanning, using the wood of quebracho, chestnut and oak; the bark of various oaks, hemlock, spruce, douglas fir, birch, larch, willows; fruits, cups and galls, i. e., divi-divi, catechu, myrobalans; further, the leaves of sumac. Instead of using these vegetable matters, their watery extracts frequently are applied.

E. Object of tanning.

Tannage tends to render the skin permanently supple and durable by impregnation with tannin. Aside of the mechanical imbedding of molecules by impregnation, a chemical action (fermentation) may take place in the case of bark tannage, due to the presence of microbes in the bark, chemically binding the tannin to the albumen and gelatine of the skin.

F. Criteria of a good method of manufacture are:

- I. The weight of the leather produced. Since leather is sold by the pound, the tanner tries to press into the hide the maximum amount of tannin, tannin being much cheaper than hides.

Beyond a certain point, this extravagance of impregnation fails to increase the wearing qualities of leather and is therefore useless to the buyer.

- II. The color of the leather produced and the adaptability of the leather for coloring.
- III. The possibility of tannin being washed out through wear and tear. From chromium tanned leather even a boiling process will not remove the tannin.
- IV. Quickness in filling orders and amount of capital required.
- V. Cheapness of manufacture. The best leather is produced slowly only by use of materials rather poor in tannin.

G. Statistical notes.

- I. One ton (2,240 pounds) of hemlock bark will tan 300 pounds of sole leather or 400 pounds of upper leather; 4 to 5 pounds of good oak bark are required to produce 1 pound of sole leather.

One acre of hemlock wood is said to yield about 7 cords of bark, and 1,500 board feet of timber are said to carry one cord of bark.

One acre of hardwoods will yield on the average not over one-half cord of chestnut oak bark.

- . One cord of chestnut wood yields one barrel of extract.
- II. The price of bark at the tanneries ranges from \$4 to \$16 per cord. The cord of bark is not measured, but is weighed, 2,240 pounds being called a cord.
The price of a cord of chestnut wood f. o. b. cars is \$2.50 to \$3.
- III. One hundred pounds of dry hides yield 150 to 185 pounds of leather; 100 pounds of green hides yield 60 to 80 pounds. The cost of the hide amounts to from 50% to 75% of the cost of production.
- IV. The number of tanneries in the United States has greatly decreased from the year 1880 (5,628 plants) to 1900 (1,306 plants). The small tanneries using old fashioned and wasteful methods have been killed by the large and intelligently conducted modern plants. The leather trust controls over 100 of the largest plants.

The investment of capital has increased from \$73,000,000 in 1880 to \$174,000,000 in 1900.

The cost of raw material, \$155,000,000, and the value of the product, \$204,000,000, have remained almost unaltered during the same period.

- V. "Hides" are obtained from oxen, cows and horses; "kips" from yearling cattle; "skins" from calves, sheep, goats and pigs.

Calf skin is used for upper leathers of shoes; sheep skin for cheap shoes, linings and gloves; goat skin for fine upper leathers and gloves.

Hides often are split and the so called grain and flesh splits are used in place of goat and calf skin.

H. Manufacture.

The old fashioned methods used from time immemorial consisted of rinsing skins; scraping off the flesh; treating the hair with lime; placing alternating layers of crushed oak bark and of skins in rough vats. The time consumed in this process of manufacture frequently exceeded a year. The best leather, however, is produced in this way.

The modern process in manufacturing sole, belt and harness leather is:

- I. Soak in soft water (heated to less than 70° F.) to remove salt and blood and to restore the original softness and pliability of the skin.
- II. Loosen hair by either liming green hide in milk of lime for three to six days or sweating dry hides at 70° in a close room, inviting a partial decomposition of the hair sheath. The sweating is preferred for acid hemlock tannage.
- III. Remove on the "beam," by hand or machine, flesh, hair, blood, lime, dirt.

- IV. Prepare the liquors in the leech house. The liquors contain often from 5% to 6½% of tannin only. Cold water extracts only part of the tannin from either bark or wood. Very hot water may extract all, extracting with it, however, undesirable coloring matters and killing the fermenting microbes.
- V. The tannage itself is either "Acid hemlock tannage" or "Non-acid hemlock, oak and union tannage."
- (a) Acid hemlock tannage consists of:
 1. Coloring in a dilute solution of tannin.
 2. Placing skin for 2 to 4 days in a sulphuric bath (of 10% to 30%) by which the hide is swelled to a great thickness.
 3. Placing the hide in a strong, concentrated solution of tannin.
 - (b) Non-acid hemlock, oak and union tannage (2-3 hemlock, 1-3 oak bark):
 1. Treat the hide, to begin with, with very weak solutions of tannin.
 2. Gradually increase thereafter the concentration of the liquors. If a hide is at once hung in a strong liquor, its outer layers only are tanned. The hide will not swell, and the inner layers will fail to be impregnated.
- VI. The operations finishing the process of manufacture are: Washing; scouring off the so called bloom; stuffing (which means bathing in grease); drying; dampening and rolling under pressure; redrying; glossing on a brass bed by brass rollers.

§ XXXIII. CHARCOAL BURNING IN CHARCOAL KILNS.

A. Distillation of wood.

Destructive distillation of wood, under reduced admission of air, yields chemically the following proportion of substances:

I. 25 % of non-condensable gases, viz.:

carbon monoxide	acetylene
carbon dioxide	propene
marshgas	ethylene

II. 40% of condensable vapors, viz.:

acetone	formic acid
furfurol	butyric acid
methyl alcohol	crotonic acid
methylamine	capronic acid
acetic acid	propionic acid

III. 10% of tarry liquid, viz.:

tar	cresol
creosote	phlorol
toluol	naphthalene
xylol	pyrene
cumol	chrysene
methol	paraffin

IV. 25% of solid residue, viz.:

charcoal	inorganic salts
----------	-----------------

B. The kiln process.

In the kiln process of destructive distillation of wood, all of the above substances are allowed to escape unused, excepting the solid residue.

Modern technology succeeds in catching and utilizing several of the substances given under II and III, as appears from Section XXXV.

Still, the large majority of the charcoal commercially used is produced by the old and wasteful charcoal kiln.

C. Characteristic qualities of charcoal.

- I. Charcoal has per cubic foot a larger heating power than wood.
- II. Owing to its lesser weight, it is very cheaply transported.
- III. Its freedom from sulphur and phosphates makes it valuable for metallurgic work (Swedish charcoal iron).

D. The work at the kiln.

- I. For use in kilns, wood must be thoroughly seasoned, free from heavy knots. The billets must have equal length. The kilns should be charged with one species and one assortment of wood only at a time.
- II. The work consists of:

- (a) Preparation of ground near water by leveling and hoeing the soil, by removing roots and stones, by raising the center of the circle to be occupied by the kiln about 10 inches over its circumference.

The diameter of the circle is from 15 feet to 30 feet usually. The best soil is loamy sand, which secures proper regulation of the draft.

The site should be protected from wind. Twigs are woven into a wind screen on the windward side, if necessary.

- (b) Erecting the "chimney" by placing three or four poles of even height at one foot distance from a center pole, fastening them together to the central pole by withes.

The chimney is cylindrical if kiln is lighted from above, pyramidal if kiln is lighted from below.

The chimney is filled with inflammable substances (dried twigs etc.).

(c) Constructing the kiln proper.

The kiln should have a parabolic form. It consists of two or more tiers of billets placed almost vertically, the bark turned outward, the big end downward, the finest pieces near the chimney and near the circumference, the largest pieces half way between.

These tiers are topped by a cap, consisting of smaller billets placed almost horizontally. A cylindrical chimney extends through the cap. A pyramidal chimney is closed by the cap.

In the latter case a lighting channel is left on the ground running radially on the leeward side from the bases of the pyramidal chimney to the circumference. This channel, too, like the chimney, is filled with easily inflammable material.

(d) Stuffing all irregularities, interstices, cracks etc. showing on the outside of the kiln with small kindling.

(e) Covering the kiln by two draft-proof layers so as to exclude or restrict the admission of air.

1. The green layer, $\frac{1}{2}$ to $\frac{3}{4}$ feet thick, made of green branches, grass, weeds and moss.
2. The earth layer, 4 inches to 6 inches thick, consisting of wet loam, charcoal dust etc.

If kiln is lighted from below, a belt about 1 foot high running around the circumference on the ground is left without earth cover until fire is well started.

The earth layer and the green layer are thoroughly joined by beating with a paddle.

In large kilns a wooden frame (the armor) consisting of T sections is used to prevent the cover from sliding down.

III. The kiln is lighted early in the morning on a quiet day. The cylindrical chimney is stuffed up with wood from above and then closed on top by heavy covering after the fire is well started in the cap.

The lighting channel, in the case of a pyramidal chimney, is similarly stuffed and closed.

IV. The regulation of the fire and of the draft are the most important functions of the attendant who guides the fire

evenly and gradually from the cap down to the bottom. The means of guidance are:

- (a) To check draft, increased earth cover.
- (b) To increase draft, holes of about $1\frac{1}{2}$ inches diameter punctured through the cover with the paddle reversed.

If wind is strong, all holes are closed and earth cover increased.

Cracks forming in the cover must be closed at once.

In dry weather the kiln is continuously sprinkled. The kiln may explode if cover is too heavy and draft too strong.

The color of the smoke escaping through the punctures indicates the completion of the charring process above the holes (transparent bluish color).

The holes are then closed, and another row of punctures is made about two feet below the closed holes.

- V. Refilling is required where dells are forming irregularly, while the kiln gradually collapses to half of its original volume.

For refilling, the cover over the dell is quickly removed, all holes having been closed beforehand, and the dell is rapidly filled with fresh wood.

- VI. When the bottom holes show the proper color of smoke, the charring process is completed. All holes are then closed and the kiln is allowed to cool.

The duration of the charring process is from six days to four weeks, according to size of kiln. The contents vary between four and sixty cords.

- VII. The kiln is gradually, beginning at the leeward side, uncovered, and the crust of earth, after hoeing, is thrown on again. The earth, trickling down, quenches the fire. After another twelve to twenty-four hours, preferably at night, the coal is taken out in patches.

Water must be ready at hand, since fire usually breaks out when coal is drawn.

- E. Statistical notes.

The loss of weight in the charring process is 75 %.

The loss of volume is 50 %.

In America charcoal is sold by the bushel, a bushel weighing about 25 lbs.

- F. Appendix.

In Norway, Sweden and Russia kilns of trapezium form are built of peeled logs 15 to 30 feet long.

The lighting channel runs lengthwise on the ground.

The kiln is lighted at the narrow end and covered with green branches and earth in the usual manner.

The side walls being almost perpendicular, the cover is held in place by slabs spliced against the walls. No refilling is required. Fire is conducted from the top of the kiln at the big end toward the bottom of the kiln at the little end.

The process lasts six to eight weeks.

The billets are placed horizontally, skidway fashion, the largest billets being put in the center and the smallest at the head and at the foot of the kiln.

§ XXXIV. LAMPBLACK AND BREWER'S PITCH, AND THEIR MANUFACTURE.

The former is used in the manufacture of patent leather; the latter for pitching beer barrels.

- A. Raw material is spruce rosin.
- B. The process consists in a combined melting and pressing of rosin. The brewer's pitch runs out through a pipe connecting the bases of the melting vats with a cooling vat.
- C. The solid residue remaining in the vats is slowly burned in an oven. The smoke passes through a cool room and into a smoke room, the top opening of which is covered by a common bag. In this room pine soot or lampblack is deposited. The draft is regulated by the attendant according to the shape or bulge which the bag assumes under the influence of the smoke.
- D. Some turpentine can be derived at the same time if the vats are closed air tight and if the escaping gases are condensed in a worm.

§ XXXV. PYROLIGNEOUS ACID, WOOD (METHYL) ALCOHOL, AND THEIR MANUFACTURE.

- A. Raw materials: These are, preferably, broad leafed species—beech, birch, maple—which must be thoroughly seasoned. Heavy stuff is preferable, it is said, to small stuff.
- B. Distillation: The process consists in a dry distillation of the wood, differing from the charcoal kiln process merely by allowing the gases to condense.

The distillation takes place in large horizontal iron cylinders, usually about 10 feet long by 5 feet in diameter, into which the wood is run on steel trucks. After closing the cap of the cylinders (admission of air reduces the output of pyroligneous acid) the cylinders are slowly heated to a redhot. The gases forming are led through long worm pipes into a condenser.

Not all of the gases formed allow of condensation. The uncondensable gases are conducted to the fire room.

At the bottom of the cylinder, tar is forming and is let out by a system of pipes into a collecting basin. Conifers yield more wood tar than hardwoods.

C. Further treatment.

The gases, condensed to a liquid a large proportion of which is water, are then treated with lime. Lime neutralizes the pyroligneous acid, forming acetate of lime.

The liquid is then redistilled, wood alcohol going over first, water next. The residue is boiled down in open pans to the consistency of a sugar, the acetate of lime of commerce. From it acetic acid and its salts are derived in chemical works.

D. The output.

One hundred volumes of air dry wood furnish up to forty-eight volumes of pyroligneous acid.

One and three-quarters cords of beech yield 2,650 pounds of liquids, 25 gallons of tar and 700 pounds of charcoal.

The 2,650 pounds of liquids furnish 200 pounds of acetate of lime and 9 gallons of 82% wood alcohol.

E. Use: Acetate of lime is used by the chemical industry in the manufacture of acetic acid and of the salts of acetic acid.

Wood alcohol is used largely in the manufacture of varnishes, dyes, celluloid and especially for heating. It is poisonous.

§ XXXVI. TRUE OR AETHYL ALCOHOL AND ITS MANUFACTURE

A. Principle underlying the process.

Wood boiled under pressure in the presence of acids yields sugar (dextrose). This sugar, freed from the acid admixed, is allowed to ferment under the influence of yeast and changed into aethyl alcohol.

B. Raw material:

Cottonwoods, linden, yellow poplar are said to be superior to the heavy hardwoods as well as to conifers. Possibly chestnut wood, from which the tannin is withdrawn in tannin extract factories, may answer as a raw material. Unless sawdust is available, the wood is prepared, sawed and pounded as if it were to be used in the manufacture of chemical fibre.

C. Process:

The acid used does not enter into any chemical combination with the wood. It merely acts by its presence and is said to be most efficient when in statu nascendi. Sulphuric acid, sulphurous acid, hydrochloric acid or a mixture of these and similar acids are used.

The temperature of the lead-coated vats containing acid and wood is gradually raised to about 250° F. Hydraulic pressure is also applied, either before or after the boiling process. As a matter of fact, the partial conversion of cellulose into starch seems to be due to pressure—not to boiling. The acid is then neutralized and the temperature reduced to about 85° F. By the addition of yeast (fed on phosphates of potash and of ammonia) a violent fermentation of the sugar is started, ending within thirty-six

hours, when the yeast has dropped down to the bottom of the vat while the sugar has been converted into alcohol.

The liquid is distilled and redistilled, yielding alcohol of any desired concentration.

The wood remaining—only 20% of its weight seems convertible into sugar—might be used for paper manufacture or as fuel for the boilers. Classen claims, after his methods, to obtain at least 30 % dextrose from absolutely dry wood.

D. Output.

One hundred pounds of dry wood are said to actually yield about 5 pounds of 96 % alcohol. The process of manufacture is far from being perfect. A number of chemists, notably Classen, are hard at work to further improve and to cheapen the process. Cheap alcohol—a fuel, a source of light and a source of technical energy—manufactured from wood will be a boon for household, industries and forest.

§ XXXVII. ARTIFICIAL SILK MADE FROM CELLULOSE.

A. History.

Artificial silk was first prepared by Hilaire de Chardonet in 1884.

Today many patents and numerous factories to exploit them exist in the old country.

B. Process.

There are two main processes in use, namely:

I. A solution of nitrocellulose, a compound of nitric acid and cellulose in ether or alcohol, is pressed through minute capillary pipes, appearing in long, silky threads. Additional chemicals (methods of Vivier, Lehner) reduce or entirely destroy the inflammability of the product.

II. Pure cellulose is readily dissolved in a few chemicals only, notably in concentrated copper oxide dissolved in ammonia. This solution forms a waxy mass which is pressed through minute capillary openings and appears in the form of supple, long, silky threads, immediately entering a bath of sulphuric acid. Here cellulose is set free, now a solid thread, while blue vitriol and sulphate of ammonia result at the same time. The threads are spun exactly like threads of natural silk.

C. Qualities of product.

Artificial silk has an exquisite shine and is easily colored before the pressing process. The tearing strength of silk obtained from nitrocellulose, however, is now only 33% of that of true silk, its toughness only 45%.

Artificial silk is used on a daily increasing scale in silk weavings. New methods and modifications of manufacture continuously increase its chances as a substitute for natural silk.

§ XXXVIII. MANUFACTURE OF OXALIC ACID FROM WOOD.

A. Principle.

Any wood heated to about 400° F. in the presence of caustic substances yields, among many other products of disintegration, a goodly percentage of oxalic acid.

B. Raw material.

Any wood finely ground or pulverized, and especially sawdust and mill refuse, is well adapted to the process—oak as well as beech, pine, chestnut etc. Cottonwood is said to be rather poor as a raw material.

C. Process.

A mixture of caustic soda, caustic potash and sawdust is heated, under continuous stirring, in open pans ($\frac{1}{2}$ foot deep and 6 feet square) by superheated steam or air. The temperature is gradually raised to 480° (not over) F., remaining at that figure for about $1\frac{1}{2}$ hours. The melted mass, consisting of oxalate of sodium and of carbonate of potassium, is thrown into water and allowed to cool, when the oxalate forms a dough of minute crystals. This dough is freed from water by centrifugal power, then treated with lime and thereafter with sulphuric acid, with the result that gypsum is precipitated from a solution of oxalic acid.

D. Output.

One hundred parts of wood yield up to 80 parts of oxalic acid.

The quantity of output depends on proper mixture of caustic soda and potash, and on proper regulation of the temperature.

§ XXXIX. THE MAPLE SUGAR INDUSTRY.

In the sap of all broad leaved species considerable quantities of sugar are found. This quality is commercially important, however, only in the case of hard maple. In 1900 there were produced 51,000,000 pounds of maple sugar and about 3,000,000 gallons of maple syrup.

New York, Vermont and New Hampshire lead this industry. Seventeen percent of all granulated sugar made in the United States is obtained from the maple tree.

Vermont protects its maple sugar industry from counterfeits by State inspection and official stamp.

A. Tapping the trees.

I. Time. End of January and February is best.

Cold nights and hot days necessary for best results.

II. A hole is made, with an auger, $\frac{1}{2}$ inch to $\frac{3}{4}$ inch in diameter, slightly slanting towards the entrance, to a depth of 2 inches to 8 inches, at a point 2 to 3 feet above ground. Holes on north side of tree said to be most productive. Holes 10 feet above ground do not yield any sap.

III. A wooden or galvanized iron spout (3 to 8 inches long with a hook at the end to suspend the bucket) is inserted into the hole.

IV. Buckets are emptied at least daily, as the sap ferments.

easily. The sap, poured into large tanks resting on sleds, is quickly taken to the sugar shed. Buckets must carefully be kept clean.

- V. Production per tree is 4 lbs. of sugar per season. The season lasts not over a month. The trees are not affected by tapping, either in quality or vitality. A new hole is made every year.

B. Boiling process.

Immediately after gathering, the sap is boiled down in open pans.

I. Manufacture of sugar.

Syrup is boiled to the consistency of wax, poured into forms and stirred to prevent formation of large crystals. Crystalization takes about 12 hours. Fifty quarts of sap yield 2 lbs. of sugar.

II. Manufacture of syrup.

The sap is boiled down to a lesser consistency and at once canned or bottled.

§ XL. NAVAL STORES, THEIR PRODUCTION AND MANUFACTURE.

A. Statistics.

In 1902 the United States produced 600,000 bbls. of turpentine worth \$13,200,000; 2,100,000 bbls. of rosin or colophany worth \$4,200,000.

One acre of orchard yields in three years' tapping 25 gallons of spirits of turpentine, worth \$8, and 800 pounds of rosin worth \$4, at a labor expense and manufacturing expense of \$10. Thus a profit of \$2 per acre is left to the owner.

Orchards are leased actually at \$1 to \$2 per acre for three years.

B. Methods of orcharding.

I. Southern method (also Austrian method).

- (a) Species used: Longleaf pine (used now down to 8 inches in diameter); Cuban pine; echinata (small trees preferred); after W. W. Ashe, also Taeda; in Austria, *Pinus Austriaca*.

(b) Operations of the first season:

1. Boxing: The tree is cut into, 8 inches above ground, with a narrow, thin-bladed "boxing axe." Usually two boxes to a tree, on opposite sides. Width of box is 14 inches; depth horizontally 4 inches, vertically 7 inches; height of the tip above the lip about 10 inches. Boxing takes place in January and February.
2. Cornering: Immediately after boxing the tree is "cornered." Cornering implies the removal of two triangular strips of bark and sapwood above the

box, running as high as the tip. The resulting grooves act as gutters for the rosin.

3. Hacking: Hacking or chipping begins in early March and is continued until October. The "hack" is a bent-bladed, sharp instrument which is used obliquely across the tree, producing a series of V shaped grooves in the outer layers of sapwood above the box and the corners. The points of the Vs stand in a vertical line over the tip. The surface thus scarified is called a face. The chipping removes $\frac{1}{2}$ inch of sapwood. The face of the first season is from 18 inches to 24 inches high and always remains as wide as the box.
4. Collecting: The virgin dip accumulating in the box during the first season is dipped out seven or eight times; the rosin, hardened on the face, is scraped off.

(c) Operations of subsequent seasons:

In the following seasons, the face is gradually carried upward until the working becomes unprofitable.

The output of dip, now called yellow dip, decreases from year to year, with the increase of distance between freshly hacked face and box. The scrape preponderates over the dip.

Longleaf pine may be tapped for an indefinite number of years, if intermissions of a few years permit the trees to recuperate.

II. French method (Hugues system).

- (a) Species used: *Pinus maritima*, which grows on the sand dunes fringing the western shore of France, is exclusively treated to this method.

(b) Operations:

1. Remove the rough bark around the tree to prevent pieces of bark from falling onto the face.
2. In early March make a scar close to the ground 4 inches wide and $1\frac{1}{4}$ feet high, removing $\frac{2}{5}$ inch of sapwood. The instrument used is a bent-bladed, crooked-handled axe.
3. Insert a toothed collar, made of zinc or

- iron, into an incision cut with a sharp curved knife at the bottom of the scar.
4. Hang a glazed earthen pot on a nail immediately under the lip of the collar. The pot is $5\frac{1}{2}$ inches deep, $5\frac{1}{2}$ inches wide at top and 3 inches wide at bottom.
 5. Extend the 4-inch scar week by week upward until October, taking each time a thin layer of sapwood off the old face. The final length of the face reached in a number of years is up to 30 feet.
 6. The collar and cup are moved each spring to the top of the preceding year's face. The nailhole in the pot allows rainwater to run off, since water is lighter than crude rosin.
- The pot is often covered with a wooden lid, the face itself by rough boards.

III. Dr. Charles H. Herty's gutter method.

(a) Applicability:

The method can be applied to bled or unbled trees. It has been tried by the Bureau since 1902 in the Southern pineries.

(b) Operations of the first season:

1. Use cornering axe to provide two flat faces 8 inches above the ground forming an angle of about 120° ; each is half as high as long; total width about 14 inches. Two men, right and left handed, cut 3,000 faces per day.
2. Make incisions at base of faces, one at least an inch higher than the other. Tool used is a broad axe having a 12-inch straight blade.
3. Insert galvanized sheet iron gutters into the incisions. Gutters are 2 inches wide and 6 inches to 12 inches long, bent to proper form (angle 120°) by a tilting-bench contrivance. The lower gutter projects by $1\frac{1}{2}$ inch over the mouth of the upper, the projection forming a spout.
4. Fasten an earthen cup of a capacity equaling that of a box ($5\frac{1}{2}$ in. x $3\frac{1}{2}$ in. x 7 in.) on the side of the upper gutter in such a way that its rim stands $\frac{1}{2}$ inch below the spout, and that the nailhole is as far as possible from the spout. The

FOREST UTILIZATION

nailhole should be two inches below the rim of the cup.

5. Chipping as in method I; cups emptied from time to time into collecting buckets.

(c) Operations of subsequent seasons:

Next season, the uppermost chipped channels are used for the insertion of the gutters. The cup is fastened at the upper end of the face made in the previous year.

(d) Equipment:

Equipment required for 10,000 boxes is: 10,500 cups (cost $1\frac{1}{4}c$ each = \$131.25); gutter strips made from 1,886 pounds of galvanized iron, 29 gauge (cost of material \$103.27; cutting and shaping gutters cost \$4); 10,000 six-penny nails (costing \$1.05); freight charges are about \$30; labor at the trees requires an outlay of \$80.

(e) Results:

Dr. Herty justly claims financial superiority of this method over the old Southern method, due to an increased output of turpentine.

C. Manufacture of naval stores from pine products.

I. From rosin of longleaf pine etc.

- (a) Melting crude rosin in order to separate from the liquid constituents pieces of bark, wood and a pitchy residue.
- (b) Dry distillation of the latter in a copper distilling apparatus, heated usually from an open fire beneath the apparatus; but preferably from steam of high temperature.
- (c) Cooling of gases in a worm and condenser where there are obtained:
 1. An upper layer of turpentine which is redistilled.
 2. A middle layer of rosin (colophany) of a light yellow color, which is sifted repeatedly into different qualities.
 3. Water forming the lowest layer.

II. From roots, branches and stumps of pine, the stumps to be dug out a few years after the trees are cut.

- (a) Cut the wood into kindling.
- (b) Fill it (from above) into a gasproof brick still-room, 15 feet high and 6 feet through, holding from 5 to 6 cords of kindling. The top and bottom of the still are funnel shaped and provided with pipes. The still is surrounded by the fire room.

- (c) After closing the upper funnel, apply heat very gradually. Within 24 hours turpentine begins to escape through the top pipe which leads through a worm into a condenser. When the gases appear dense and thick, the top pipe is closed and the gases (now largely containing pyroligneous acid) are forced through the bottom pipe to be condensed in another condenser. Light (at a later stage dark) tar is let out through this same pipe. The fires are checked when the tar begins to flow freely.
- (d) The process takes, for heating, 3 days; for cooling, 8 days. Charcoal is left in the still room. Proper regulation of temperature is most essential.
- (e) One cord of pine kindling yields about 25 gallons of tar, 1 to 1½ gallons of machine oil, ½ to 1 gallon of turpentine, some pyroligneous acid and ½ cord of charcoal.

III. Uses of naval stores:

- (a) Spirits of turpentine are used for colors, paints, varnishes, asphalt laying, solvent for rubber.
- (b) Colophany is used for glue in paper manufacture, varnishes, soap making, soldering, manufacture of sealing wax.
- (c) Wood tar made of conifers is lighter than water (owing to spirits of turpentine therein contained); made of broadleaved is heavier than water. It contains tolnol, xylo, cumol, naphthalin, paraffin, phenol, kreosol, pyrogalol and many other carbohydrates.

Caustic soda causes the solution of the aromatic alcohols contained in wood tar. From this solution true creosote is derived.

Dry distillation of wood tar yields:

- 1. Light wood oil;
- 2. Heavy wood oil;
- 3. Shoemaker's pitch, a residue.

D. Conifers other than pines are used only to a limited degree in the manufacture of naval stores.

- (a) The larch yields the so-called venetian turpentine, which is obtained by boring (with 1½ inch auger) a deep hole into the heart of the tree. The hole is closed by a plug. After a year the turpentine, entirely filling the hole, is extracted.
- (b) Spruce was tapped for turpentine on a large scale in the old country before the orchards of the South were developed. Only scrape is obtained

from long and narrow faces. The scar invites red rot, badly checking the value of the timber. The output in ten years is, per acre, 73 lbs. of crude spruce rosin.

- (c) Fir has rosin ducts only in the bark. Blisters or bubbles of the bark filled with rosin yield the so-called "Canada balsam" and "Strassburg turpentine," collected in tin cans. The blisters are opened with the rim of the can.

§ XLI. VANILLIN.

Vanillin, a substitute for vanilla, which has caused the price of bean vanilla to decline rapidly and permanently, is obtained from spruce (fresh cut) by removing the bark and collecting the sap either with sponges or broad-bladed knives. The sap is then boiled, strained and condensed in the vacuum pan to one-fifth of its former volume.

In the cooling room, crystals of coniferine are formed from the syrup. Coniferine, when treated with potassium bichromate and sulphuric acid, is oxydized into vanillin. The syrup obtained as a by-product is distilled and used in the manufacture of alcoholic beverages.

Eighty gallons of sap yield one gallon of coniferine.

§ XLII. BEECHNUT OIL.

Mast years of beech occur, according to climate, every 3 to 8 years. The nuts are gradually dried, slightly roasted, peeled and cleaned of shells; then either ground, applying moderate heat, or pounded in mills by stampers. The oil oozing out is strained and placed in a cool room (in earthenware vessels), where the clean oil forms a top layer to be poured off gradually.

The residue is pressed into cakes and used as feed for stock.

Two hundred pounds of dry beechnuts yield 5 quarts of oil.

§ XLIII. PINE LEAF HAIR.

Pine leaf hair, or curled pine straw, is used as a substitute for wool and cotton in upholstering, carpets etc. The stuff is mothproof.

Three hundred to 400 pounds of needles yield 100 pounds of wool.

The price is \$3 to \$12 a cwt., according to the quality.

A by-product is known as pine needle extract, used by the perfumer.

The process of manufacture consists of:

Drying the freshly cut needles; steaming; fermentation; crushing and disfibring in pounding mills; repeated washing of the feltlike mass; loosening on sets of oscillating sieves; drying and bleaching. The product has a greenish or yellowish color. It is called "pine hair" in North Carolina, where the industry, now extinct, promised a successful career twenty years ago.

§ XLIV. IMPREGNATION OF WOOD.

Impregnation tends to increase the durability of wood by injecting an antiseptic liquid and may mean a desirable or undesirable change of color, and in some cases fireproofing. Little is known about the latter.

Four principles may be applied:

A. Immersion:

- I. The oldest method used was immersion in a strong solution of salt. European railroads place ties for eight days in large tanks filled with a light solution of corrosive sublimate. No other work required. The method is called "Kyanizing." Drawbacks are that the liquid is washed out on wet ground; that spikes do not hold well in the timber. Expense per cubic foot, $6\frac{1}{2}c$.
- II. "Metalized" wood is obtained as follows:

Immerse the wood in a solution of sulphate of iron; then smear the wood with chloride of calcium. In the outer layers of the wood gypsum (sulphate of lime) is formed together with chloride of iron. Such wood is impermeable to water and has a metallic shine.

B. Boiling:

- I. Boiling in salt water or in a solution of borax seems to be a method rarely practiced. Boiling, however, with exhaust steam, when a black juice is forced out of the log, is frequently seen abroad.

In the latter case the log is practically steam dried.

- II. "Franks" mixture consists of 95 % liquid manure and 5 % of lime. It is pumped into large vats, within which the wood is boiled for 3 to 8 days. The liquid enters to a depth of about 3 inches and darkens the wood to a mahogany tint.

- III. A method called "siderizing" injects by a boiling process a solution of copperas. The wood is then dried, and liquid glass (a hot solution of silicate of aluminum) smeared on the surface. By a chemical reaction silicates of iron are formed in the outer layers, which are insoluble in water and resist decomposition. The wood at the same time obtains a beautiful gloss.

C. Use of hydrostatic pressure:

A solution of sulphate of copper (blue vitriol) is used after Boucherie. It is kept in a tank 30 ft. to 40 ft. above ground. The timber must be fresh cut with the bark on and is spread on a rough log-deck. At the big end of each stick a ring made of rope is held in place by a board or heading nailed to the log. A hose connected with the tank injects the liquid into the small cleft formed between log and heading. After a few hours, drops of vitriol appear at the small end, showing that the process is complete. The pressure being slight, only the outer sappy layers are impregnated. This method is largely used abroad, often in

the woods themselves, for telegraph poles of pine, spruce, fir etc.
Expense per cubic foot, 4c.

D. Use of steam pressure:

The wood is dried thoroughly, then placed on small steel cars running into long cylinders or boilers, closed by a strong head. A vacuum pump removes the sap water and causes a vacuum to form in the wood itself. Then an antiseptic liquid is pressed into the boilers; temperature of liquid is 150° to 200°.

The liquids used are:

- (a) Chloride of zinc.
- (b) Creosote or rather cheap coal tar oils.
- (c) Gases of tar oils (so called thermo-carbolization).

The creosoting method is used for ties and paving blocks. Creosoted timber holds nails well; creosote is not washed out by rain; on the other hand, the darkened color of the wood is sometimes objectionable. It is claimed that creosoting in the United States has failed, probably because an extravagant amount of the liquid has been pressed into the timber. In Germany the expense per tie is only 63c as against \$1.25 in the United States.

E. Results:

Heart wood is not as permeable and hence not as impregnable as sap wood. Maple, birch, beech, spruce, sappy pine etc. are more benefited by impregnation than white oak, longleaf pine etc. Generally the duration of life of impregnated ties is increased at the following ratio: Beech, 400%; yellow pine and oak, 200%; spruce, 50%.

Obviously, every additional pound of preservative pressed into the fibre has a lesser effect on the lastingness of the wood than the preceding pound. For every woody species the limit must be found at which additional impregnation proves unremunerative.

G. S. Hamlin Jr.

LECTURES ON FOREST POLICY

By C. A. SCHENCK, PH.D.

Director of the Biltmore Forest School, and Forester to the

Biltmore Estate, N. C.

Lectures

BILTMORE LECTURES

Second Part:

“FORESTRY CONDITIONS IN THE
UNITED STATES.”

G. S. HAMLIN Jr.

1904

Biltmore Forest School,
Directors' Office.

Biltmore, N. C., January 1, 1904.

Dear Sir—My lectures on Forest Policy appear in print, primarily, for the benefit of the students attending the Biltmore Forest School. Forestal text-books fit for American use not being available, I have been forced, for a number of years, to lengthily dictate the essence of my lectures.

The following pages merely record the dictation. They are not intended for public sale.

I most sincerely request, dear sir, that you may lend me your aid in checking and correcting the data concerning your State, namely,, given on pagef. f., so that this little volume, duly filed and controlled by collaborating friends, may thereafter publicly appear, in a better garment and improved contents, for the benefit of the American student of forestry.

Thanking you for any kindness that you may deem fit to show me in connection with the improvement of my lectures on "Forest Policy," I am, dear sir,

Most truly yours,

LECTURES ON FOREST POLICY

By C. A. SCHENCK, PH.D.

Director of the Biltmore Forest School, and Forester to the
Biltmore Estate, N. C.

FORESTRY CONDITIONS OF ALABAMA:

1. Area: 38,300 square miles, or 74% of total area, are wooded.

2. Physiography: The Cumberland Mountains force the Tennessee River into Alabama, where it forms a huge curve. The Appalachian Mountains send a double chain of mountains, in a northeast to southwest direction, from Chattanooga to Birmingham. Tombigby River and Alabama River join just before emptying into Mobile Bay. Chattahoochee River on Georgia line. Southern section of State undulating, swamps alternating with slightly elevated dunes. Mountains near Birmingham bear coal and iron.

3. Distribution: The southern third of the State is occupied by long leaf and Cuban pine; the former on dry, the latter on wet land. Four large isolated tracts of long leaf pine (unaccompanied by Cuban pine) in the northern half of State. Taeda occurs all over the State in varying proportion, accompanying here long leaf, there echinata or hardwoods. Echinata is found, generally, outside the region of Cuban pine and does not proceed to the coast. Best stumpage of echinata on upland, with oak undergrowth. Pine stumpage estimated, in 1880, to be 21 billion feet b. m. Enormous cypress swamps along the rivers. Outside the long leaf pine sections, the hardwoods, notably black, Spanish and post oak, prevail in number, but not in importance. In the curve of the Tennessee River, the southernmost sentinels of the fine hardwood and red cedar forests once typical for Tennes-

FOREST POLICY.

see. In the mountain section, the flora of the Cumberland plateau (see under Tennessee), with some little white pine and hemlock.

4. Forest ownership: 525 firms own 1,224,000 acres of forest. The federal government, State railroads and homesteaders are the chief owners.

5. Use of timber: Destructive lumbering only of recent date. Huge deserts are nowhere left by the lumber jack, as is the case in the lake States. No pine resists fire better than long leaf. Cuban pine is protected by its position. The industry threatening ruin to the forests is the turpentine industry, which leaves only taeda intact. The output of the saw mills was in

1880	\$ 2,700,000
1890	8,500,000
1900	12,900,000

The cut in 1900 consisted of:—

Yellow pine	1,012,000,000 feet b. m.
Other conifers	32,000,000 feet b. m.
White oak	61,000,000 feet b. m.
Other hardwoods	44,000,000 feet b. m.

Total 1,149,000,000 feet b. m.

Mill investments average \$5,251 with 1,087 mills. Logs on stump are worth \$1.20, at mill \$4.30 per 1,000 feet b. m. Cooperage stock production, in 1900, is valued at \$200,000; miscellaneous sawn products at \$400,000; shingles, notably cypress shingles, at \$460,000. In 1885, the naval store industry yielded \$851,000.

Leather industry surprisingly large, producing, in 18 tanneries, \$1,098,000 worth of leather and using 18,651 cords of oak bark, worth \$62,628.

Paper and pulp industry: None.

6. Forestry movement: None.

7. Laws: Fire laws of 1852, against wilful or negligent firing. Firing turpentine orchards is under a fine of \$100 to \$1,000, or punishable with hard labor for not more than 12 months.

8. Reservations: None.

9. Irrigation: 89 acres of land were irrigated, in 1899, for truck farming.

No rice fields enjoyed irrigation.

FOREST POLICY.

FORESTRY CONDITIONS OF ALASKA:

1. Area: The total area of Alaska is 590,000 square miles. The area of woodlands can scarcely exceed 60,000 square miles.

2. Physiography: The territory of Alaska forms a square, traversed by the east and west course of the Yukon River and framed by the ocean on three sides, with two appendages, namely:

(a) In the S. W., the Aliaskan Peninsula, with Kadiak and Apognak Islands.

(b) In the S. E., the mountainous coastal belt, 60 miles wide by 500 miles long, with over 1,000 islands (notably Sitka Island) fronting the coast.

Mt. McKinley, in the Alaskan Range, lying somewhat south of the center of the territory, 20,464 feet high, is drained by the Kuskokwim River. The Kuro Shiwo causes abundant (60 inches to 160 inches) rainfall and high atmospheric along the southern coast. Eternal snow, however, lies above the 2,000-foot contour line, even in the coast range and St. Elias Mountains. The mountains are beset with the hugest glaciers on earth, outside the polar region. Short growing season. Geologically, Alaska is one of the latest portions of the continent.

3. Distribution: The south coast, east of Kadiak Island, shows splendid coniferous forests, stocked with Sitka spruce, balsam fir (*grandis?*) hemlock, red cedar (*Thuja plicata*) and yellow cedar (*Chamaecyparis Nutkaensis*). Amongst the hardwoods, cottonwood alone reaches commercial size. Sitka spruce penetrates, in stunted form, to the Arctic Circle.

The hills of the lower Kuskokwim River have little wood; heavy spruce forests, however, exist on the mountain slopes of its upper course, whilst the valleys exhibit splendid summer prairies.

The northwestern hills are bare. Woodlands are found along the west coast up to Norton Sound.

Arctic tundra—a treeless plain full of ponds and swamps—extends from the Yukon northward to the Arctic Ocean. Dwarfed spruces and willows dot it far to the north.

4. Forest ownership: Practically all woodland belongs to the federal government, though the Russian Greek Church may own comparatively small tracts. Lack of surveys prevents land entries.

5. Use of timber: Most lumber is imported from the

FOREST POLICY.

Pacific States. Coal (sulphurous) is found in many places, restricting the consumption of wood. The population scarcely exceeds, in 1902, 90,000, of which two-fifths are native.

Yellow cedar is used by the natives for huge dugout canoes. The bark of the balsam fir is employed for tanning. The common local timber tree is the knotty Sitka spruce, used for house building, mine props, sledges and firewood.

The large output of the fish canning industry (over 51,000,000 lbs. salmon in 1899) requires packing crates and slack barrels.

The 12th census reports a cut of 6,500,000 feet b. m. lumber, mostly spruce, valued at \$90,000. Much unlawful cutting on vacant timberland.

6. Forestry movement: None.

7. Laws: None.

8. Reservations: The Apognac Forest and Fish Culture Reservation lies north of Kadiak Island and comprises 403,640 acres.

The Alexandria Archipelago Forest Reserve covers 4,506,240 acres.

9. Irrigation: None.

FORESTRY CONDITIONS OF ARIZONA:

1. Area: 16,000,000 acres, or 22% of entire area of Territory, are reported under forest.

2. Physiography: Arizona consists of a high plateau, 5,000 feet elevation, sloping gently towards Gulf of California, intersected in northwest by the Grand Cañon, and diagonally traversed from the northwest to the southeast by a chain of mountain ranges, many tops of which rise to 10,000 feet elevation. This chain drains towards west into the Rio Gila and towards east into the Little Colorado, both of which are tributaries of the Colorado River. The rainfall, especially during the summer months, often evaporates before reaching the ground. Streams are frequently smaller at the mouth than at the head, due to dryness of the atmosphere.

3. Distribution: Below 3,500 feet elevation occur deserts, with cactus, yucca and agave. The river cañons are deeply cut into the plateaus and are fringed with broad-leaved species, i. e.,

FOREST POLICY.

cottonwoods, willows, alders, ashes, hackberries and cherries. The foothills around the deserts show scattered scrub pines; scrub oaks occur notably on the hillsides; Mesas exhibit stunted oaks and pines. Above 5,500 feet elevation, open, park-like forests occur, notably of yellow pine (*ponderosa*), which, in the San Francisco Mountains near Flagstaff, are said to form the largest pure pine forest in the world. Trees are short, branchy and sappy. On the northern slopes, at about 6,500 feet elevation, occurs Douglas fir. The Rocky Mountain white pine (*P. flexilis*) and foxtail pine (*P. balfouriana*) are found at similar elevations in the San Francisco Mountains. Above them, large, often pure forests of Arizona cypress (*Cupressus Arizona*). At the timber line, after Fernow, Engelmann's spruce and Arizona cork fir (*Abies Arizona*) occur.

The plateau north of the Colorado Cañon is almost treeless.

A large number of coniferous species peculiar to Arizona are found in the southern part of the diagonal chain. Here the forest forms narrow stretches of fringe at altitudes exceeding 7,000 feet elevation. The best known mountain ranges are the Bradshaw Mountains, with 25 square miles of forest, the lower slopes dotted with nut pines (*monophylla* and *edulis*).

The Mazatzal Mountains contain about 70 square miles of forest (yellow pine, white pine, Douglas fir, white fir).

The White Mountains contain about 100 square miles of forest. Here, near the natural bridge, a splendid, almost pure forest of Arizona cypress occurs.

The Chirihahua Mountains contain 160 square miles of forest, a strip four miles wide and forty miles long. The Arizona pine (*Pinus Arizona*) and the Chirihahua pine (*Pinus Chirihahua*), further, the Mexican pine (*Pinus cembroides*) and a white pine (*Pinus strobiformis*) are additions to the tree flora in these southeastern mountains, which otherwise consists of yellow pine (*ponderosa*), white pine (*flexilis*), Douglas fir and California white fir (*Abies concolor*). Between the deserts and forests there is invariably found a belt showing pinons and scrub oaks. Timber species are generally wanting on mountains less than 7,000 feet high.

4. Forest ownership: The United States reserves aggregate, in 1902, 6,740,000 acres. Large Indian reservations, notably the Moqui and Navajo, in the northeast and in the White Moun-

FOREST POLICY.

tains. Lumbermen own 409,000,000 feet b. m. yellow pine stumpage on 202,000 acres.

5. Use: Most prominent use of the forest is that for cattle and sheep pasture. Forest fires do little damage, forests being open. Sheep grazing in the reserves from April until December.

Output of lumber industry in 1900 was 36,250,000 feet b. m., worth \$547,000. Log stumpage, \$1.03. Saw logs at mill, \$7.50. Only 14 saw mills, with average capital of \$26,000. No pulp or leather industry. Mining industry, near Prescott, obtains supplies from the Bradshaw Mountains. Saw mills turn out largely yellow pine ties. Percentage of 1's and 2's in the lumber not over 7%.

6. The forestry movement in Arizona is nil.

7. Laws: Forest fire laws punish negligent or wilful firing as a misdemeanor.

8. Reservations: The Grand Cañon forest reserve is not a forest reserve proper. It contains forest only south of the Colorado. It occupies 1,851,520 acres.

The Prescott forest reserve covers 423,680 acres; the Black Mesa forest reserve 4,658,880 acres. The latter extends to the New Mexico line, forming a narrow belt of forest at high elevations.

The San Francisco Mountain forest reserve, with Flagstaff in the center, lies between the Grand Cañon and Black Mesa reserves and contains 1,975,310 acres. This reserve will be important for lumbermen in the near future.

In April, 1902, the Santa Rita forest reserve of 387,300 acres was created. In July, 1902, there were created three new reserves, namely:—

Mt. Graham forest reserve (118,600 acres);

Santa Catalina forest reserve (155,520 acres);

Chirihahua forest reserve (169,600 acres).

All reserves lie on the diagonal mountain range referred to, and are well selected.

9. Irrigation: In 1900, 190,000 acres of farm land were irrigated. Area is small, owing to irregularity of precipitations and lack of steady supply. The necessity and, at the same time, the opportunity for farms irrigated from storage reservoirs is great.

FOREST POLICY.

Some tribes of Aborigines have irrigated their farms long before the advent of the whites.

Irrigation in the Salt River Valley, near Phoenix, shows results similar to those obtained in southern California. Fruits put on the market slightly earlier and freight rates to the east slightly better, give Arizona a certain advantage over California.

The value of the irrigation works constructed is \$4,400,000; the value of the irrigated products \$2,200,000 (anno 1899).

FORESTRY CONDITIONS OF ARKANSAS:

1. Area of woodlands 45,000 square miles, equal to 84% of the State. Probably maximum percentage amongst the States.

2. Physiography: Undulating plains. Ozark Mountains traverse northwest corner of the State in a belt 80 miles wide and from 1,000 to 2,000 feet high. Arkansas River traverses State from west to east, joined by the White River close to its junction with the Mississippi. Red River in the southwestern part of the State.

3. Distribution: Forest everywhere. A small tract of prairie in east central part of State. South of the Arkansas River and west of the Mississippi bottom lands gigantic virgin forests of pine occur (*echinata* and *taeda* mixed, the former prevailing on pine ridges, the latter prevailing on pine flats). Both pine species sold under the name of "short leaf pine." Stumpage of both species very heavy, say 6,000 feet b. m. per acre. Sargent estimated, in 1880, the stumpage of short leaf pine at 41,315,000.-000 feet b. m. per acre. Bald cypress found in vast swamps in the bottom lands of the rivers. Stumpage about 5,000 feet to the acre.

The hardwoods prevail north of the Arkansas River and all along the Mississippi; further, in the bottoms of the Red River. Here the trees are said to be unsurpassed in size. Black walnut is said to be particularly abundant in the valley of the Red River. The leading hardwoods are white and red oaks, cottonwoods, sweet gum, black gum, yellow poplar, beech, ash, hickories, cow and texan oak. *Pinus echinata* shows some important bodies north of the Arkansas River as well, whilst *taeda* is here lacking.

The composition of the forest at Pine Bluff, after F. E.

FOREST POLICY.

Olmsted, on an average acre, excluding trees of under 12 inches diameter, is as follows:—

On Pine Land.		In Hardwood Bottoms.	
Echinata	5.9 trees	Hickory	5.8 trees
Taeda	5.3 trees	Cow oak	4.8 trees
White oak	3.8 trees	White oak	3.5 trees
Post oak	3.3 trees	Holly	2.1 trees
Black Oak	0.7 trees	Ash	1.3 trees
Gum	2.1 trees	Basswood	0.6 trees
Spanish oak	1.2 trees	Post oak	0.2 trees
Hickory	0.8 trees	Pines	1.2 trees
Miscellaneous	0.7 trees	Miscellaneous	1.5 trees

Apparently the pines form little over half of the growing stock on pine lands. Hardwoods not marketable on pine land.

4. Forest ownership: 28% of the hardwood land is reported attached to farms. 517 lumber firms own 1,497,000 acres, of 6,700 feet b. m. average stumpage.

5. Use of timber: Logs on stump are worth \$1.09, and logs at mill \$4.74.

Logging in the pine woods by cattle and high wheel trucks, or by donkey engines. Mill investments, for 738 mills reporting, are \$9,224 on an average. The lumber industry has grown very rapidly of late—more so in Arkansas than in any other State of the Union.

In 1880 the lumber output was valued at....\$ 1,800,000

In 1890 the lumber output was valued at.... 8,900,000

and in 1900 the lumber output was valued at. 30,000,000

The cut in 1900 consisted of:—

Cypress	108,000,000 feet b. m.
Yellow pine	1,113,000,000 feet b. m.
Cottonwood	117,000,000 feet b. m.
Red gum	61,000,000 feet b. m.
White oak	226,000,000 feet b. m.
Other hardwoods	40,000,000 feet b. m.

Forests are little used for pasture, other than hog pasture. The railroad freight consists largely of lumber and timber. Three small tanneries. No pulp or paper mills.

FOREST POLICY.

6. Forestry movement: "To get rid of the lumber" is the only demand. Conservative lumbering attempted near Pine Bluff, since cut-over pine land is scarcely salable.
 7. Laws: The usual fire laws are unobserved.
 8. Reservations: None, excepting a military reserve at Hot Springs.
 9. Irrigation: None.
-

FORESTRY CONDITIONS OF CALIFORNIA:

1. Area: 28,600,000 acres of forest, equal to 22% of area of State.

2. Physiography: The Valley of California, drained by Sacramento from the north and San Joaquin from the south, and embraced by Coast Range and Sierra Range, opens towards bay of San Francisco. Towards the south the Coast Range emits irregular sentinels, notably the Santa Lucia Mountains, San Gabriel Mountains, San Bernardino Mountains, rising up to 10,000 feet elevation. Deserts along the Nevada, Arizona and Oregon line.

3. Distribution: California excels in the number of coniferous species, the variety of forest growth depending on the peculiarities of her climate. Rain winds in southern California are, strange to say, northeast winds. Rainy season begins in September, preceded by three or four months of drought. Coast Range contains no commercial forests south of Santa Cruz. Water courses deep seated, torrents in winter, mere threads in summer, unfloatable.

Immediately along the ocean shore, stunted conifers only grow. Above shore belt, the famous redwood belt of the Coast Range, consisting of *Sequoia sempervirens*. The redwood belt extends from the Oregon line southward to Santa Cruz; it is composed of large, pure redwood forests, exhibiting greatest stumpage of any tree per acre. Accompanying redwood are found, principally, Douglas fir, yellow pine, sugar pine, incense cedar, tideland spruce and three firs (*Abies grandis*, *magnifica* and *nobilis*), which run up to the crest of the range. The coniferous woods are intersected with tracts where chestnut oak and madrona (*Arbutus Menziesii*) dot the brush covered slopes. The east slope of the Coast Range, towards the Sacramento Valley, shows a

FOREST POLICY.

scattering growth of pines and oaks, often imbedded in brush thickets.

The bottom lands of Sacramento and San Joaquin Rivers have a park like growth of huge oaks, which are now rapidly removed by the farmers.

Ascending the Sierras from the west we find the lowest belt, below 2,000 feet elevation, to consist of gray (digger or nut) pine (*Pinus sabiniana*), the favorite nut tree of the Indians, occurring in very open growth, alternating with oaks and the knob cone pine (*Pinus attenuata*), which regenerates only under the influence of fire.

The typical tree of the next higher belt, from 2,000 to 4,000 feet elevation, is the nutmeg tree (*Tumion Californicum*), which is found along the borders of streams. The hillsides show a comparatively poor growth of pine and fir, the Douglas fir being frequently of the "yellow" variety.

Above this zone, from 4,000 to 10,000 feet elevation, extends the famous timber belt of the Sierras. Rainfall is 50 to 60 inches. Typical for the California Sierras is the lack of any woody undergrowth on the ground. The soil is covered with a growth of flowering weeds. Imbedded in this belt are, island-like, ten groves of the big trees (*Sequoia gigantea*). This species, unlike its sister, the redwood, never grows in pure forests. The companions are Douglas fir, sugar pine, yellow pine, incense cedar and firs (*Abies magnifica* and *concolor*).

At elevations ranging between 3,000 and 8,500 feet, incense cedar frequently replaces the big tree. On old burns, lodge pole pine is found in pure stands. Amongst the nut pines, the one-leaf pine is highly thought of by the Indians. In addition, there occur the bull pine (*Pinus Jeffreyi*) and the big cone pine (*Pinus Coulteri*).

The highest belt, reaching up to the timber line at 12,000 feet, is the home of the firs proper. Here the red fir (*Abies magnifica*) and the white fir (*Abies concolor*) prevail. Timber line itself shows the Alpine hemlock, young trees of which are buried in snow all winter. *Pinus monticola*, the white pine, is said to excel in power of resistance to storms. The limber white pine (*Pinus flexilis*) and the white bark pine (*Pinus albicaulis*) are also found. Two typical species for this zone are the foxtail pine (*Pinus Balfouriana*) and the bristle cone pine (*Pinus aristata*).

FOREST POLICY.

In addition, twisted pine (*Pinus contorta*) occurs on high mountain pastures.

Crossing to the east slope of the Sierras, the growth soon gets poorer, for lack of rain. Only pine species are found here, especially lodgepole pine, yellow pine and bull pine. Close to the Nevada line desert growth only occurs, such as mesquit and yucca.

In southern and southwestern California there are scarcely any commercial forests. Along the Arizona and Nevada line the Mohave desert and Colorado desert cover millions of acres. The plains, close to the sea and rivers, have dense groves of willows and sycamores. Majestic oaks occur scatteringly in the river valleys. In addition there are huge cottonwoods. On the edges of the deserts, in slight depressions, two *Prosopis* species are found, i. e., mesquit (*Prosopis juliflora*) and screw bean (*Prosopis odorata*). Piñons or nut pines are also found. The California palm (*Washingtonia filifera*) is found in canyons opening toward the deserts. In the deserts themselves are scattering yuccas. Ascending the mountain ranges the trail winds through endless chaparral thickets, dotted with live oaks and scrub pines (piñon). Forests occur at high altitudes on the Sierra Madre, San Bernardino, San Gabriel, Cuyamaca and San Jacinto Mountains. Here prevail yellow pine, Coulter's big cone pine, big cone fir (*Pseudotsuga macrocarpa*), white fir (concolor), in company with sugar pine, incense cedar, lodgepole pine and limber white pine. In the semi-arid zone reaching up to the 5,000-foot contour line are at home juniper, single leaf pine and gray pine, whilst the moister slopes and canyons, or the water courses, exhibit live oak, sycamore, walnut, alder, willow and cottonwood. The bristle cone fir (*Abies venusta*), a large fir of the canyons, seems unique in the Santa Lucia region.

4. Ownership: Farmers are said to own 1,673,000 acres of forest land. The United States forest reserves cover 8,800,000 acres; the United States parks 1,100,000 acres; both together about one-third of all the forests and 8.6% of the area of the State. According to the last census, 156 lumber firms control 1,177,000 acres of forest land, mostly situated in the Coast Range, and containing one-sixth of the timber of the State.

5. Use: There is scarcely any hardwood fit for cooperage, carriage works and furniture. Firewood is costly in southern California. Large lumber operations are conducted on the Coast

FOREST POLICY.

Range only, supplying South America and the far east. Here a yield of 1,000,000 feet b. m. per acre is amongst the possibilities. Logging is done by railroad and donkey engines. Commercial species, aside from redwood, are sugar pine, Douglas fir, incense cedar and red fir (*Abies magnifica*). Redwood is said to furnish the best tank material and railroad ties, if tie plates are used. From the Sierras, lumber is exported into Nevada and Arizona for the use of the mines.

The Alpine meadows of the Sierras offer good pasture, but are said to suffer severely from sheep pasture. Regeneration in Sierra belt is said to be poor, no undergrowth being at hand. On old clearings, near mines, sugar pines and yellow pines are said to show a good second growth.

The tannin industry of California occupies the tenth rank among the States, using during the last census year 36,123 cords of chestnut oak bark, valued at \$16 per cord. Production is largely sole leather.

The paper and pulp industry is nill, five plants having died during the last decade.

The products of the lumber industry were worth:—

In 1850	0.9 million dollars.
In 1870	5.2 million dollars.
In 1890	8.8 million dollars.
In 1900	13.8 million dollars.

The total cut in the census year was only 864 million feet b. m., drawn from a growing stock of 36 billion feet b. m., owned by private individuals. Log stumpage is worth \$1.16. Logs at mill are worth \$4.63. California leads in the use of traction engines, which are employed on undulating ground. The mill establishments are large, next in size to those of Minnesota and Wisconsin, the investments averaging \$29,300. Eucalyptus plantations are made in the timberless regions of the south to obtain posts and firewood. Species recommended are: *Eucalyptus globulus*, *rostrata*, *viminialis*, *corynocabyx*, *leucoxylon*.

6. Forestry movement: California has been sensible of the dangers threatening from forest destruction and forest fires, since agriculture depends largely on the possibility of irrigation, safeguarded by forests. A State Board of Forestry was established in 1885, drawing a good appropriation, writing some valuable re-

FOREST POLICY.

ports and establishing some experiment stations. In 1891, political decrepitude caused the board to lose its foothold. A prominent member of the board was Abbot Kinney. To him is due the introduction of Eucalyptus.

The tree botany of the State has been advanced by J. G. Lemmon. The California legislature has memorialized the United States government to set aside all forests for reserves. When, in 1897, all western reservations were opened to pasture by Binger Hermann, the California senators opposed the move and secured exemption for their State. At the university of South-California a forestry school was established in 1899. The Sierra Club (John Muir, President) and the California Water and Forest Association (since 1898) are taking up the work of the defunct State board. Sheep owners are the only people in California opposing the forest reserve policy.

7. Laws: The usual fire laws. The State Board of Forestry demanded of Congress, but in vain:—

(a) The temporary repeal of the timber and stone act.

(b) A law providing for sale of stumpage only from forest land, the government retaining the fee simple rights. State law of 1903 appropriates \$15,000 to assist the Bureau of Forestry in a canvass of the forest resources.

8. Reservations: The total area reserved, in 1902, is 8.8 million acres. The reserves are well selected, covering the tops of the Sierra Nevada and the high mountain ranges of the south. No reserves on the Coast Range.

The Sierra forest reserve, aggregating 4,096,000 acres, lies south of the Yosemite National Park, is about 200 miles long by 50 wide and comprises the Sequoia National Park, General Grant National Park and Mount Whitney Military Reservation. North of the Yosemite National Park lies the Stanislaus forest reserve, covering 691,200 acres. The Lake Tahoe forest reserve, of 136,335 acres, is the only reserve drained by the Sacramento. The highest summits of the Sierras are in the reserves. 85% of the reserves are timbered and 15% are covered with snow or glaciers. 70% of the 85% have, however, suffered from fire.

The southern reserves form links in a long chain running, approximately, east and west, and consist of the

Pine Mountain and Zaca Lake forest reserve (1,644,594 acres).

FOREST POLICY.

- San Gabriel Timberland reserve (155,520 acres).
- Santa Ynez forest reserve (145,000 acres).
- San Bernardino forest reserve (737,280 acres).
- Trabuco Cañon forest reserve (109,920 acres).
- San Jacinto forest reserve (668,160 acres).

The reserves were established solely to protect the water supply. The brush thickets occupy from 50% to 90% of the reserved tracts.

The Yosemite National Park comprises the Yosemite Valley, which was ceded to California by Congress in 1854, and is now in charge of three commissioners said to be lacking in good taste.

9. Irrigation: Value of products from irrigated land exceeds those in any other State. The average size of the irrigated farms is 75 acres. Cost per acre of irrigation system is \$16.80 and average yearly cost is \$1.70. In 1903 the State appropriates \$45,000 to assist federal departments in mapping and surveying reservoirs and in studying methods of water distribution.

The "district law" of 1887 causes great ease in bonding irrigation districts, and hence throws heavy burdens on the irrigationists. Many of the bonds issued are now worthless.

The irrigation systems were constructed at an expense of \$19,200,000.

Irrigation in the north is rather the exception. In the south it forms the rule. Along the Sierra streams, water is lavishly used. In the south, the greatest economy prevails.

Shipments of oranges raised in the south, in 1899, were \$7,000,000 in value.

In 1899, 1,600,000 acres were irrigated. Value of irrigated crops was \$33,000,000.

Irrigation prevails, where the precipitations and the flowage of streams are least; on the other hand, where there is no danger from frost.

FORESTRY CONDITIONS OF COLORADO:

1. Area: 33,500 square miles of woodland, or 32% of the area of the State.
2. Physiography: The 105th meridian separates the eastern

FOREST POLICY.

third from the western two-thirds of the State. The eastern third is a treeless plateau, falling from 6,000 to 4,000 feet, towards the Kansas State line. Little rainfall. The central third of the State is the crest of the continent and is covered with irregular ridges rising up to 14,000 feet elevation. From here the South Platte and Arkansas Rivers run east; the Rio Grande south; the tributaries of the Colorado River (the Green, White, Grand and San Juan Rivers) west; the North Platte river north.

The western third of the State is a high plateau, intersected by high, detached mountain ranges and peaks. Large parks are characteristic of this mountain section. In winter the snow at Durango, in the southwest, is said to be six feet deep. The rainfall west of the crest is much greater than east of the crest.

Forest fires have played more havoc in Colorado than in any other State.

3. Distribution: The central crest is sparingly timbered with yellow pine, lodgepole pine, limber white pine and foxtail pine. Engelmann's spruce, usually associated with balsam (*lasiocarpa*), yields the best logs and must be considered the main timber tree of Colorado. It is found at elevations ranging from 8,000 to 12,000 feet. On moist sites, forests are formed by Colorado blue spruce and the gray modest variety of Douglas fir, followed by quaking aspen after devastation. All over the foothills pinon dots the ground (*edulis*), often replaced by the one-seeded juniper. Along the rivers, a fringe of hardwoods (especially cottonwoods, box elder and ash) is found. The best timber is said to stand in the southwest. It seems that the western third of the State has some timber everywhere, although it is not heavily timbered anywhere. Lodgepole pine is the prevailing species in the parks. The Rocky Mountain oak (*Quercus undulata*) forms brushy thickets on all exposures. Rivers fringed with cottonwood, box elder, elm and ash.

4. Forest ownership: Most forest land belongs to the federal government. Lumbermen own 92,000 acres only. 44,000 acres of forest are said to be attached to farms. One-seventh of the wooded area is reserved.

5. Use: The forest is subservient to irrigation and mines. Majority of cut is yellow pine. Total cut in census year was 135,000,000 feet b. m., worth \$1,627,000. Stumpage of yellow pine on best holdings 8,000 feet.

FOREST POLICY.

Logs on the stump are worth \$1.12 per thousand; at mill, \$4.99. There are 155 saw mills of \$3,883 average investment, 59 of which are said to control 671,000 feet b. m. stumpage. Mineral products of the State are worth \$30,000,000 annually. Stock pasture plays a very important part.

6. Forestry movement: Colorado's constitution is the only constitution emphasizing forestry. State forestry association since 1884. Various attempts to transfer custody of the United States forests, for protective purposes, to the State. Irrigationists strongly in favor of reserve policy.

7. Laws: In 1885 a State forest commissioner and "forest conservators" (justices of the peace and county commissioners) for the protection of forests. Fire law notices to be kept posted by the conservators. Law of 1897 creates a Department of Forestry, Fish and Game; its forest commissioner is charged with forest extension, with water preservation and with the care and records of all woodlands at any time belonging to the State.

The State agricultural college has four experiment stations and offers a course in arboriculture. A law of 1901 practically prohibits lumbering on public domain above irrigation districts. Campers must secure permits. Non-resident hunters must secure "game and forest wardens" for guides. Railroads are required to keep right of way cleared, to supply engines with spark arrestors, to be responsible for damage by fire started by locomotive sparks.

The Denver and Rio Grande has the privilege of obtaining repair material from United States forests.

8. Reservations: The reserves, in 1902, cover 4,849 square miles, which is 5% of area of State and 15% of wooded area. They are well selected and should be increased in the southwest.

The South Platte forest reserve (683,520 acres), Plum Creek timberland reserve (179,200 acres) and Pike's Peak timberland reserve (184,320 acres), north of Colorado Springs, are extremely valuable for mines and irrigation purposes. They contain little merchantable timber, due to cutting and burning.

The Battlement Mesa forest reserve contains 858,240 acres; the White River forest reserve, 1,129,920 acres. These two reserves drain towards the Colorado River. The standing live timber of these two reserves, after Sudworth, consists of the following stumpage, in million feet b. m.:—

FOREST POLICY.

In White River reserve: Spruce, 930; balsam, 310; aspen, 100; lodgepole pine, 50; Douglas fir, 25.

In Battlement Mesa reserve: Spruce, 112; balsam, 37; aspen, 65.

9. Irrigation: The products of irrigation are forage crops and coarse grain staples; further, cantaloupes, peaches, potatoes.

Farming depends entirely on irrigation. On the South Platte and Arkansas Rivers irrigated farming is highly developed, handicapped in its progress by private ownership of water storage at the headwaters.

The irrigated area of Colorado, 1,611,000 acres, exceeds that of all other States. The value of the irrigated products was, in 1899, \$15,100,000. The irrigation system constructed cost \$11,700,000.

FORESTRY CONDITIONS OF CONNECTICUT:

1. Area under forest, 1,900 square miles, or 39% of the State, are classed as woodland.

2. Physiography: The Connecticut River traverses the State centrally, running north to south. Low mountains and hills stretching in the same direction show rugged and stony slopes.

3. Distribution: The primeval woods are extinct. A third or fourth growth of coppiced chestnut, oak, birch, ash, elm, hickory, basswood and cottonwood forms the woodlands, mixed with white pine said to readily reproduce on old fields and wood lots. The usual coppice rotation is 30 years.

4. Forest ownership: 50 mill firms own 9,195 acres of forest. Average stumpage is said to be 9,200 feet b. m. (?) 90% of the woodlands are attached to farms.

5. Use of timber: Stumpage costs \$2.90; logs at mill, \$7.88 per 1,000 feet b. m. 187 saw mills, mostly along the rivers, report an average investment of \$3,567. The output of the lumber industry is rising in value.

In 1860	\$ 572,000
In 1880	1,076,000
In 1900	1,118,000

FOREST POLICY.

The cut in 1900 aggregated 107,600,000 feet b. m., in which white pine participates with 23,800,000 feet b. m.; chestnut with 64,500,000 feet b. m. The coppice woods produce large quantities of fuel.

Leather industry: The output of 7 tanneries is valued at \$891,000. It consumes 495 cords of hemlock bark, worth \$3,810; 133 cords of oak bark, worth \$1,041; 3,516 barrels of bark extract, worth \$37,909; 205 bales of gambier; 494 barrels of quebracho; 111 tons of sumac, and chemicals worth \$1,791.

In 1900, 50,000 hides and 300,000 sheep skins were tanned.

The output of the paper industry is valued at \$3,565,000. No cord wood is used; only rags, waste paper, manilla, imported pulp and imported fiber.

6. Forestry movement: Some interest is manifested in planting waste sand land. The Connecticut forest association is presided over by the State forester.

7. Laws: Fire laws of 1886. Tax exemption on plantations made on abandoned fields, consisting of 1,200 saplings 6 feet high, for 20 years.

In 1901 the office of State forester (Mr. Walter Mulford) was created, charged with the acquisition of waste land at a price not to exceed \$4 per acre. Appropriation, \$2,000. Seed is to be used for planting. The expense of reforestation is not to exceed \$2.50 per acre. The State pays taxes on her own woodland.

8. Reservations: None.

9. Irrigation: 56 farms, situated along brooks, have 471 acres under ditch; expense of system \$34.21 per acre.

FORESTRY CONDITIONS OF DELAWARE:

1. Area: 700 square miles, or 35% of State, are wooded. Very little merchantable timber left after 12th census.

2. Physiography: Delaware occupies the northeastern portion of the peninsula formed by the Chesapeake and Delaware Bays. Soil sandy, slightly undulating.

3. Distribution: In the northern half of the State the broad-leaved species prevail. Here appears, scatteringly attached to farms, a struggling second growth of oaks, maple, poplar and

FOREST POLICY.

gum. In olden times "Delaware white oak," coming from this section, was famous as shipbuilding timber.

In the southern half of the State, woodlands consisting of pines (*mitis*; *rigida*; *virginiana*) and broad-leaved species predominate over the farms.

4. Forest ownership: 10 firms own 2,203 acres.

5. Use of timber: Logs on stump are worth \$3.52; at mill, \$5.55. 76 saw mills report an average investment of \$3,255. The output of the mills rises in value from census to census, in spite of supplies reported as waning. It was in

1850	\$236,000
1880	411,000
1900	471,000

The cut in the census year consisted of:—

Conifers	30,000,000 feet b. m.
Hardwoods	6,000,000 feet b. m.

After Fernow, in 1887, 200,000 cords of firewood were cut, selling at \$3 to \$4 per cord. The Dupont Powder Works use willow charcoal, obtained from their own plantations. Staves and headings locally produced are worth \$37,000. The local production of furniture and carriage stock, etc., is practically nil.

The leather industry is important, its output (from 20 firms) being \$9,500,000 in the 12th census year. The product, however, consists almost entirely of goat skins. These skins are not tanned by the vegetable tanning process, but chemicals (chromium, aluminum and other salts) are used. The price of the chemicals consumed alone is \$244,000. The consumption of hemlock bark amounts to 1,316 cords only; that of oak bark to 300 cords only.

The paper and pulp industry produces \$600,000 worth of goods. It consumes large amounts of fiber and pulp produced elsewhere. There are used, however, 21,320 cords of poplar wood, locally produced and valued at \$131,467 (for soda fiber).

6. Forestry movement: None.

7. Laws: Delaware has excellent laws relative to the main impediments to forestry, which are taxes and fires.

(1) Property is taxed only on its rental value. Hence woodland is almost exempt from taxation, the rents being exceedingly small.

FOREST POLICY.

(2) Firing of woodlands is punishable unconditionally and everywhere. The only fires allowed are those kindled between March 10 and May 1 by land owners intending to burn their clearings previous to plowing.

8. Reservations: None.

9. Irrigation: None.

FORESTRY CONDITIONS OF FLORIDA:

1. Area: 37,700 square miles, or 70% of State's area, under forest, mostly stocked with commercial timber.

2. Physiography: Southern section consists largely of swamps and hummocks, impassable from June to October (Lake Okeechobee). North of the 28th degree of latitude, the country is level, rarely undulating. Here the swamps are found more near the coast.

The western section of the State, near Tallahassee, is higher than the rest (average about 250 feet above sea level), intercepted with low mountain ranges.

Frost is rare; the summer climate is unhealthy in the south. The Everglades show from 1 to 3 feet of water even during the dry season of the year. Drought frequent from February to June.

3. Distribution: Sargent estimates, in 1880, the stand of pine at 6,615,000,000 feet b. m. A line drawn from Charlotte Harbor to Cape Malabar divides the State into a northern three-fifths and a southern two-fifths.

(a) Northern section. It contains long leaf and Cuban pine, with some little Taeda. Long leaf pine, on its way south, loses continually in volume and in quality of timber. Along the shore, evergreen oaks, notably live oak, are found in place of pine; further, palmetto and scrub pines. In the western counties, near Tallahassee, broad-leafed species of northern character prevail besides the pines. Large yellow poplars, ashes and hickories occur here along the water courses.

In the bottoms, cypress and gum swamps are said to scale 10,000 feet b. m. per acre. Evergreen broad-leafed species (magnolias, oaks, bays) fringe such swamps. A species peculiar to this region is the "stinking cedar" (*Tumion taxifolium*) and the

FOREST POLICY.

pencil cedar, the latter of splendid quality on hummocks and bottom land. Palmetto occurs everywhere on moist soil and abandoned fields as a weed. There is practically no echinata.

(b) Southern section. The southern section has only one pine, the Cuban pine, to show, which grows on sand dunes in the Everglades. Cypress swamps prevail everywhere. Along the coast and on the "Keys," the northern sentinels of the West Indian tropical flora occur in small specimens. Their occurrence is commercially unimportant. Amongst them are mahogany and lance wood (*Ocotea catesbyana* Sarg.).

4. Forest ownership: 113 lumber firms own 1,318,000 acres; balance of forests belong to State, federal government, farmers and holders of old Spanish land grants.

5. Use of timber: 368 saw mills of \$16,588 average investment. Logs on stump worth \$1.22, at mill \$6.23. Value of mill output was in

1880.....	\$ 3,100,000
1890.....	5,500,000
1900.....	10,800,000

The cut in 1900 consisted of

Cypress.....	110,000,000 feet b. m.
Yellow pine.....	712,000,000 feet b. m.
Hardwoods.....	2,000,000 feet b. m.

Red cedar (Virginiana) output is not given by the 12th census. The largest pencil cedar mills of the world exist at Cedar Keys. Cypress is used for door, sash, shingles, fish and syrup barrels; long leaf pine for railroad ties, car sills, trestle bridge timbers, doors, blinds, flooring and general house building purposes, also for shingles. Value f. o. b. steamer, on an average, now \$14 per 1,000 feet b. m. (in 1895 only \$9).

Conservative lumbering has been practiced along the Gulf coast by lumbermen for dozens of years, unknowingly, since only prime stumpage used to be convertible into lumber. Logging was done in former days by canals (which in many cases were 20 miles long), dug as connections between trees, swamps and water courses.

No leather industry, although the mangrove (*Rhizophora* mangle) forests of the tropical south might yield bark extremely rich in tannin.

FOREST POLICY.

No paper industry.

6. Forestry movement: None.

7. Laws: Wilful firing of woodlands punishable. Fires rare, after Sargent, owing to multitude of swamps.

8. Reservations: None.

9. Irrigation: Florida leads among the humid States—the rice-growing States excepted—in the value of irrigated products and in number of irrigated farms (only 1,485 acres). 180 truck farms (winter farming) report irrigation. Cost of system, \$101.52 per acre (very high).

FORESTRY CONDITIONS OF GEORGIA:

1. Area under forest 42,000 square miles, or 71% of total area, containing, after 12th census, mostly (?) merchantable forests. Sargent, in 1880, estimated stand of pine at 16,800,000,000 feet b. m., a figure found much too low.

2. Physiography: The extreme northwestern eighth of the State is traversed by the Table Mountain and Alleghany Ranges, spurs of which protrude to Rome and Atlanta. Southeast of the mountains the Piedmont plateau occupies two-eighths of the State, separated by a line running through Augusta, Macon and Columbus from the remaining five-eighths of the State formed by the level or slightly undulating coastal plain. The huge Okefenokee Swamp lies in the extreme southeast.

3. Distribution: The mountainous section has the species of the southern Appalachians, namely, white, red, scarlet and chestnut oak; chestnut, walnut and hickory; yellow poplar, cucumber, sweet and yellow birch; cherry, beech, locust, rigid and table mountain pine; also white pine and hemlock. In the Piedmont plateau, oaks and hickories, with or under *Pinus echinata* (usually) or *taeda*. A stray island of long leaf pine is found on the Alabama line in the northwest. The lowlands of the coastal plain show long leaf pine on sandy soil, mixed with *taeda* on moister sites. Huge swamps near coast and rivers are stocked with cypress and gums. White cedar prefers the half-swamps. Evergreen broad-leaved species (*Persea*, *Magnolia*) line the swamps. Cuban pine grows far inland, up to 100 miles from shore, occupying the wet dells in the long leaf pine woods.

FOREST POLICY.

4. Forest ownership: 453 firms own 1,108,000 acres of forest, containing 3,800 feet b. m. average stumpage. The balance of the wood lands belongs to farmers, or to counties and State under tax-forfeitures.

5. Use of timber: Long leaf pine was and is frequently sold as "Georgia pine." The woods are far from being exhausted. The inroads of the turpentine industry seem more injurious to the perpetuity of the forest than those of the lumber industry. 1,202 mills of \$4,274 average investment. Logs on stump are worth \$1.01; at mill, \$4.41. Logging by railroad and by rafting. Value of output in

1860	\$ 2,400,000
1870	4,000,000
1880	4,900,000
1890	6,500,000
1900	13,700,000

The cut of 1900 consisted of:—

Yellow pine	1,295,000,000 feet b.m.
Other conifers	18,000,000 feet b. m.
Hardwoods	39,000,000 feet b. m.

Cooperage and miscellaneous industries are small, their output amounting to only \$135,000 in the census year.

The leather industry produces in 36 establishments \$1,187,000 worth of products and consumes 23,217 cords of oak bark (valued at \$87,000); 85 cords of hemlock bark; 5,107 barrels of oak bark extract (worth \$41,000), and 950 barrels of quebracho extract (worth \$16,800).

Paper and pulp industry: None.

6. Forestry movement: In 1887 a bill asking for a forest commission, etc., seems to have failed.

7. Laws: Firing of woods by the owner must be preceded by notice given the adjoining land owners (excepting the months of March and April).

8. Reservations: None.

9. Irrigation: 7,856 acres of rice fields were irrigated in 1899, constituting 35% of the total rice area and yielding 72% of the total rice product. Cost of system, per acre, is \$31.85.

FOREST POLICY.

FORESTRY CONDITIONS OF IDAHO:

1. Area: 35,000 square miles, or 42% of the State, are wooded.

2. Physiography: Southern third is traversed by the east and west course of the Snake River and consists of barren plains. The northern, wedge-shaped part of the State, contains the mountainous Coeur d'Alene region. The Teton and Yellowstone Ranges form the boundary towards Wyoming; the Bitter Root Mountains the boundary towards Montana. The mountains of central Idaho drain southward towards the Snake River, northward towards the Salmon River.

3. Distribution: Southern lava plains, destitute of timber and vegetation, except sage brush. The Salmon River Mountains are unexplored and contain, after Gannett, little timber. The Rockies show yellow pine, Douglas fir, lodgepole pine and western white pine. In the Bitter Root Mountains, Douglas fir and yellow pine prevail below 6,000 feet elevation, lodgepole pine above 6,000 feet elevation. In the extreme north a dense forest cover, originally found, is now badly burned. Here yellow pine and Douglas fir cease to be prevailing; white pine (*monticola*) and larch (*Larix occidentalis*) preponderate, numerically and in volume. In the Priest River Mountains three zones may be distinguished. In the highest zone, above 4,800 feet, balsam (*Abies lasiocarpa*) and white bark pine preponderate.

The zone between 2,400 feet and 4,800 feet is the largest and contains white pine and larch.

In the lowest zone, Douglas fir is mixed with yellow pine, lowland fir and western red cedar. Lodgepole pine is found all over the northern and eastern part of Idaho, taking advantage of heavy fires. Black hemlock, lowland fir and Engelmann's spruce also occur.

4. Forest ownership: 4,147,200 acres of forest land are reserved. Lumbermen own only 84,000 acres in the lowest zone, with 6,900 feet average stand per acre. Over 200,000 acres lie in the Indian reserves. Over 600,000 acres of forests are attached to farms.

5. Use: Timber is mostly used for mining props. The mill cut in 1900 was worth \$937,000, and consisted largely of yellow pine. The stumpage is worth \$1.09. Logs at mill are worth

FOREST POLICY.

\$3.95. 114 saw mills report an average investment of \$4,759. No paper, pulp or leather industries.

6. Forestry movement: Nill.

7. Laws: Usual fire and camper's laws. Arbor Day law.

8. Reservations: Bitter Root forest reserve, meant to protect irrigation in Washington, contains 4,147,200 acres, of which 690,000 acres lie in Montana.

The Priest River forest reserve, part of which (104,000 acres) lies in Washington, comprises 645,120 acres.

9. Irrigation: Only possible from small feeders in outskirt valleys.

The products of irrigation are forage crops (alfalfa) and small grain at the higher elevations of 4,000 to 5,000 feet; orchard fruit at elevations of 2,000 to 3,000 feet, notably along the lower course of the rivers (Snake River).

The irrigated area, 600,000 acres, has produced, in 1899, \$5,400,000 worth of crops from irrigation systems costing \$5,100,000.

FORESTRY CONDITIONS OF ILLINOIS:

1. Area: 10,200 square miles or 18% of area of State are classed as woodland.

2. Physiography: Gently rolling prairies. Mississippi River on western line. Illinois River traverses State from north-east to southwest.

3. Distribution: The southern third of the State once contained good to splendid hardwood forests stocked with the hardwoods of the Mississippi River Basin, in addition to cypress swamps. The northern two-thirds are prairie, excepting a belt along the lake, on which white pine is sparingly found. The oak openings on the prairie are stocked with burr, scarlet, red, black and post oaks.

4. Forest ownership: All woodland is attached to farms, excepting 162,000 acres of 4,800 feet b. m. average stumpage, owned by 167 lumber firms.

5. Use of timber: Chicago is still the most important lumber distributing center in the United States, fed by the pineries

FOREST POLICY.

of the Lake States and by the hardwood forests of the Mississippi Valley. There are found in the State 825 saw mills, of \$3,815 average investment, and 280 large planing mills, of \$25,000 average investment. The output of the lumber industry is rising, being \$5,000,000 in 1880 and 1890, and \$7,600,000 in 1900. The cut of home grown timber in 1900 consisted of:

Conifers.....	138,000,000 feet b. m.
Cottonwood.....	19,000,000 feet b. m.
White oak.....	170,000,000 feet b. m.
Other hardwoods.....	63,000,000 feet b. m.

Logs are worth on stump \$2.64 and at mill \$8.36 per 1,000 feet b. m.

The leather industry has used in the census year 18,312 cords of hemlock bark (imported) and 22,846 bales of gambier. Products are valued at \$7,800,000.

The pulp and paper industry uses only 864 cords of native wood, and depends on straw, rags, waste paper and pulp of foreign manufacture for its raw material.

6. Forestry movement: None except Arbor Day and bounties for prairie planting.

7. Laws: Firing of woods and prairies permissible only from April 15 to October 15. Railroads liable for fires starting from sparks. Bounty of \$10 per acre for forest plantations.

8. Reservations: None.

9. Irrigation: None.

FORESTRY CONDITIONS OF INDIANA:

1. Area: After 12th census, 10,800 square miles, or 30% of State, are wooded. No large forests exist.

After recent official investigations,

250,080 acres are stocked with heavy timber;
834,506 acres contain second growth, and
3,733,456 acres are described as thin wood pasture.

2. Physiography: Undulating land. Main river is the Wabash. 692,738 acres are classed as waste lands in 1903.

FOREST POLICY.

3. Distribution: Prairie only in some northern counties where the forest is said to be expanding. Entire balance of Indiana, 100 years ago, was heavily wooded with 12 species of oak, 3 of elm, 2 of walnut, 7 of hickory, 3 of maple, 3 of birch, 4 of ash, yellow poplar, linden, buckeye, black and honey locust, dogwood, catalpa, sassafras, hackberry, red mulberry, sycamore, ironwood, chestnut, beech, cottonwood, white pine, gray pine and Virginia pine, bald cypress, tamarack and red cedar. All trees show splendid bole development. The requirements of the farmer and home seeker have caused the forest to be considered a mere encumbrance of the ground. Only small groves now exist.

4. Forest ownership: 162 lumber firms, in 1900, owned 104,000 acres of woodlands. The rest is attached to farms.

5. Use of timber: Indiana leads the United States in the output of wagon stock (raw material), producing 33% of the entire output. In furniture stock, Indiana is second only to Ohio. One-half of Indiana's manufactures rely on the forest for their raw material. Log stumpage worth \$5.39 (maximum amongst Union States); logs at mill worth \$9.39 per 1,000 feet b. m. There are 1,829 saw mills of \$4,500 average investment.

Output of the lumber industry

In 1870 was	\$12,300,000
In 1880 was	14,300,000
In 1890 was	20,800,000
In 1900 was	20,600,000

The cut in 1900 was:—

Conifers	3,000,000 feet b. m.
White oak	646,000,000 feet b. m.
Other hardwoods	336,000,000 feet b. m.

Total.....985,000,000 feet b. m.

The leather industry, comparatively small, produces \$1,500,000 of leather and consumes 700 cords of hemlock bark, 7,000 cords of chestnut oak bark and 5,000 barrels of oak bark extract.

The pulp and paper industries are said to use 6,300 cords of domestic (?) spruce, 10,500 cords of Canadian spruce, 20,300 cords of poplar and 4,200 cords of miscellaneous woods, in addition to

FOREST POLICY.

a large quantity of rags and straw (120,000 tons). 39 mills produce \$4,200,000 of paper products.

6. Forestry movement: Recent, but energetic propaganda, influenced by John P. Brown (of Connersville).

State forest association.

7. Laws: Fire laws since 1818. A unique forest reservation law (of 1899) encourages private reserves. Such reserves (which must not exceed in acreage an eighth of a tract individually owned, trees per acre) are assessed at \$1 per acre only, whilst the average assessed value of farm land, in 1898, was \$20. In 1901 there existed 284 private reserves, covering 5,312 acres. Law of 1901 creates a Board of Forestry, consisting of five members, one of them drawing a salary (W. H. Freeman). Its duties are:—

(1) Collection of statistics.

(2) Forestry education.

(3) Formulation of plans for private and State forest reserves. Insufficient appropriations.

8. Reservations: 2,000 acres of State forest reserves are set aside by law of 1903, as a demonstration forest and for nursery purposes.

9. Irrigation: None.

FORESTRY CONDITIONS OF IOWA:

1. Area: Area of woodlands is 7,000 square miles, equal to 13% of area of State. Settlement has reduced the woodland area by 50%. Planted forests said to aggregate 120,000 acres.

2. Physiography: Level or undulating land, extending from the Missouri to the Mississippi.

3. Distribution: Broad bottom lands of the Mississippi bore, and still bear splendid hardwoods, the best in the south-eastern section. In the western prairie section the streams are skirted with hardwood groves from one-half to 4 miles wide. Of the northeastern flora there occur in the hardwood bottoms: shag bark and bitternut hickory; burr, red, black and white oaks; green ash, hard and soft maple, box elder, basswood, white

FOREST POLICY.

elm and butternut. From the southeast enter the Kentucky coffee tree, honey locust, swamp white oak, pin oak, laurel oak, red bud, Ohio buckeye, mocker nut, pecan and black walnut. The only conifers found are white pine, scattered in extreme northeast, and red cedar.

4. Forest ownership: Practically all woodland belongs to farmers. 43 lumber firms own 56,160 acres, stocked with 4,900 feet b. m. on the average acre.

5. Use of timber: Woodlands are used for pasture. During seasons of drought, young growth is frequently found dying. The lumber industry, in addition to the cooperage industry, is about to exhaust the fine hardwoods. Logs on stump are worth \$4.95; logs at mill, \$12.16 (maximum of the United States). Still there are now left 264 mills of \$18,885 average investment. The largest of these mills are located on the Mississippi River, and saw pine rafts coming from Minnesota and Wisconsin.

The value of the sawn product in 1870 and 1880 was \$6,000,000; in 1890 it was \$12,000,000; in 1900 it had dropped to \$8,700,000.

The output of the mills in the census year was 303,000,000 feet b. m. of conifers and 40,000,000 feet b. m. of hardwoods. Since there is but little white pine found in Iowa, it seems as if white pine, not home grown, composed the bulk of the output of softwoods. Lumbermen, however, are said to still own, inside the State, 231,000,000 feet b. m. of conifers (?).

Leather industry, none. Paper industry uses straw (12,350 tons of straw in census year).

6. Forestry movement: Arbor Day since 1874. Prairie planting still practiced, the favorite species being soft maple, green ash and box elder. The Agricultural College at Ames has given instruction in tree planting for almost 30 years.

7. Laws: Prairie fire law. A law exempting almost \$6,000,000 worth of property from taxation, in order to encourage tree planting, is now repealed.

8. Reservations: None.

9. Irrigation: No data available.

FORESTRY CONDITIONS OF KANSAS:

1. Area: 5,700 square miles, or 7% of the State's area, are wooded.

FOREST POLICY.

2. Physiography: Undulating prairies. Arkansas River, from Colorado, traverses the western half.

3. Distribution: A few yellow pines occur in the higher ridges of the western section, which is otherwise treeless, except for the fringes of poplar and willow in the river canyons.

The eastern section shows wide belts of hardwood forests along the streams, the best timber being found in the extreme southeast, where the heavy timbered outskirts of the Mississippi River hardwood bottom lands appear.

4. Forest ownership: About 1,000,000 acres of forest are said to be attached to farms. Not quite 8,000 acres are owned by 22 lumber firms, stocked with 3,500 feet b. m. on the average acre.

5. Use of timber: Lumber industry in Kansas has declined since 1880, when 146 establishments were cutting 45,000,000 feet b. m. of lumber.

In 1900 there were in existence 54 mills, showing lowest average investment in the United States, namely, \$1,070. Value of product, \$104,000, against \$683,000 in 1880. Log stumpage worth \$2.17; logs at mill, \$7.84 per 1,000 feet b. m.

Fuel and fencing are badly required by the farmers.

Lumber for building purposes obtained from the east and south.

Paper, pulp and leather industries: None.

6. Forestry movement: Usual Arbor Day enthusiasm.

The State Agricultural Board reports 119,000 acres planted in forest since 1884.

Some of the best catalpa plantations are found on rich prairie soil in Kansas. In 1885 the office of Commissioner of Forestry was created, issuing reports and distributing seedlings. The State Horticultural Society tries to centralize interest in tree planting and issues a Tree Planter's Manual. Kansas City boasts of employing a "Forester."

7. Laws: Bounty Law of 1868 is repealed. Wilful firing is fined \$500. It is the sworn duty of the justices of the peace to bring incendiaries to judgment.

8. Reservations: 94,732 acres of sandy land, south of Arkansas River, are withdrawn from entry to be used for planting trees. No presidential proclamation issued so far.

9. Irrigation: In the census year 24,000 acres of land were irrigated (2,000 acres from wells).

FOREST POLICY.

The irrigated crop was valued at \$226,000. The construction expense of the irrigation system was \$530,000.

FORESTRY CONDITIONS OF KENTUCKY:

1. Area: Area of woodlands 22,000 square miles, or 53%.
2. Physiography: Ohio River on the north. Mississippi River on the west. The Big Sandy, tributary of the Ohio River, on West Virginia line. Cumberland Mountains in the extreme southeast, giving rise to the Kentucky River, which runs north into Ohio, and to the Cumberland River. Undulating plateau well watered.

The Cumberland Mountains, where limestone formation prevails, have coal and iron mines. Middlesborough about the center of the coal industry.

3. Distribution: Kentucky "barrens" in the southwest, very productive of tobacco, hemp and grain. Here the pioneers found big stumps called "stool grubs," the remnants of a splendid forest, probably burned by the Indians. The black oak forest (black jack, black post and Spanish oak) is gradually invading the "barrens."

The bottoms of the Ohio and Mississippi Rivers, subject to inundations, exhibit in the swamps bald cypress, sweet and black gum. On very wet soil, cottonwoods, cow oaks, gums, ashes and hickories of splendid development occur. On somewhat drier soil, beech, red oak, yellow poplar, white oak and burr oak prevail.

In the "Blue Grass Region," gigantic red cedars, walnuts, poplars, hickories, beeches, sycamores, lindens, locusts, coffee trees and white oaks have been cleared away, and only groves or fringes of these species are now left. In the mountain section, walnuts, chestnuts, chestnut oaks, yellow poplars, ashes, hickories, three maples, locusts, white, red and black oaks of splendid development form the bulk of the timber.

The section above the falls of the Cumberland River was practically untouched as late as 1880.

The pines form only a small percentage of the timber. White pine, accompanied by hemlock, occurs at the higher altitudes of the Cumberland Mountains. Echinata is scattered over

FOREST POLICY.

the southern two-thirds of the State, especially in the east, never forming pure forests, groves on abandoned fields excepted. *Pinus Virginiana* seems to develop unusually good boles in the eastern half of State and is locally used for custom lumber. *Rigida* is found, like *echinata*, running up higher into the mountains.

4. Forest ownership: 208 mill firms own 382,000 acres of forest, having 4,700 feet b. m. average stumpage. After the 12th census this stumpage includes 125,500,000 feet b. m. black walnut, which figure seems largely overestimated.

5. Use of timber: The value of the sawn product was in

1850	\$ 1,500,000
1860	2,500,000
1870	3,600,000
1880	4,100,000
1890	7,900,000
1900	13,800,000

The cut in 1900 consisted of:—

Conifers	34,600,000 feet b. m.
Ash	4,900,000 feet b. m.
Black walnut	2,100,000 feet b. m.
Poplar	279,000,000 feet b. m.
White oak	392,800,000 feet b. m.
Other hardwoods	63,100,000 feet b. m.

Total776,500,000 feet b. m.

In the census year there were further produced 60,000,000 shingles, worth \$115,000; 63,000,000 (mostly) oak staves, worth \$1,042,000; 3,500,000 sets of heading worth \$234,000. Furniture, wagon and agricultural stock is valued at \$1,358,000. Kentucky ranks 6th in cooperage and 8th in miscellaneous timber industries. The ratio of forestry in wages, investments and products to all other industries, in 1900, was that of 14 to 100. 1,232 mills showed an average investment of \$4,658. Logs are worth on stump \$2.67, and \$6.86 at mill. Logging in mountains by oxen; elsewhere by oxen, horses and mules. Transportation largely by raft, or loose driving. Small portable mills in tracts far from rivers and railroads. Big mills on Cumberland River.

FOREST POLICY.

Leather industry yields, in 1900, a product worth \$3,750,000, and uses 1,080 cords of hemlock bark, worth \$9,440; 29,840 cords of oak bark, worth \$22,400; 13,300 barrels of bark extract, worth \$139,000; besides some quebracho, gambier and sumac.

Paper and pulp industry is insignificant.

6. Forestry movement: Little; recently stirred up by Federation of Women's Clubs. Berea College gives, through Prof. S. C. Mason, excellent training in conservative forestry to farm boys. Agricultural reports allude to forestry and its importance.

7. Laws: In a number of counties the firing of woods is forbidden. Constables are required to extinguish fires at expense of county.

8. Reservations: None.

9. Irrigation: None.

FORESTRY CONDITIONS OF LOUISIANA:

1. Area: 28,300 square miles, or 62% of the total area of the State, are wooded.

2. Physiography: Undulating land, alluvial soil, river bottom lands subject to continuous inundations. Mississippi River forms the eastern line. Red River of the South traverses the State from northwest to southeast. Sabine River is on the Texas line; the Pearl River on the lower Mississippi State line. A multitude of water-courses form a help to the utilization of the forest and to the prevention of fires.

3. Distribution: After the 12th census, the southwest portion is prairie. Long leaf pine in two large bodies, separated by the Red River, aggregating 4,300,000 acres of densest stumpage (4,000 to 6,000 feet and over per acre) often untouched. No Cuban pine. Echinata and Taeda extend from Red River northward to State line. The former species frequently shows an undergrowth of Spanish oak, black jack, post oak and hickories. Cypress grows in enormous swamps, with red gum and black gum. Along rich bottoms, evergreen magnolias, water oaks, red oaks, gums, cottonwoods, burr oak, white ash, pecan, persimmon, sassafras and beech. In drier localities, cow oak and burr oak.

FOREST POLICY.

4. Forest ownership: The State owns large swamp tracts. The farmers own 35% of all the woodlands. 170 lumber firms own 1,500,000 acres of 6,700 feet average stumpage.

5. Use of timber: The use of cypress for cooperage was large as early as 1880, when the pine woods were still untouched. The main center of long leaf pine mills is now at Lake Charles (Calcasieu River). Main center of short leaf pine mills is at Shreveport (Red River).

In 1900, 405 mills existed, of \$25,800 average investment. Logs were worth, in 1900, on stump, \$1.22, and at mill, \$5.59.

New Orleans is not a mill center, but is the largest southern shipping point of the lumber and cooperage industry.

Moss ginning is an industry turning out, in 1880, \$550,000 worth of material. There are no later statistics. Turpentine is only recently introduced, tending to ruin the prospects for conservative lumbering, owing to the danger of fire connected with it. In 1880, Sargent's fire statistics show a loss of \$6,000 worth of timber only, virgin pine being fireproof and the other species protected by swamps. Sargent, in 1880, estimates the stand of pine at 48,200,000,000 feet b. m. The products of the lumber industry are valued, in 1880, at \$1,700,000; in 1890, at \$5,700,000, and, in 1900, at \$17,400,000; a very rapid increase.

The cut in 1900 consisted of 1,200,000,000 feet b. m. (800,000,000 yellow pine, 340,000,000 cypress, 50,000,000 cottonwoods, 5,000,000 white oak). The average stand of white oak is said to be 7,800 feet b. m. per acre (?). Swamps cleared of cypress are doomed to lie barren.

No pulp industry.

Three small leather concerns use a few cords of oak bark, sumac and a few barrels of extract.

6. Forestry movement: None.

7. Laws: Unknown.

8. Reservations: None.

9. Irrigation: Louisiana, leading the States of the Union in rice production, irrigates from water-courses and from wells 202,000 acres of rice fields.

The cost of the irrigation system averages only \$12.54 per acre.

FOREST POLICY.

FORESTRY CONDITIONS OF MAINE:

1. Area: Woodlands comprise, after 12th census, 23,700 square miles, or 79% of State. In 1893 the State assessor reports only 15,000 square miles of forest.

After report of the forest commissioner in 1903 forest lands comprise 21,000 square miles, and 14,800 square miles are taxed as "wholly wild land."

2. Physiography: The north and northwest are said to be mountainous. Mount Katahdin, the highest peak, is 5,385 feet high. The south and southeast is hilly. Lakes, valuable for forest transportation, are found all over the State. The coast line is deeply indented. The most important rivers are the Androscoggin, Kennebec, Penobscot and St. John, the latter on and close to the New Brunswick line. 18,000 square miles are absolute forest land.

3. Distribution: The conifers of the northern pine belt (white pine, red spruce, white spruce, hemlock, balsam, tamarack, white cedar) occur mixed with maple, white and yellow birch, beech, ash, oak, hickory and basswood in varying proportions. Large bodies of hemlock used to exist in the southeast. Valuable bodies of poplar are found, especially on the Kennebec. Only the immediate coast region between the Kennebec and Penobscot lacked the conifers.

The State is largely cleared in the south, and the north is culled of its white pine. Pulp wood has been removed from one-half of the wild lands. Still lumbermen alone in 1900 were reported to be owners of over 1,000,000,000 feet b. m. of white pine. Good second growth of white pine is found all over the southern counties. Regeneration of spruce is frequently met beneath an ushergrowth of gray and white birch, poplar and pine.

The sustainable yield of the spruce woods amounts to 637,000,000 feet b. m. (after Ralph S. Hosmer) per annum.

Forest Commissioner E. E. Ring publishes the following figures as the result of recent explorations:—

Stumpage of coniferous timber (9 inches and over in diameter) in million feet b. m.

Drainage System.	St. John River.	Penobscot River.	Kennebec River.	Androscoggin River.	Ten Minor Rivers.
Spruce.....	6,942	5,166	3,883	3,248	2,000
Pine	427	153			
Cedar	1,830	438			

FOREST POLICY.

4. Forest ownership: 204 saw-mill firms own 2,108,000 acres of 2,000 feet (only?) stumpage. Paper firms own several hundred thousand acres of woodland, largely cut over. 22.4% of woodland is attached to farms.

5. Use of timber: The State contains 832 saw mills. of \$11,754 average investment. Stumpage costs \$2.52; logs at mill, \$8.15 per 1,000 feet b. m.

Value of output of saw mills and timber camps was:—

1850	\$ 5,900,000
1860	6,600,000
1870	11,400,000
1880	7,900,000
1890	11,800,000
1900	13,500,000

The cut for saw mills in 1900 consisted of:—

Spruce.....	425,000,000 feet b. m.
White pine.....	220,000,000 feet b. m.
Hemlock.....	89,000,000 feet b. m.
Other conifers.....	87,000,000 feet b. m.
Hardwoods.....	29,000,000 feet b. m.

Total.....850,000,000 feet b. m.

There were produced in the census year \$903,000 worth of shingles, \$408,000 worth of cooperage stock, \$364,000 worth of lath, \$600,000 worth of boxes, \$20,000 worth of baskets and wood-ware, \$294,000 (60% of output of United States) worth of bob-bins and spools (white birch) (Ring reports a production of 800,-000,000 spools, worth \$1,000,000, for 1903).

The hardwood industries are increasing with the expansion of the railroads ("Hardwood Novelty Mills"). Modern lumbering is astonishingly conservative and never destroys the chances of a good second growth. Conservative lumbering in pure spruce woods ("black growth") is, however, apt to be followed by sweep-ing blow-downs. Logging for pulp, consuming about 275,000,000 feet b. m. annually, is less wasteful than logging for lumber. Saw mills, on the other hand, are less interested in permanent supplies than pulp mills. Average age of spruce logs is about 200 years. The use of the cross-cut saw is novel in the Maine woods. Logs are usually peeled (which requires summer cutting), and

FOREST POLICY.

long lengths of logs are held out. Railroading is gradually superseding river driving.

Leather industry: 31 firms produce \$2,451,000 worth of leather and consume 40,600 cords of hemlock bark, worth \$229,000; 4,000 cords of oak bark, worth \$28,000; 1,080 bales of gambier, worth \$7,370; 200 barrels of extract, worth \$2,740; 125 tons of sumac, worth \$7,675; chemicals, worth \$5,615.

Paper and pulp industry: 35 mills produce in the census year \$13,200,000 worth of material and consume: home-grown spruce, 265,000 cords, worth \$1,325,000; Canadian spruce, 20,600 cords, worth \$170,000; home-grown poplar, 49,000 cords, worth \$199,000; Canadian poplar, 500 cords, worth \$1,700; other pulp-wood, 6,500 cords, worth \$21,700.

6. Forestry movement: Public sentiment is aware of the inter-dependence between the State's prosperity and the safety of the forest; hence forest fires are not allowed to roam at random. The memory of famous fires, like the Miramichi fire of 1825, has helped to mould public opinion. The fire warden system, however, is still inadequate.

The public are interested in developing the resort character of the woods. Pine offspring in farming sections is carefully husbanded.

Good reports by Chas. E. Oak and Austin Cary in 1894 and 1896; by E. E. Ring in 1902.

7. Laws: The State Land Agent (now E. E. Ring) acts as Forest Commissioner, since 1891. His duties are:—

- (1) Forestry education, through public schools.
- (2) Preparation of circulars relative to care of woodlands, to be furnished upon application to any citizen of the State.
- (3) Distribution of fire reports (blank forms) amongst fire wardens.
- (4) Posting fire law notices.
- (5) Collecting forest, lumber and fire statistics.
- (6) Prevention, control and extinguishment of forest fires in unorganized townships.

Guides are licensed and charged with protection of the forest. Fire wardens are

(a) In unorganized townships appointed by the forest commissioner (since 1903), paid by the State at the rate of \$2 per day. Helpers summoned by the warden are paid 15c. per hour. An

FOREST POLICY.

emergency fund of \$10,000 annually is set aside for this purpose by the legislature.

(b) In organized towns recruited from the selectmen, each selectman serving ex officio as warden for a specified district, at the expense of the town, which also pays for helper's services.

The fire wardens shall submit to the forest commissioner reports on the extent, damage and cause of forest fires; further, on the remedial measures taken to subdue fires within their wardships.

Fire wardens seem, however, not punishable for neglect of duty.

The forest commissioner has, unfortunately, no control over the fire wardens in organized towns.

8. Reservations: None.

9. Irrigation: 11 farms irrigate 17 acres for truck production.

FORESTRY CONDITIONS OF MARYLAND:

1. Area: 4,400 square miles, or 44% of State. After 12th census very little of wooded area contains merchantable timber.

2. Physiography: Three sections.

Western section in Alleghanies and Blue Ridge Mountains, with altitudes of over 3,000 feet. The Potomac, forming the West Virginia and Virginia line, breaks through the Blue Ridge on extreme east corner of West Virginia.

The middle section presents a plateau, falling from the Blue Ridge down to Chesapeake Bay.

The eastern section of lowlands consists of two peninsulas formed by the Chesapeake Bay, Potomac River and Delaware Bay.

3. Distribution: The mountain section was, originally, heavily timbered with white pine, hemlock, maple, birch, beech and spruce—the Adirondack forest at an elevation 1,000 feet higher than it is found in the Adirondacks. Now little virgin forest is said to be left.

The central section was, originally, covered with hardwoods. Now chestnut coppice prevails, or a second growth of white oak, black oak, hickories and gum.

The eastern peninsula shows a second or third growth of pitch and scrub pine, mixed with hardwoods.

FOREST POLICY.

4. Forest ownership: 114 firms own 66,928 acres of 3,700 feet b. m. average stumpage.

5. Use of timber: The lumber manufacture has never been prominent in Maryland. After the census reports, however, it continues growing, in spite of the lack of primeval supplies. The output of the Maryland mills was valued in

1850	\$ 585,000
1860	605,000
1870	1,501,000
1880	1,813,000
1890	1,600,000
1900	2,650,000

The cut in 1900 consisted of:—

Yellow pine	79,000,000 feet b. m.
Hemlock	21,200,000 feet b. m.
White pine	1,600,000 feet b. m.
Spruce	3,500,000 feet b. m.
Miscellaneous conifers	4,300,000 feet b. m.
Oak	66,000,000 feet b. m.
Chestnut	5,000,000 feet b. m.
Poplar	5,000,000 feet b. m.
Miscel. hardwoods ...	2,300,000 feet b. m.

Logs on stump are worth \$2.92; at mill, \$6.75. 366 mills represent an average investment of \$3,643.

The cooperage industry was important in olden times; had greatly declined in 1880, and depends in 1900 almost entirely on the use of imported cooperage stock, turning out \$700,000 worth of products. The home grown staves and headings are worth only \$15,000. No furniture stock and little carriage stock is obtained inland.

The box factories turned out, in 1900, \$1,800,000 worth of boxes, and seem to depend on imported stock for raw material.

Leather industry: There are 21 tanneries of \$1,754,000 annual output. They consume 3,116 cords of hemlock bark, valued at \$21,888; 12,087 cords of oak bark, valued at \$80,603; 309 barrels of oak bark extract; 111 tons of sumac and chemicals; 25 tons of quebracho.

The paper and pulp industry produces, in 21 mills, \$2,600,000 worth of products and uses 23,229 cords of home-grown spruce,

FOREST POLICY.

worth \$147,615; 4,616 cords of poplar, worth \$30,825; 20,623 cords of other woods, worth \$135,825.

6. Forestry movement: None.

7. Laws: A bill, failing in 1902, provided for:—

(a) State Board of Forestry, consisting of three members, one to be a scientific forester, two to be owners of 100 acres of farm land. Commissioners hold office at Annapolis, are supplied with a secretary and receive \$600 each annually. Their duty is to purchase woodland at the headwaters, at a price not to exceed \$8 per acre, or else deforested land in other sections of the State. No price limit is given for the latter purchases. An appropriation of \$30,000 annually is set aside for land purchase, and \$6,000 for salaries and expenses.

(b) Bounties of 10 cents a tree shall be paid for every locust, black walnut, hickory, red and black oak planted according to certain regulations; also a bounty of 5 cents for every chestnut thus planted and for trees of other species fit for fence posts. \$5,000 are annually provided for bounty payments.

Only malicious firing is punishable.

8. Reservations: None, the above cited reserve law having failed to pass.

9. Irrigation: None.

FORESTRY CONDITIONS OF MASSACHUSETTS:

1. Area under forest: After 12th census, 4,200 square miles, or 52% of the State, are wooded. A State canvass of 1885 gives, however, only 1,390,000 acres of woodland classed as follows:—

317,000 acres of timber over 30 years old.

993,000 acres of growth under 30 years old.

6,000 acres of planted forest,

74,000 acres of woodland not classified.

2. Physiography: The western half of the State is mountainous. Here the Taconic and Hoosac Ranges, with the Berkshire Hills, rising in Mount Graylock to 3,535 feet elevation. The eastern half is hilly, or flat in the southeastern peninsula.

3. Distribution: Massachusetts forms part of the northern pine belt, stocked originally with white pine, hemlock and spruce, mixed with hardwoods in varying proportions. The hard-

FOREST POLICY.

wood coppice now existing consists of maple, chestnut, oaks, gray birches, hickories and pitch pine. Scattering red cedar and a few groves of white pine or hemlock are frequently met.

4. Forest ownership: The Boston park system now aggregates 6,784 acres. 162 lumber firms own 41,000 acres of 9,000 feet b. m. stumpage. Cities near South Orleans, after Sargent, have fully 10,000 acres planted in pitch pine. The balance of the woodlands is attached to farms.

5. Use of timber: Stumpage costs \$2.64; logs at mill, \$9.49. 534 saw mills, the larger ones placed along the Connecticut, report an average investment of \$7,518. The value of the sawed output is constantly rising:—

1850	\$1,500,000
1860	2,200,000
1870	3,500,000
1880	3,100,000
1890	5,200,000
1900	6,500,000

The cut of the mills in 1900 consisted of:—

Spruce	29,000,000 feet b. m.
White pine	261,000,000 feet b. m.
Hemlock	12,000,000 feet b. m.
Other conifers	2,000,000 feet b. m.
Chestnut and oak	42,000,000 feet b. m.

Total 346,000,000 feet b. m.

A large proportion of this cut seems, however, to have originated in Vermont and New Hampshire.

Farm lots are said to produce nearly 600,000 cords fire wood and over 400,000 railroad ties.

Woodenware, manufactured from second growth white pine, forms an important industry (notably near Winchendon).

Large production of hoop poles. The miscellaneous industries are otherwise insignificant. The box, casket and barrel industries rely entirely on stock imported from other States for a production valued at \$5,500,000 per annum.

Leather industry: Massachusetts is second only to Pennsylvania in leather production. 119 plants produce \$26,000,000 worth of leather and consume 62,000 cords of hemlock bark, worth

FOREST POLICY.

\$498,000; 1,000 cords of oak bark, worth \$9,000; 15,500 bales of gambier, worth \$106,000; 17,000 barrels of extract, worth \$170,000; 3,600 tons (!) of sumac, worth \$190,000; 500 tons quebracho, worth \$8,000; chemicals worth \$307,000.

Paper and pulp industry: Massachusetts is second only to New York in these industries; still her consumption of wood is small, consisting of home-grown spruce, 21,200 cords, worth \$110,000; Canadian spruce, 13,800 cords, worth \$113,000; home-grown poplar, 3,000 cords, worth \$18,000; other wood, 1,000 cords, worth \$5,000. Enormous amounts of rags, manilla, waste paper; further, imported pulp and fiber form the chief raw material.

6. Forestry movement: The Massachusetts Forestry Association is backed by wealthy and educated tree lovers, and employs a forester (T. F. Borst). The Arnold Arboretum, at Jamaica Plains, offers unrivalled advantages to the student of dendrology. Chair of forestry at Harvard since 1903.

7. Laws: The selectmen of towns appoint annually one or more fire wardens, paid according to the pleasure of the town. Unique and interesting is a law allowing cities and towns to contract loans and to secure State contributions (50% of expense) for forest park purposes. Tax exemptions are granted for ten years on plantations, consisting of 2,000 saplings over 4 feet high (per acre), made on abandoned fields. Sand dunes at Cape Cod are being replanted under State law.

8. Reservations: City reserves are small, but of great local importance. Three State reserves, called the Mount Tom, Graylock and Wachusett State Parks, were established in 1902 and placed in charge of a State forester.

9. Irrigation: 28 farms irrigate 134 acres, for truck production.

FORESTRY CONDITIONS OF MICHIGAN:

1. Area: Area of woodland, inclusive of stump land, is 67% per cent of State area, or 38,000 square miles. Fernow gives 38% only.

2. Physiography: Two peninsulas. Ground level or undulating with sandy or gravelly ridges. Splendid shipping facilities via the lakes. Rivers important in the white pine industry are the Muskegon, Manistee, Shiawassee, Kalamazoo and Saginaw.

FOREST POLICY.

3. Distribution: Prairies only in the extreme south of the lower peninsula. South of the 43d degree of latitude, broad-leaved species prevail on land pre-eminently fit for agriculture. Here are found elm, ash, basswood, maple and white oak of splendid development.

The northern part of the lower peninsula and the entire upper peninsula were occupied by the famous pineries of Michigan, sprinkled with swamps of tamarack, cedar, spruce and balsam, and sand barrens stocked with jack pine, poplar, birch and scrub oak.

In the pineries there are mixed with the white pine, often as an undergrowth, ash, sugar maple, beech, oaks, hemlock, basswood, elm.

In 1880 the standing hemlock was estimated to be seven billion feet b. m., carrying seven million cords of bark.

The maple sugar industry is important, Michigan ranking third in 1880.

4. Forest ownership: The State claims 3,000,000 acres of so-called tax homesteads, which are held for sale to ignorant immigrants.

320 lumber firms own 2,750,000 acres stocked with 5,300 feet b. m., on an average.

In the southern section wood lots are usually owned by farmers.

5. Use of timber: From 1862 to 1887 the State produced \$870,000,000 worth of white pine. In 1880, Sargent reports for white pine a growing stock of 35,000,000 feet b. m., whilst Fernow, in 1896, estimates it at 6,000,000 feet b. m. (underestimate). Another five years will, probably, bring about the end of the white pine in Michigan.

In lumber production Michigan has recently lost its leadership, held since 1870, to Wisconsin. The value of the saw mill products was in

1850	\$ 2,500,000
1860	7,000,000
1870	32,000,000
1880	52,000,000
1890	83,000,000
1900	54,000,000

FOREST POLICY.

The cut of 1900 consisted of:—

White pine	1,300,000,000 feet b. m.
Hemlock	850,000,000 feet b. m.
Cedar	370,000,000 feet b. m.
Other conifers	110,000,000 feet b. m.
Ash	86,000,000 feet b. m.
Basswood	46,000,000 feet b. m.
Elm	110,000,000 feet b. m.
Maple	400,000,000 feet b. m.
White oak	135,000,000 feet b. m.
Other hardwoods...	52,000,000 feet b. m.

Logs are worth on the stump \$3.06; at mill, \$7.60.

1,613 mills of \$20,900 average investment are reported. Michigan still leads the United States in the value of miscellaneous forest products (furniture, wagon, agricultural, cooperage and flooring stock), the output being \$6,700,000.

In the shingle production, worth \$3,200,000, it is second only to Washington. The splendid railroad systems developed in the past now facilitate the logging of hardwoods. A State census of 1884 estimates the cord wood consumption at 5½ million cords annually, worth 8.9 million dollars.

Paper industry uses 12,300 cords of home-grown spruce and 83,000 cords of Canadian spruce. Total value of product is \$4,200,000, for 1900.

Leather industry consumes in census year, in 27 tanneries, 62,000 cords of hemlock bark, valued at \$498,000; 1,000 cords of oak bark, valued at \$8,800; 3,700 barrels of hemlock bark extract, worth \$45,000, and 13,500 barrels of oak bark extract, worth \$124,000.

6. Forestry movement: The impediments to conservative forestry are: Agricultural qualities of white pine soil, excessive taxation, total lack of means to check fires, difficulty of conservative lumbering in scattering holdings of virgin woods subject to wind fall.

In 1875 a forestry commission was created, dying after two years of existence.

In 1887 the State Board of Agriculture was constituted as a "Forestry Commission." Forestal agitation is lead by Senator C. W. Garfield, assisted by the university, the agricultural college, farmers' institutes and women's clubs.

FOREST POLICY.

In 1899 the "Forestry Commission" (appropriation \$2,000 annually) was revived as a commission of inquiry and legislative advice. It consists of three scientific members, but no lumbermen. Allowance \$2,000 a year, to be spent for gathering statistics. A department of forestry was established in 1901 at the State University (now under Dr. F. Roth), and 57,000 acres of land forfeited for non-payment of taxes were turned over to the commission to be worked for two years. In lieu of these 57,000 acres a recent law has turned over to the commission all State holdings in three townships at the head waters of the Muskegon River. By the aid of a continuous appropriation of \$7,500 a year, the commission is gradually acquiring the contiguous lands, so as to make these reserve holdings more solid. The attempt of reserving all land forfeited for non-payment of taxes (and of a protective character) for State reserves failed in 1901.

7. Laws: Fire laws since 1817. Not enforced. Loss from fires reported by Sargent is \$1,000,000 in 1880.

8. Reservations: Now 64,000 acres at the head of the Muskegon River.

9. Irrigation: None.

FORESTRY CONDITIONS OF MINNESOTA:

1. Area: Woodlands, inclusive of stump land, cover 52,000 square miles, an area equal to 66% of the State. Stand of white pine after Sargent, in 1880, eight billion feet b. m.; after Gen. C. C. Andrews, in 1895, seventeen billion feet b. m.; after Horace B. Ayres, in 1900, twelve billion feet b. m.

2. Physiography: Undulating. 10,000 lakes and lakelets, the largest being Red Lake, Leech Lake and Millelac Lake. A multitude of swamps increase in size and number towards the north. Hills are rare. The Rainy River and Rainy Lake form the boundary line towards Ontario; the St. Louis River empties at Duluth; the St. Croix River runs on the Wisconsin line; the Red River on the Dakota line; the Mississippi starts in Lake Itasca and is navigable from Minneapolis southward.

3. Distribution: Two-fifths of the State is prairie, adjoining the Dakota and Iowa lines; another fifth, next to prairie, shows hardwoods prevailing over the softwoods; the remaining two-fifths is pine land and swamp land.

FOREST POLICY.

The northwestern pine belt of the United States reaches its western limit in Minnesota. The species prevailing in the hardwood belt are black oaks, sugar maple, birches and cottonwood. In the pine belt, white pine, Norway and jack pine are found, according to the soil. The poorer the soil, the more jack pine. White pine occurs, usually, with an undergrowth of linden, maple and hazel. In the swamps, black spruce, balsam, white spruce, white cedar and tamarack. On the wind-swept side of lakes, conifers are missing. No hemlock is found, a fact denied by H. B. Ayres. Birches and poplars occupy cut-over white pine land and secure, acting as nurses or ushers, if fire is kept out, a gradual recurrence of white pines. White pine underneath white pine is never found, whilst Norway pine immediately replaces Norway pine, and whilst jack pine invariably follows in jack pine's wake.

4. Forest ownership: 85 lumber firms own 2,025,000 acres of 3,900 feet average stumpage per acre. State owns between 2 and 3 million acres of land forfeited for non-payment of taxes. The United States own enormous tracts still. 30 townships remain unsurveyed north of the continental divide. Large Indian reserves.

5. Use of timber: The value of the products of the lumber industry in Minnesota gives it third rank as a lumber producing State. Minnesota came slowly to the front, having in 1880 an output of \$7,400,000; in 1890, \$25,000,000, and in 1900, \$43,600,000.

The cut in 1900 consisted of:—

White pine	2,250,000,000 feet b. m.
Norway pine	108,000,000 feet b. m.
Other conifers	20,000,000 feet b. m.
Spruce	1,000,000 feet b. m.
Hardwoods	62,000,000 feet b. m.

Total

2,441,000,000 feet b. m.

The miscellaneous industries (furniture, cooperage, wagon stock, flooring, spools, etc.) yielded, in 1900, only \$1,300,000. White pine and hardwoods in Minnesota are, on the average, inferior to white pine and hardwoods in Wisconsin and Michigan.

404 saw mills of \$60,848 average investment (maximum investment, by far, of United States). Logging by rail is taking the place of log driving, on which the mills of Minneapolis used

FOREST POLICY.

to depend. Skidding by horses during the winter months forms the rule. Sleighing over ice roads to the lakes or rivers. Wages of workmen about \$28 (with full board) per month. Large amount of timber consumed by the iron mines of northeastern Minnesota. Logs are worth \$3.40 on stump, and \$8.09 at mill.

The leather industry is small, hemlock lacking. Nine tanneries use 107 cords of bark, 37 barrels of extract and a little gambier and quebracho.

Relative to paper and pulp industry, no data are given by the 12th census. Possibilities are very good, since there is plenty of spruce. Big Weyerhaeuser mill near Duluth.

6. Forestry movement: Since 1876 a forestry association encourages prairie planting. Bounties for prairie planting since 1891. Arbor Day since 1883-1884. The Hinckley fire, of September 1, 1894, through which a large number of lives and many millions of dollars worth of stumpage were lost, caused the creation of a forest fire warden system, effective enough to prevent a second Hinckley conflagration, but insufficient for the absolute safety of forestal investments. The legislators hailing from the prairies antagonize outlays benefitting the wooded portion of the State. The State auditor is "forest commissioner."

Town supervisors and the mayors of cities are constituted fire wardens and are fined for neglect of duty. Remuneration only \$2 per day for not to exceed 15 days annually (two-thirds paid by county and one-third by State). The chief fire warden (\$1,200 salary) is appointed by the State auditor; he maintains and superintends the activity of the fire wardens; has authority to mass them at points of danger; controls an emergency fund of \$5,000 for suppression of fires. Annual forest statistical reports of great value, by General C. C. Andrews.

Forestry lectures by Prof. S. B. Green at the Minnesota State College of Agriculture.

The proposition to establish a national park at the Chippewa Indian reserve ceded to the United States was enthusiastically upheld by the Minnesota Federation of Women's Clubs and by the railroads. The influence of the lumbermen caused partial defeat of the park bill. As the law stands, the agricultural lands of the Chippewa reserve are to be opened to settlers; the pine lands, after the timber is sold at public auction, will form (without the President's proclamation) a national forest reserve. 5%

FOREST POLICY.

of the timber, however, will be left according to the selection of the Bureau of Forestry.

The friends of forestry now endeavor to obtain a national park in the northeast, close to Lake Superior.

7. Laws: "Staples bill" forbids the removal of timber previous to payment of back taxes.

"Cross bill," of 1899, makes State forestry feasible on land either donated by lumbermen or set aside by the State for reserve purposes. Practically no appropriation and practically no donations. Companies are forbidden to own over 5,000 acres of land. Fire warden law, see under "forestry movement."

8. Reservations: The Lake Itasca State forest reserve is insignificant.

The Chippewa or "Minnesota National" forest reserve will be gradually established after timber is sold, and is expected to finally comprise 225,000 acres.

9. Irrigation: None.

FORESTRY CONDITIONS OF MISSISSIPPI:

1. Area: Area of woodlands, 32,300 square miles, or 70%.

2. Physiography: Alluvial and diluvial soil. Huge bottoms between Mississippi and Yazoo Rivers. The Pearl River on the Louisiana line. The Tombigby River drains the northeastern part.

3. Distribution: Originally the forest was half pine and half hardwood. Long leaf pine prevails in the south, extending northward to the latitude of Vicksburg and Meridian, on sandy soil, especially on former dunes. A belt along the Mississippi, some 30 miles wide, is free from long leaf pine. Cuban pine, with the long leaf, up to 60 miles from the coast, occupies moist soil, on which it regenerates freely. It is not found west of the Pearl River. Echinata is not found close to the coast, beginning where Cuban pine ends. It often appears mixed with long leaf and taeda pine, and prevails on the divide separating the Tombigby from the Yazoo Rivers on 5,000 square miles. Trees are more scattering than in Texas and Arkansas, the hardwoods taking a larger share in the composition of the forest. Taeda occurs everywhere east of the Yazoo, from the coast up to the Tennessee line, under the name of short straw pine, lob-

FOREST POLICY.

lolly, swamp, slash and rosemary pine. It occupies moister and more loamy soil, and is often found in inundation districts. The undergrowth or suite consists of black and sweet gum, red oak and magnolia on wet soil; of hickories, Spanish oak and black jack on drier soil. Spruce pine (glabra) occurs in small clumps on rich, terraced soil. Cypress fills huge swamps along the Mississippi and Yazoo Rivers. White cedar occurs, with taeda, in half-swamps.

In the bottom lands are found cottonwood, both gums, white oak, cow oak (prevailing); Texan oak, water oak (nigra), magnolia and beech. Further, walnut, shagbark hickory, yellow poplar, sycamore, mulberry, elm and holly. Burr oak and red oak are here wanting. Overcup oak (lyrata) occurs under the name "swamp oak."

4. Forest ownership: 349 firms own 1,214,000 acres, stocked with 7,600 feet b. m. per acre. The United States, the State and railroads, notably the Mobile and Ohio, own large tracts. The balance is owned by farmers.

5. Use of timber: In the census year, 820 mills of \$9,400 average investment. In 1900, log value on stump, \$1.30; at mill, \$4.60. The output of the saw mills was valued in

1880 at	\$ 1,900,000
1890 at	5,700,000
1900 at	15,600,000

The cut in the census year consists of

Yellow pine	964,000,000 feet b. m.
Other conifers	37,000,000 feet b. m.
Cottonwood	39,000,000 feet b. m.
Red gum	23,000,000 feet b. m.
White oak	102,000,000 feet b. m.
Other hardwoods ...	42,000,000 feet b. m.

Total.....1,207,000,000 feet b. m.

Hardwood logging is very expensive; yellow pine logging, with four yoke of oxen hitched to a high-wheel cart, is very cheap. The average logging distance, for pine, slightly exceeds one-third of a mile. Expense of logging (cutting and hauling), \$1.25; of railroading, 50 cents per 1,000 feet b. m.

FOREST POLICY.

Railroad grades are fearful. Minimum log diameter of long leaf pine admitted is 10 inches. Average log size about 220 feet b. m.

Turpentine industry is now tapping the pole-woods as well as the tree-woods. Lumbermen box two or three years before cutting. *Echinata* and *heterophylla* as well as *palustris* are boxed.

Leather industry: Insignificant.

Paper and pulp industry: None.

6. Forestry movement: None.

7. Laws: Firing on vacant land is allowed only during the three spring months. On appropriated land, malicious firing only is prohibited.

8. Reservations: None.

9. Irrigation: In 1899, 40 acres were irrigated; 30 acres in rice and 10 in truck.

FORESTRY CONDITIONS OF MISSOURI:

1. Area: 41,000 square miles, equal to 60% of the area of the State, are classed as woodlands.

2. Physiography: The Mississippi River forms the eastern line; the Missouri River traverses the State from west to east. Undulating plains. Highest mountains are the Ozarks, from 800 feet to 1,000 feet high.

3. Distribution: The northwestern portion is prairie, with the usual forest groves along the rivers. The south-southeastern part exhibits short leaf pine (*echinata*) on the hills, notably on the Ozarks, alternating with stretches of post oak barrens. The undergrowth underneath pine is formed by oaks (scarlet, black, post, white), hickories and black gum. Altogether, 3,000,000 acres of pine are said to be found, the average stumpage being only 2,000 feet b. m. (after Mohr, often 3,000 to 4,000 feet b. m.). The lower dells of the east, south of the Missouri, show splendid broad leaf forests, where oak, walnut and ash, of prime quality, are still found away from the railroads. In the deep swamps of the southeast, cypress and tupelo gum prevail. In shallow water, swamp maple, swamp plane tree, swamp white ash and water honey locust occur. In the damp woods, gigantic cottonwoods, burr oaks, gums and cypresses. Here, perhaps, is

FOREST POLICY.

the best remaining supply for white hickory. Gigantic Texan oak, sweet gum, willow, water and scarlet oak are also met.

4. Forest ownership: In south, much forest owned by speculators. 274 lumber firms control 869,545 acres, of 5,500 feet b. m. average stumpage. Farmers own two-thirds of woodlands. State owns 500,000 acres.

5. Use of timber: 1,169 (!) mills, with an average investment of \$5,336, beset the forests. Large cooperage concerns using cottonwood, elm and oak. White oak cut for railroad ties and bridge timber. Stumpage price averages \$1.89. Logs at mill worth \$6.91.

Leather industry uses 774 cords of hemlock bark, 2,936 cords of oak bark and 869 barrels of bark extract. Output of industry, \$816,000.

The cut of the census year was:—

White oak	250,000,000 feet b. m.
Pine	269,000,000 feet b. m.
Cypress	10,000,000 feet b. m.
Cottonwoods	76,000,000 feet b. m.
Elm	28,000,000 feet b. m.
Red gum	51,000,000 feet b. m.
Other hardwoods	35,000,000 feet b. m.

No paper and pulp industry. Value of saw mill products rose from 6.3 million dollars, in 1870, to 11.2 million dollars in 1900.

Hardwood bottoms are invariably thought to be convertible into excellent farm lands.

6. Forestry movement: Arbor Day established in 1886. Forestry lectures at State Agricultural College. Residents seem to vie with one another to steal the timber belonging to non-residents.

7. Laws: Fire fines up to \$500. No inclination of jurors to punish timber theft and incendiarism.

8. Reservations: None.

9. Irrigation: No data available.

FORESTRY CONDITIONS OF MONTANA:

1. Area: 42,000 square miles, or 29% of State, is wooded.

2. Physiography: The 109th meridian divides Montana in half. The eastern half consists of high plains fit for pasture

FOREST POLICY.

only, traversed by the Missouri and Yellowstone Rivers, the courses of which are cut 600 to 900 feet deep into the plateau. This eastern half contains, practically, no forests.

The western half contains barren land only in the extreme north (Maria River Basin). Three main mountain chains may be distinguished in the western half.

(1) The Coeur d'Alene and Bitter Root Mountains on the Idaho line. Water runs towards the Pacific from both slopes via Columbia River.

(2) The main Rockies, lying between the Flat Head Basin and the Missouri River, which drain westward on the west slope and eastward on the east slope.

(3) The northern extension of the Yellowstone Range extending northward to the center of the State. Water runs from both slopes entirely towards the Atlantic, via the Yellowstone and Missouri Rivers.

All these mountains are less rugged and by 3,000 feet lower than those in Colorado and Wyoming.

3. Distribution: The best forests of Montana and of the entire Rockies are found in the chain of the Coeur d'Alene and Bitter Root Mountains. On the mountain chain forming the crest of the continent the forests are equal to the best of those in Wyoming. On the third mountain range, draining solely eastward, the forests are equal to those of the Yellowstone region.

The western cedar (*plicata*) is scarce and small. It is found in best valley soil only at low elevations. Lowland fir and Engelmann's spruce occur in moist bottoms associated with Douglas fir. Lodgepole pine forms very extensive forests at medium altitudes. Limber white pine and balsam (*lasiocarpa*) are found in great bodies, especially on the eastern drainage; larch, white pine (*monticola*) and hemlock prevail on mountains draining towards the west. Along the rivers, cottonwoods and box elders occur. Quaking aspen replaces the conifers after heavy burnings on north slopes.

4. Forest ownership: Lumbermen own very small tracts only, since taxes are high. Indian reservations and railroad grants cover large tracts. (Northern Pacific and Great Northern Railroads.) The forest reserves cover about 7,500,000 acres. Over one-fifth of Montana still belongs to the United States.

5. Use: The mining interests of Montana stand paramount. Montana is second in the production of gold and silver,

FOREST POLICY.

and first, by far, in the production of copper, amongst the States of the Union.

Next in importance are the livestock interests. The stock consists of:—

1,000,000 cattle.

2,800,000 sheep.

200,000 horses.

The forest is meant to subserve the mines, supplying props, fuel and ties; and agriculture, supplying water for irrigation purposes. To the west are the large plains of Washington. To the east those of the Dakotas and Montana, which can be irrigated only, it is claimed, by using water coming from the Montana Mountains. Log stumpage is worth \$1.18 on an average, and logs at mill \$4.11. Mill investments average \$13,475. 38 lumber firms control about 600,000,000 feet stumpage, said to average 6,600 feet per acre.

Mill products were worth in

1870	\$ 430,000
1880	527,000
1890	1,182,000
1900	almost 3,000,000

In 1900 the cut of timber was 257,000,000 feet b. m., three-fifths of which was yellow pine, the balance consisting mainly of red fir and tamarack.

The destruction by fire is said to be beyond belief.

6. Forestry movement: Numerous petitions to Congress led to the establishment of the central reserves. Geo. P. Ahern delivered lectures on forestry at the Montana College of Agriculture, at Bozeman, for a number of years.

7. Laws: Penalty for wilful or careless firing. County commission required to keep fire laws posted. Tax rebate on forestry plantations.

8. Reservations: Only 690,000 acres of the Bitter Root reserve lie in Montana. The Flathead forest reserve, comprising 1,382,400 acres, and the Lewis and Clarke forest reserve, comprising 2,926,080 acres, both lying on the crest of the Rockies, have been recently combined into one reserve under the name of the latter. At the same time, the reserved acreage was increased, making the new "Lewis and Clarke forest reserve" 4,670,270 acres.

FOREST POLICY.

The Gallatin forest reserve of only 40,320 acres, near Bozeman, is unimportant.

The Madison forest reserve (736,000 acres), bordering the Yellowstone Park, and the Little Belt Mountain forest reserve (501,000 acres), both established in 1902, seem important for irrigation at the head of the Missouri and Yellowstone Rivers. On the Lewis and Clarke forest reserve, western larch is by far the prevailing species, having twice the stumpage of Douglas fir and five times the stumpage of yellow pine. In the same reserve there seems to be more spruce than either yellow pine or lodgepole pine. The Canadian larch and spruce are sentinels of the British Columbia forest flora.

The Absaroka forest reserve of 1,311,600 acres, recently established, lies north of the Yellowstone Park. It has been consolidated with the Yellowstone and Teton reserves by Presidential proclamation.

9. Irrigation: Montana is third in irrigation, 950,000 acres being irrigated. Irrigation practicable only near the mountains at the present moment. Irrigation necessary for the cultivation of crops, notably barley.

The canal of the Minnesota and Montana Irrigation Company in Yellowstone County is 40 miles long, with an average width of 35 feet and a depth of 5 feet. Another canal in Chateau County is 75 miles long.

The great eastern plains, with very rich soil, are almost unsettled, owing to the difficulty of irrigation. The best farms are found in the Gallatin Valley, near Bozeman, and along the Yellowstone River.

Winter forage is required for the development of the rapidly increasing livestock interests.

In 1889, 950,000 acres of irrigated farm land produced \$7,300,000 worth of crops from irrigation works constructed at an expense of \$4,700,000.

FORESTRY CONDITIONS OF NEBRASKA:

1. Area: 2,300 square miles, or 3% of the area of the State, are wooded.

2. Physiography: Prairie traversed by the Platte River midway from west to east. The Niobrara flows along the north-

FOREST POLICY.

ern boundary line; the Missouri forms the eastern boundary line towards Iowa.

One quarter of the State north of the Platte River is occupied by the "Sand Hills," which are not sand dunes, but give rise to springs and offer pasture.

3. Distribution: In the broad Missouri Valley of the extreme east were once found splendid groves of hardwoods, notably of burr oak, walnut, ash, box elder, honey locust and Kentucky coffee tree. The canyons of the rivers coming from the west show cottonwoods, willows and red cedar. Further west, some yellow pine, quaking aspen, cottonwoods and birches occur. Yellow pine covers several narrow ridges 5,000 feet high near the Wyoming line. Red cedar is found sparingly everywhere, the original growth being cut away for fence posts.

In the Sand Hills, logs and stumps of yellow pine are found buried in the sand. After Dr. C. E. Bessey, pine groves (ponderosa) were found 50 years ago even in the eastern half of the State. About 300,000 acres (?) of forest plantations are now in existence. Honey locust, cottonwood and green ash are said to do best. The European pines are reported thrifty.

4. Forest ownership: The federal government still owns the Sand Hills. 321,000 acres of forest along the rivers are attached to farms.

5. Use of timber: The hardwoods of the Missouri bottoms are practically used up. In 1880 there were 38 firms producing annually 14,000,000 feet of cottonwood and burr oak lumber. In 1900, 23 mills, of \$1,900 average investment, were in existence. Output in 1900 is not given. Stumpage is worth \$2.29 per thousand, and logs at mill bring \$5.69.

Firewood and fence posts are the leading requisites.

Leather and pulp industry: None.

6. Forestry movement: John Sterling Morton, Cleveland's Secretary of Agriculture, was the soul of a vigorous movement in favor of prairie forest planting. He introduced Arbor Day.

A State agricultural society offers three premia to the largest tree planters.

The "Nebraska Park and Forest Association," founded in 1899, tries to influence the newspapers.

Instruction in forestry at the University of Nebraska by Dr. C. E. Bessey.

FOREST POLICY.

7. Laws: Tax exemption laws of 1869 were found unconstitutional. Towns are required by law to plant trees and authorized to levy taxes for that purpose. There are the usual fire laws.

8. Reservations: The Dismal River forest reserve (85,123 acres) and the Niobrara forest reserve (123,779 acres) are to be planted up, by the federal government, in yellow pine, jack pine and red cedar.

9. Irrigation: 148,000 acres of irrigated farm land have produced, in the census year, \$983,000 worth of crops, helped by irrigation works costing \$1,000,000.

FORESTRY CONDITIONS OF NEVADA:

1. Area: Under forest is 200,000 acres, or 0.3% of the State. Wooded area, after census of 1900, is 3,904,000 acres, or 6% of the State.

2. Physiography: In the western part, the east slope of the Sierras, with Virginia City and Carson City. Scarcely any water leaves the State. In the central part, narrow mountain ranges run north and south, and rise to over 8,000 feet altitude.

3. Distribution: Stunted junipers, and above these mountain mahogany (*Cercocarpus ledifolius*) skirt the barren land. Higher up, slopes dotted with nut pine, and still higher with yellow pine (*Jeffreyi* and *ponderosa*). The limber white pine is said to form extensive forests at elevations from 7,000 to 10,000 feet.

4. Forest ownership: Mines and railroads own little. The United States own practically all of Nevada. The State obtained from Congress a grant of 2,000,000 acres, to be located as the State pleased, in place of the usual school sections 16 and 36. The State sold the 2,000,000 acres rapidly in large tracts along all water courses at \$1.25 per acre to cattle men.

5. Use: Mining timber is paramount. Limber pine, yellow pine and red fir (*magnifica*) are used for props. The timber works of the Comstock mines are said to be of marvelous construction. Since 1870, \$55,000,000 worth of timber is said to have been buried in the mines. Nut pines, mountain mahogany and juniper are used for fuel and charcoal. Lumber is worth \$23 per thousand; mine props, \$10 per cord.

FOREST POLICY.

6. Forestry movement: Nil.

7. Laws: None.

8. Reservations: None.

9. Irrigation: A State irrigation law of 1903 declares all water courses public property and fixes maximum use of water per acre of irrigated land.

The development of the State depends on the possibility of constructing reservoirs (notably on Humboldt River) and on the chances of artesian wells.

The existing irrigation works, costing \$1,500,000, irrigate 500,000 acres of land and produced, in 1899, \$2,800,000 worth of products.

FORESTRY CONDITIONS OF NEW HAMPSHIRE:

1. Area: 5,200 square miles, or 58% of the State, are wooded.

2. Physiography: Northern section of the State is mountainous, containing the headwaters of the Androscoggin, Merri-mac and Connecticut Rivers ("the Switzerland of America"). Mount Washington, in the Presidential Range of the White Mountains, is 6,290 feet high. Southern section of the State is hilly, with some peaks over 3,000 feet high. Many summer tourists attracted.

3. Distribution: The growing stock was and is formed of white pine, hemlock, spruce, balsam and cedar, mixed with sugar maple, birch, beech; further, chestnut, ash, basswood and oak. After Fernow, hardwoods with spruce prevail in the northern section; pine and hemlock in the southern section. In 1900 the lumbermen alone owned 3,800,000,000 feet b. m. of stumpage, 2,000,000,000 feet of which are spruce. Large areas stock themselves with white pine after lumbering. Since 1850, 1,750,000 acres of improved farm land have reverted to unimproved land, most of which is coming up in white pine.

4. Forest ownership: 159 lumber firms own 664,000 acres of forest, 43% of the woodlands are attached to farms. Paper companies and speculators own very large tracts.

5. Use of timber: The forest has been culled for decades of years—to begin with, of prime white pine only. Fires used

FOREST POLICY.

to be severe. The stand of virgin spruce often averages 20,000 feet b. m. per acre on large tracts. Logging by water or by rail. Some firms begin to survey the sleigh roads with great care. Stumpage costs \$2.68; logs at mill cost \$6.96 per 1,000 feet b. m. The State contains 535 saw mills, of \$10,200 average investment.

The output of the saw mills was valued in

1850	\$1,100,000
1860	1,200,000
1870	4,300,000
1880	3,800,000
1890	5,600,000
1900	9,200,000

The cut of 1900 consisted of

Spruce	188,000,000 feet b. m.
White pine	310,000,000 feet b. m.
Hemlock	45,000,000 feet b. m.
Other conifers	2,000,000 feet b. m.
Hardwoods	23,000,000 feet b. m.

The miscellaneous mill stock produced in 1900 was worth \$875,000. Hoop poles, excelsior, shoe pegs and maple sugar are produced in large quantities.

Leather industry: 12 tanneries report an annual output of \$2,265,000 of leather and a consumption of 5,700 cords of hemlock bark, worth \$25,400; 712 bales of gambier, worth \$4,600; 40 barrels of bark extract, worth \$480, and of chemicals, worth \$6,400.

Paper and pulp industry: 29 firms produce an output worth \$7,200,000. The raw material consists of domestic spruce, 109,000 cords, worth \$655,000; Canadian spruce, 87,000 cords, worth \$479,000; other wood, 720 cords, worth \$3,430.

6. Forestry movement: A Forest Commission, appointed in 1881, submitted a good report in 1885. Lectures on forestry are offered at the State Agricultural College. The inhabitants are not inclined to check forest fires.

The "White Mountain State Park" movement, in 1892, failed to be successful.

A bill of 1901, intended to limit the cutting of conifers to trees of over 10 inches stump diameter, failed to become a law.

FOREST POLICY.

The "Society for the Protection of the New Hampshire Forests" employs a forester (Philip W. Ayres) and intends to work the park scheme through Congress. Its propaganda, based on merely economic grounds, is most commendable.

7. Laws: A law of 1893 establishes a forestry commission, consisting of the governor and four members appointed by him. The member acting as secretary draws a salary of \$1,000. Duties of commission are:—

- (a) Gathering forest, lumber and fire statistics.
- (b) Forestry propaganda at public meetings.
- (c) Suggesting legislation in annual reports.
- (d) Appointment (since 1895) of special fire wardens upon

application by forest owners, applicant and county equally sharing the expense of the service.

In organized towns, the selectmen are fire wardens *ex officio*, paid by the town.

Where no town organization exists, the county commissioners are empowered to appoint fire wardens serving at the county's expense.

Fire laws are unenforced.

A law of 1903 provides \$5,000 for the examination, by the National Bureau of Forestry, of the White Mountain forests. A joint resolution of the Legislature authorizes the federal government to establish, by expropriation or otherwise, a national forest reserve in the White Mountains.

- 8. Reservations: None.
- 9. Irrigation: None.

FORESTRY CONDITIONS OF NEW JERSEY:

1. Area: The woodlands cover 3,234 square miles, or 43% of State. The forest area is said to be increasing.

2. Physiography: The Delaware River and the Delaware Bay on the west side; Hudson River, Raritan Bay and Ocean on the east side. Shipping facilities and sea climate supply New Jersey with economic and forestal conditions similar to those of England. A belt 12 miles wide, stretching along a line running

FOREST POLICY.

from Wilmington, Del., to Hoboken, is covered by cretaceous clays and marls. North of this belt lies the mountain zone of New Jersey, formed of red sandstone with trap outcrops, replaced further north by gneiss and granite highlands and yielding, in the extreme north, to the limestone and slate formations of the Kittatinney Mountains.

South of the cretaceous belt lie "The Pines," a slightly rolling plain, with gravelly and sandy soil of post-tertiary origin.

3. Distribution: All timber is second or third growth. In the clay and marl belt, chestnut coppice prevails in small wood lots attached to farms; growth thrifty, protected by farmers. *Pinus virginiana* and *echinata* are found, with little *rigida*.

In the highlands and mountains of the north, the farm lots in the valleys are well stocked with hardwoods, especially chestnut. In the Kittatinney Mountains, conifers, especially *Pinus rigida*, are mixed with hardwoods. Slopes and ridges are invariably in woods. In the mountains, tracts are large and hence more frequented by fires and trespassers.

In "The Pines," pure pitch pine forests of a stunted growth prevail on pure sand, the trees formed by stool-shoots after fires. On better soil, black oak and black jack oak are mixed with pitch pine. On wet soil dense stands of white cedar occur, or hardwood swamps, stocked with sweet and black gum, maple and yellow poplar.

The trap rock ridges, breaking through the red sandstone, show a stunted coppice growth of poor oak, chestnut and red cedar.

The woodlands of the northern highlands and those of "The Pines" may be of indirect importance by shielding the water supply for a growing population.

A colony of Russian Jews practice osier culture for basket-making.

4. Forest ownership: 47 mill firms own 7,576 acres of forest, reported to contain 3,600 feet b. m. average stumpage. The balance of woodlands belongs to farmers and to owners of small private reserves.

5. Use of timber: The iron industry in "The Pines," during the 18th century, drew heavily upon the virgin forest for charcoal. In 1850 the whole State was already cut over.

FOREST POLICY.

The output of the saw mills was valued in

1850	\$1,123,000
1860	1,608,000
1870	2,745,000
1880	1,627,000
1890	1,225,000
1900	1,859,000

The cut in 1900 consisted of:—

Yellow pine	27,000,000 feet b. m.
White cedar	10,000,000 feet b. m.
Other conifers	4,000,000 feet b. m.
Chestnut	10,000,000 feet b. m.
Oak	19,000,000 feet b. m.
Other hardwoods ...	3,000,000 feet b. m.

Total 73,000,000 feet b. m.

Logs on stump are worth \$3.93; at mill, \$7.56. 197 saw mills exist, of \$4,357 average investment. The miscellaneous wood industries furnish only \$157,000 worth of stock. The consumption of forest products, other than lumber, is said to consist of 800,000 cords of wood for fuel, 1,250,000 railroad ties; 14,000 telegraph and trolley poles and \$365,000 worth of fencing. The usual rotation in coppice woods and pineries is from 35 to 50 years.

Leather industry: 77 tanneries produce \$13,700,000 worth of leather and consume 4,016 cords of hemlock bark, worth \$39,600; 15,150 cords of oak bark, worth \$170,830. In addition, large amounts of gambier, quebracho, sumac and chemicals are used for tanning.

The paper and pulp industry works in 34 plants, producing \$3,200,000 worth of paper. No cord wood, however, is used. The raw material consists of rags, straw, pulp and fiber obtained from outside the State.

6. Forestry movement: Public opinion is well aware of the benefits derivable from a sound forest policy. Forestry bills are continuously introduced and continuously fail of passage.

The Geological Survey of New Jersey, since 1885, deals with the forest problem, and, under a law of 1894, has issued, in 1899, a very good report on the forests of the State. No action

FOREST POLICY.

was taken upon it. A State Forestry Association seems to have died. The splendid public road law of New Jersey should greatly facilitate conservative forestry. What New Jersey needs is an enthusiastic and unselfish leader of propaganda for forestry.

7. Laws: Since 1792, county officials act as fire wardens and are privileged to summon help. Railroads are responsible for damages caused by spark fires, and locomotives must be supplied with spark arrestors. The "Minch bill," of 1902, providing salaried fire marshals, seems to have failed. Arbor Day since 1884.

8. Reservations: None, except small private reserves.

9. Irrigation: Only on 73 acres producing hay, vegetables and corn.

FORESTRY CONDITIONS OF NEW MEXICO:

1. Area: 23,700 square miles, equal to 19% of total area of Territory, are wooded.

2. Physiography: Rocky Mountains traverse Territory from north to south. Average elevation of Rockies, north of Santa Fe, 10,500 feet. Drainage chiefly towards the Gulf of Mexico, via the Rio Grande from the west slope of the Rockies, and via Pecos and Canadian River from the east slope of the Rockies. River beds sunken 200 feet into the table lands. Rainfall averages less than one inch per month, except in the higher altitudes. Mean altitude of the whole territory is about 5,600 feet.

3. Distribution: Arid plains east of the Pecos River (Llano Estacado), with some mesquit. In the southwest, narrow mountain ranges separate wide plains on which Madrona, Spanish Bayonet and Palo Verde grow. "Journanda del Morte," along the Mexican frontier, is said to be the worst of all deserts. The mesas show scattering scrub oak with groups of red cedar, western juniper and pinon. In the depressions of the mesas occur fine groves of mesquit. Splendid grazing on the mesas. Along the rivers appear fringes of box elders, willows and cottonwoods. The mountain ranges show, at the highest elevations, a cupressus species forming dense forests (probably *Arizonica*); lower down, on the north slopes, white pine (*flexilis*), Douglas fir and Engelmann's spruce, which are replaced, after heavy cuttings and burnings, by quaking aspen. On south slopes

FOREST POLICY.

yellow pine preponderates in open forests (ponderosa). The foothills show juniper, cedar, pinon, scrub oak. The best forests are in the central north and in the southwest, where the diagonal mountain chain traversing Arizona enters the territory.

4. Forest ownership: Lumbermen own 1,518,000 acres. Attached to farms are 10% of the forests. The railroads and mines are said to control large tracts. Reservations cover 3,258,080 acres, equal to 4% of the territorial area.

5. Use: Forests are mostly used for pasture, especially in the yellow pine region. In the foothills' forests, yellow pine is the most valuable timber. Cedar and juniper are used for fence posts. Scrub oaks and pinion are used for fuel. In the census year the cut was 203,000 feet b. m. of Engelmann's spruce and Douglas spruce, and 31,637,000 feet. b. m. of yellow pine, averaging 1,700 feet b. m. to the acre. Merchantable timber is found only on the higher mountains. Mill investments average \$5,200. Lumbermen control 1,000,000,000 feet b. m. of spruce and 1,300,000,000 feet of yellow pine. No pulp or leather industries. Stock raising stands paramount. Fires are said to do little damage, excepting north of Santa Fe.

6. Forestry movement: None.

7. Laws: Usual fire laws. Liability for all damages. Denver and Rio Grande railroad is the only road privileged to cut timber for repairs from government land.

8. Reservations: The Pecos River reserve, of 431,000 acres, lies northeast of Santa Fe and comprises the sources of the Canadian and Pecos Rivers.

The Gila River forest reserve is large (2,327,040 acres) and compact and drains, through the Rio Grande, westward into the Pacific. In July, 1902, the Lincoln forest reserve of 500,000 acres was created in the central south of the Territory.

9. Irrigation: 88,900 acres. Agriculture possible only in the cañons of the main rivers, depending on irrigation.

The Aborigines have irrigated their farms from time immemorial on. Agricultural chances are best along the southern broad-bottomed course of the Rio Grande. Ditches, roughly constructed, are usually held in common by the Mexican inhabitants. The farms have the form of oblongs, the narrow side joining the river.

FOREST POLICY.

The largest reservoir is on the Pecos River, in the south-east of the State near Carlsbad.

The irrigation works existing in 1889 were constructed at an outlay of \$4,100,000 and irrigate 204,000 acres of farm land, producing \$2,800,000 worth of crops.

FORESTRY CONDITIONS OF NEW YORK:

1. Area: 18,700 square miles, or 39% of the State, are classed as woodlands.

2. Physiography: Whole State slightly mountainous. Western section more level. Catskills on west bank of Hudson; Adirondacks in extreme north, rising in Mount Marcy to an elevation of 5,345 feet (with gneiss and granite for underlying rock). A large number of inland lakes in north and west facilitate transportation.

3. Distribution: The western section is the farming section of the State. Originally the broad-leaved forest of the Mississippi Basin covered the entire State, excepting:—

(a) The Adirondacks, where maple, birch and beech prevail in irregular mixture with spruce, hemlock, white pine and red pine, the spruce forming pure stands on the poorest soil, whilst wet depressions are occupied by balsam, tamarack and white cedar.

(b) The low hills bordering the Hudson and extending westward along the Pennsylvania line, in which the coniferous species of the northern pine belt preponderate.

In 1900, the forests, with the exception of those in parts of the Adirondacks, consist of second growth. Many a so-called "virgin forest" of the Adirondacks has lost its stand of white pine for many a year.

4. Forest ownership: 276 firms own 648,000 acres, stocked with 5,600 feet b. m. per acre. The State reserves comprise 1,325,000 acres in the Adirondacks and 82,000 acres in the Catskills.

5. Use of timber: The stand of conifers in New York was estimated, by Sargent, in 1880, at 8.3 billion feet b. m., and by Fernow, in 1896, at 5.3 billion feet b. m.

FOREST POLICY.

The value of the output of the saw mills, since 1850, shows unexplainable fluctuations. It was in

1850	\$13,100,000
1860	9,700,000
1870	21,200,000
1880	14,300,000
1890	17,100,000
1900	15,800,000

New York stepped down gradually, as a lumber producing State, from first rank in 1850 to 12th rank in 1900.

The cut in 1900 consisted of:—

Hemlock	314,000,000 feet b. m.
Spruce	256,000,000 feet b. m.
White pine	122,000,000 feet b. m.
Other conifers	6,000,000 feet b. m.
Maple	51,000,000 feet b. m.
Oak	43,000,000 feet b. m.
Basswood	30,000,000 feet b. m.
Elm	16,000,000 feet b. m.
Chestnut	14,000,000 feet b. m.
Birch	13,000,000 feet b. m.
Ash	9,000,000 feet b. m.
Hickory	1,000,000 feet b. m.

Stumpage is worth \$3.12, and logs at mill are bought at \$7.75 on an average. 1,742 mills report an average investment of \$6,163. The shingle production is valued at \$342,000; the production of miscellaneous stock at \$1,101,000. In barrel and box manufacture, further, in the manufacture of baskets and woodenware, New York occupies first place amongst the States. 159 box factories turn out \$7,900,000; 413 barrel factories, \$6,500,000; 180 basket and woodenware factories, \$1,000,000.

The expense of logging in the Adirondacks averages \$4.50 per 1,000 feet b. m. Horses only are used in skidding and sleighing. Logs are driven down the rivers, frequently with the help of splash dams.

The average growing stock in primeval parts of the Adirondacks shows, per acre. 31.5 spruces, 4.5 hemlocks, 4 balsams, 0.2 white pines, 0.1 cedar, 14 birches, 10 beeches, 6 hard maples, 2.5 soft maples and a few ash and cherry, making a total stand of 73.4 trees of over 10-inch diameter per acre.

FOREST POLICY.

Leather industry: 147 tanneries yield annually \$23,200,000 worth of products and consume 179,000 cords of hemlock bark, worth \$1,200,000; 4,000 cords oak bark, worth \$33,000; 19,000 bales of gambier, worth \$123,000, 2,100 barrels of hemlock bark extract, worth \$25,000; 526 barrels of oak bark extract, worth \$5,500; 615 barrels of quebracho, worth \$9,500; 2,150 tons of sumac, worth \$104,000; and chemicals, worth \$330,000.

Paper and pulp industry: New York leads the United States, in the 12th census year, by producing \$26,700,000 worth of pulp and paper. 179 firms consume: Home-grown spruce, 363,000 cords, worth \$1,985,000; Canadian Spruce, 141,000 cords, worth \$945,000; domestic poplar 32,000 cords, worth \$181,000; Canadian poplar, 9,600 cords, worth \$57,000; other pulp wood, 9,500 cords, worth \$40,000. After Fernow, more spruce is now consumed for pulp than for lumber.

6. Forestry movement: New York, as late as 1884, was still the owner of some woodlands in the Adirondacks, and Catskills. The Adirondack Park Association stimulated further acquisitions by the State. The New York State college of forestry was expected to demonstrate the feasibility of practical forestry on 30,000 acres of experimental forest and to supply the State with scientific foresters.

7. Laws: Law of 1886 allows the State to pay taxes on her own land.

Law of 1889 provides penalty of \$25 for every tree cut or stolen from the State's land.

In 1897, the Adirondack Park law was enacted.

Since 1893, forest utilization in the Adirondack forest preserve is forbidden by a constitutional clause.

In 1895, the Forest Commission was combined with the Fish and Game Commission (See XXXI).

In 1900, the office of chief fire warden was created and the Commission authorized to employ three expert foresters to act as deputy fire wardens, attend reforestation, etc.

In 1901, the Forest, Fish and Game Commission was consolidated with the Forest Preserve Board. D. C. Middleton, of Watertown, is the forestry member of the Commission. Col. Wm. F. Fox is Forest Superintendent. The law makes it the duty of the Commission

(a) To take care of the State forest preserves.

(b) To promote "further growth" in the preserves.

FOREST POLICY.

(c) To husband the people's interests in forestry and tree planting, and especially with reference to forest fires. The law authorizes the Commission to employ a superintendent, an assistant superintendent, a land clerk, 12 "foresters and game protectors" and 35 "forest rangers," the latter drawing a salary of \$500 per annum.

Outside the State preserves the town supervisors act *ex officio* as "fire wardens," empowered to summon help (at \$2 per diem) and instructed to annually report to the Commission on the number, extent and cause of forest fires occurring in their respective precincts; further, on the remedial measures taken to fight fires. The town pays half of the fire warden's wages (\$2.50 per diem).

If the fire wardens neglect proper discharge of their duties, then the Justices of the Peace or the Commissioners of Highways shall act as fire wardens in their stead.

Aside of these fire wardens *ex officio*, the Commission may rely, "in forest towns," on the vigilance of fire wardens specially appointed by the Commission. A forest town may be subdivided into two or more fire warden districts.

In 1901, the chief fire warden had a force of 617 fire wardens at his command, with whom he kept in contact by continuous visits. A booklet, "Instructions to Fire Wardens," was issued in 1901.

The negligent or wilful firing of woodlands is punishable by a fine ranging between \$50 and \$500.

8. Reservations: The Adirondack Park exists only on the map and comprises that land which eventually should become the property of the State. It covers 3,226,144 acres, including over 2,000,000 acres of private holdings. The Adirondack forest preserve (the majority of), which lies inside the park, comprises 1,163,414 acres. It is entirely (excepting a few cases of divided rights) owned by the State, and contains 450,000 acres of forest proper, 590,000 acres of woodlands heavily lumbered, 40,000 acres of deforested land, 60,000 acres of water surface, 4,600 acres in farms. The spruce stumpage on the preserve is estimated to be 1.5 billion feet b. m.

The Catskills forest preserve comprises only 82,330 acres.

Both preserves are gradually increased by purchase, the prices ranging from \$1 to \$9 per acre. Tree planting on waste land, within the preserve, was begun in 1902.

FOREST POLICY.

9. Irrigation: 123 acres on 11 farms producing vegetables and tobacco.

FORESTRY CONDITIONS OF NORTH CAROLINA:

1. Area: 35,300 square miles of woodlands, or 73% of the State, are reported as "mostly timbered."

2. Physiography: The western mountain region occupies 6,000 square miles. It is formed by the Blue Ridge on the South Carolina line and the Great Smokies on the Tennessee line. Cross ridges connecting these chains show the highest elevations. Mount Mitchell, of 6,711 feet elevation, is the highest mountain east of the Rockies. Normal precipitation, 57 inches annually. Normal average temperature, 50 degrees F. Rivers running northward, breaking independently through the Great Smokies.

The Piedmont plateau, 400 to 1,500 feet high, occupies 22,000 square miles. Its configuration is rolling, in the west hilly. This fertile plateau is drained by the Catawba and Yadkin Rivers; further, by the headwaters of the Cape Fear, Neuse and Roanoke Rivers. Its elevation averages about 900 feet above sea level; its precipitations, 50 inches; its annual temperature, 59 degrees F.

The coastal plain of North Carolina, an area of 24,000 square miles, falls from 400 feet elevation down to sea level. North of the Neuse River the soil is loamy; south of it more sandy. Normal precipitations, 55 inches. Normal temperature, 61 degrees F. Large swamps along coast.

3. Distribution:

(a) Mountain region:

(1) Lower mountains. There are 6 species of oaks, 4 of hickories, chestnut, dogwood, black gum, sourwood and chinquapin. Post and Spanish oak are said (by W. W. Ashe) to be rather local. *Pinus echinata*, *rigida*, *virginiana*, *strobus* and (after Ashe) *pungens* prevail. White pine is said to cover 200,000 acres, notably in counties close to the Virginia line, reaching its finest development at altitudes ranging between 2,800 and 3,800 feet elevation. The lower mountains are practically deprived of virgin growth.

(2) Higher mountains. (3,000 feet to 5,000 feet elevation.) On the north slopes, hemlock, birches (*lutea* and *lenta*), red oak,

FOREST POLICY.

beech, basswood, cherry, yellow poplar, white ash, cucumber, chestnut and buckeye occur, frequently with a dense undergrowth of rhododendron.

On the south slopes, white, scarlet and chestnut oaks; chestnut, locust and hickory prevail. Table mountain pine on dry ridges. North Carolina hemlock on eastern slopes. Woods virgin.

(3) Mountain summits (over 5,000 feet elevation). Black spruce (*Picea rubens*) and balsam (*Abies fraseri*) cover the mountain sides, protected from storms. Buckeye, beech and sweet birch; further, mountain ash are mixed with the soft woods, the two first named often in groups.

The undergrowth is a tangle of laurels standing on a dense matting of mosses. On the wind-swept side of the mountains "balds" occur, fit only for pasture, covered with *Ericaceae*, dotted with stunted red oaks, chestnuts and a locust here and there

(b) Piedmont plateau. Uplands show an irregular mixture of broad-leaved species (notably black oak) with pines (*echinata* and *taeda*). On red sandstone a pure growth of *taeda* and *echinata* is frequently found without admixture of hardwoods. On fertile red clay (tobacco land), hardwoods (black, white and red oak; white, shagbark and small nut hickory; yellow poplar; white ash) occur without pines. The virgin forest is practically removed. Along the large streams, sweet and black gum, overcup and swamp (cow) oak, sycamore and hackberry occur. Along the smaller streams are found red and white oak, yellow poplar, beech, maples and hop hornbeam.

(c) Coastal plain. Maritime forests along seashore are broad-leaved and evergreen, composed of water (*nigra*), laurel (*laurifolia*) and live (*virens*) oak, devilwood (*Osmanthus americana*), mock orange (*Prunus caroliniana*), sweet bay, yaupon (*Ilex vomitoria*) and palmetto. The pine belt uplands, adjoining the maritime forests, show long leaf pine or *taeda* or both, according to fertility of soil. The lowlands in the pine belt exhibit so-called "Oak Flats," with cow, overcup, white, water and Spanish oaks, in company with ash, elm, gum, cottonwood and red maple; or swamps stocked with gum and cypress; or so-called "Bays," where white cedar prevails; or "Pond pine swamps," formed by *Pinus serotina*, mixed with oaks and *taeda* pine.

FOREST POLICY.

4. Forest ownership: 629 lumber firms control 1,714,000 acres. Balance of woodlands is owned by farmers and speculators.

5. Use of timber: There are altogether 1,751 saw mills. The average mill investment is \$3,572. The mill output in North Carolina amounted in the year

1850 to	\$ 900,000
1860 to	1,100,000
1870 to	2,000,000
1880 to	2,700,000
1890 to	5,900,000
1900 to	14,900,000

The cut of 1900 consisted of:—

Yellow pine	1,228,000,000 feet b. m.
Cypress	31,000,000 feet b. m.
Other conifers	11,000,000 feet b. m.
Poplar	51,000,000 feet b. m.
White oak	86,000,000 feet b. m.
Other hardwoods	8,000,000 feet b. m.

The naval store products, in 1885, were \$1,320,000. Then, already, the industry was on the decline, the output having decreased (after Fernow) since 1880 by 30%. The main shipping points for naval stores are Wilmington and Norfolk. After Sargent, the stand of yellow pine, in 1880, was 5,200,000,000 feet b. m. Since 1880, however, at least 15 billion feet of yellow pine have been cut. The stumpage in the mountain section after H. B. Ayres and W. W. Ashe, in 1901, amounts to 10,650,000,000 feet b. m. or 2,640 feet b. m. to the acre. In addition, the stand of firewood in the mountain section is estimated to be 16.83 cords per acre. The various species participate in said stumpage as follows:—

Oaks	41.41%	Chestnut	17.20%
White pine	2.68%	Hemlock	5.30%
Spruce	0.80%	Poplar	1.85%
Ash	1.43%	Buckeye	2.00%
Basswood	2.69%	Black gum	1.64%
Beech	1.06%	Cucumber	0.84%
Maple	2.67%	Birch	3.03%
Pitch pine	1.34%	Hickory	3.16%
Locust	0.67%	Echinata	0.43%
		Miscellaneous	9.80%

FOREST POLICY.

The miscellaneous industries (producing stock for furniture, wagons, agricultural implements, lath, bobbins and spools), in 1900, show an output of \$644,000.

Little cooperage stock (value \$30,000) and boxes (value \$76,000) were produced. Logs on stump are worth \$1.34; at mill, \$4.45.

The leather industry consumes, in the census year, in 75 tanneries, 1,808 cords of hemlock bark, worth \$8,524; 20,467 cords of oak bark, worth \$107,242; 270 barrels of oak bark extract, worth \$3,294. The value of the leather produced is \$1,502,000.

The paper and pulp industry is nill. The spruce forests of the high mountains are still inaccessible; in addition, freight rates are too high for good prospects of paper mill investments.

6. Forestry movement: The "North Carolina Forestry Society" is inactive. A forester, attached to the North Carolina Geological Survey, draws \$1,000 per year salary (W. W. Ashe).

7. Laws: Good fire laws, on the statute book, are a dead letter, since there is no staff charged with their enforcement. A recent law, practically prohibiting the export of logs for manufacture, is, probably, unconstitutional.

8. Reservations: The "Appalachian National Park" (or Reserve?), now planned, is located, largely, in the Great Smokies of Western North Carolina. Congress is asked to appropriate \$10,000,000 for the establishment of such a park covering 4,000,000 acres. North Carolina and the adjoining States have passed laws authorizing the United States to establish and manage such a park. Main difficulty to be met is the problem of local taxation.

9. Irrigation: 101 rice plantations, covering 3,283 acres, or 15% of the total area in rice, were irrigated in 1899, producing 30% of the total rice yield of the State.

Tide water is utilized for irrigation. The cost of the system averages \$34.35 per acre.

FORESTRY CONDITIONS OF NORTH DAKOTA:

1. Area: 600 square miles are wooded, an area equal to 1% of the entire State. No State of the Union has a smaller percentage of wooded area.

FOREST POLICY.

2. Physiography: Plains are unsheltered from the north. There are low hill ranges near the Canadian line, i. e., Turtle Mountains. The Missouri, after taking in the Yellowstone River, runs eastward and then southward through the State. The Red River of the North forms the boundary towards Minnesota.

3. Distribution: All river bottoms show disconnected groups of burr oak (*macrocarpa*), sycamore, cottonwood, box elder and green ash. The low northern mountains contain cottonwoods mainly.

4. Forest ownership: Several thousand acres (40,000?) of artificial forest planted under the timber culture act.

5. Use: Hardwoods used for firewood. Near Canadian line, wood is worth \$1.50 per cord. Building timber obtained from Minnesota. Twelfth census reports 4 saw mills of \$2,000 average capital. Logs worth \$1 on stump and \$5 at mill. No pulp and no leather industry.

6. Forestry movement: An association formed in 1887 seems to have died since. The timber culture act gave rise to enthusiastic but mostly unsuccessful planting. Arbor Day movement since 1884. Much interest in forest planting maintained by the press.

7. Laws: A bounty of \$2 annually to everyone planting one acre or more in trees. A plantation of five acres exempts a quarter section, plus \$1,000 worth of improvements, from taxation for ten years. Usual prairie fire laws. Owner must fire his land in March, April or May, and give 24 hours' notice of his intention to do so to all people living within one mile.

8. Reservations: None.

9. Irrigation: Possibility of reclamation along main Missouri River is limited.

The irrigated area, in 1899, aggregated less than 5,000 acres, yielding crops worth \$28,000.

Only \$18,000 has been spent for irrigation systems up to 1899.

FORESTRY CONDITIONS OF OHIO:

1. Area: Originally entire State was wooded. Forest area statistics are annually derived from data furnished by tax

FOREST POLICY.

assessors. In 1853 forest area was 55%; in 1870, 38%; in 1886, 22%; in 1896, 17.4%. After the 12th census, however, the area of woodlands was 23% of area of State, or 9,300 square miles.

2. Physiography: No mountains, no dry or rocky soil. Undulating, rich table land, every square foot fit for agricultural purposes. Lake Erie in the north and Ohio River in the South facilitate transportation.

3. Distribution: Scattering groves of long boled hardwoods appear everywhere (hickory, sycamore, oaks, chestnut, ash, maple, yellow poplar, walnuts, elm, beech, etc.). Original forest is, probably, left in swamps only. White pine along the Pennsylvania line in a narrow belt.

4. Forest ownership: All woodlands are attached to farms, except 80,700 acres, of 4,100 feet b. m. average stumpage, controlled by lumber mills.

5. Use of timber: Ohio occupies seventh rank as a lumber producing State of the Union, having maintained its position admirably in spite of reports of declining supplies. Ohio leads in the production of furniture stock. Logs are worth at mill \$9.47, and on stump, \$4.92. There are 2,023 mills, of \$4,638 average investment. Value of products of lumber industry averaged, in 1870, 1880, 1890 and 1900 respectively, \$10,000,000, \$14,000,000, \$15,000,000 and \$21,000,000.

The cut in 1900 consisted of:—

White oak	593,000,000 feet b. m.
Other hardwoods	325,000,000 feet b. m.
Conifers	42,000,000 feet b. m.

Leather industry: 58 tanneries use 5,500 cords of hemlock bark, 23,800 cords of oak bark, 10,000 barrels of bark extracts and a little gambier, quebracho and sumac. Total product of tanneries equals \$5,200,000.

Paper and pulp industry has 51 plants using rags, waste paper, straw and manila grass preferably, in addition to 5,000 cords of home-grown (?) spruce, 2,000 cords of Canadian spruce, 10,000 cords of home-grown poplar, 2,000 cords of Canadian poplar and 12,000 cords of miscellaneous woods.

6. Forestry movement: State Forestry Association inactive. Woodland is considered only as farmland bearing the wrong crop. A bill for forestry school defeated in 1897.

FOREST POLICY.

Forestry lectures by Wm. R. Lazenby, at State University.
Cincinnati Forestry and Improvement Association formed
in 1903.

7. Laws: Fire laws since 1805. State forestry bureau
created in 1885. Officers unsalaried and now inactive.

8. Reservations: None.

9. Irrigation: None.

FORESTRY CONDITIONS OF OKLAHOMA AND INDIAN TERRITORY:

1. Area: In Indian Territory, 65% of the total area or
20,000 square miles are wooded.

In Oklahoma, 11% of total area or 4,400 square miles are
wooded.

2. Physiography: Undulating plateau, drained by rivers
flowing west to east, notably the Canadian River and Cimarron
River. The Red River of the south forms the southern
boundary.

The highest mountain ranges in the Ozark plateau are the
Arbuckle and the Boston Mountains. The Cross timbers enter
from Texas.

The Wichita Mountains, in the southwest, are over 2,000
feet high.

3. Distribution: Western section is prairie, with green
ash, hackberry and cottonwood along the rivers. Red cedar is
said to have been found 20 years ago on the edges of all canyons.

Middle section has woodlands of blackjack oak and post
oak, notably in the Cross Timbers. Further, some burr oak,
hackberry, white oak, shittim wood and wild china berry tree
occur. These species are said to be gradually extending towards
the west. After W. L. Hall, black walnut, catalpa and locust
can be planted successfully within the original oak forests.

In the eastern section (Indian Territory), south of the
Canadian River, *Pinus echinata* and *taeda* are found in large,
valuable bodies on the ridges. The lowlands in the east are
splendidly timbered with the hardwoods of the Mississippi bot-
toms. Here the best black walnut of the United States is said
to exist. Further, red oak, cow oak, hickories, white ash, gums,

FOREST POLICY.

cottonwood, sycamore, mulberry, maple, osage, orange and pecan.

4. Forest ownership: In Indian Territory, 32,347 acres are owned by lumbermen, with stumpage averaging 3,800 feet per acre.

In Oklahoma, lumbermen own 10,940 acres, of 1,300 feet average stumpage.

5. Use of timber: In Indian Territory, the sawn products of 1900 were valued at \$200,000, consisting of 16,000,000 feet b. m. Logs on stump worth \$1.21 and logs at mill worth \$4.61. There were 48 mills, representing an average investment of \$1,911.

In Oklahoma there were 33 mills, of \$1,423 average investment, which have turned out, in the census year, \$63,000 worth of lumber. Logs on the stump are worth \$2.54 and at mill \$5.82.

Leather, paper and pulp industries: None.

6. Forestry movement: Some forest planting in Oklahoma.

7. Laws: Unknown.

8. Reservations: The Wichita forest reserve, of 57,120 acres, in the Wichita Mountains of Oklahoma.

9. Irrigation: Irrigation is unimportant, being practiced, in 1899, on 2,300 acres only.

The systems of irrigation cost \$22,000.

The irrigated crops are valued at \$16,000.

FORESTRY CONDITIONS OF OREGON:

1. Area: The forests occupy 34,750,000 acres, equal to 57% of total area of State. Fernow gives only 20,000,000 acres and the vice-president of the defunct Oregon Forest Association only 16,000,000 acres of forest. Reason for difference is the difference of definition of forest. The great commercial forests cover about 10,000,000 acres.

2. Physiography: Coast Range separated from the Cascade Range by the Willamette, Umpqua and Rogue Rivers. The heavy rainfall in the Coast Range is due to the Japan current (Kuroshivo). In the northeastern part of the State the Blue Mountains extend into Washington. The southeastern third of the State is without forests, exhibiting deserts close to Nevada.

FOREST POLICY.

3. Distribution: Similar to that in Washington.

(a) Coast Range. Tideland spruce close to the ocean. The bulk of the forests consist of Douglas fir and red cedar. Lawson's cypress forms a forest of great commercial value in the southern third of the Coast Range, where it exhibits splendid silvicultural qualities, i. e., abundant regeneration. In the extreme south of the Coast Range, sugar pine, winter bald white oak and also California chestnut oak are met with.

(b) Cascade Range. On west slope, most important tree is Douglas fir, forming pure forests below 2,000 feet elevation and reproducing splendidly on clearings. Red cedar, hemlock and, higher up, white pine (*monticola*) are next in importance to Douglas fir. The firs (noble, amiable and grand) run high up on the mountains, fringing Crater Lake (10,000 feet elevation). In southern extension of cascades, sugar pine occurs.

On east slope: Below 5,000 feet an open forest of yellow pine is found; above 5,000 feet, Douglas fir, lodgepole pine and lowland fir are mixed with yellow pine. In addition, Engelmann's spruce, western larch and white pine occur. At timber line white bark pine and hemlock are found in open forests.

The river bottoms between Coast Range and Cascade Range exhibit heavy, broad-leaved groves composed of cottonwoods, alders, ashes, willows and white maples; also the ever-green California laurel.

(c) The Blue Mountains (in northeast corner of State) show open stunted forests of yellow pine, Douglas fir and larch, and, above 4,000 feet elevation, a heavy growth of lodgepole pine.

4. Ownership: Farmers own 1.5 million acres.

Lumbermen, mostly Michigan and Wisconsin men, composing 212 firms, control 825,000 acres, of 25,000 feet b. m. per acre average.

United States reserves cover close to 4.5 million acres on the Cascade Range. None exist on the Coast Range.

The Warm Springs and Klamath River Indian reservations cover about 1,000,000 acres each, but are not heavily forested.

5. Use: The hardwoods are largely used for woodenware, cooperage and furniture. The California laurel is the finest wood for cabinet work and ship building on the coast. The center of the hardwood industries is Portland. The cut in the census

FOREST POLICY.

year was 740 million feet b. m. only, which is equal to 0.3% of the growing stock of 225 billion feet b. m. This growing stock is composed as follows:—

Red fir	150 billion feet b. m.
Yellow pine	40 billion feet b. m.
Hemlock, spruce and cedar	35 billion feet b. m.

Mills smaller than in Washington, the average investment being \$12,300. Stumpage prices lower than in any other State, being 66c. per 1,000 feet b. m. Saw logs at the mill cost \$4.46 per 1,000 feet b. m.

The paper and pulp industry used in 1900, 150,000 cords of spruce in 5 establishments. The leather industry had 16 tanneries, worth \$11,000 on an average, reporting to be annually using altogether 936 cords of hemlock bark and 1,247 cords of oak bark (?).

Very important for Oregon is the live stock industry.

The stock consists of

14,000,000 cattle,

24,000,000 sheep,

2,000,000 horses,

500,000 mules.

Sheep are driven to the summer range in the high cascades, so as to leave all pasture in the lowlands to the heavier stock.

Annual value of the wool product is over \$1,500,000. In the reserves, only 60 owners with 188,000 sheep in 86 bands.

6. Forestry movement: In 1888-1889 Legislature petitions Congress to establish reserves. In 1897 outbreak of antagonism against "Reserve Policy," backed by the Wool Growers' Association (John Minto).

In 1898 forest reserves were opened to limited sheep pasture, and the antagonism to reserves has since subsided.

7. Laws: State fire laws of 1893 impose fines on malicious or careless firing of woods, but are ineffective. The public domain is protected under special fire laws. New fire law of 1903 was passed by both houses, but vetoed by governor.

8. Reservations: Reserves cover 13% of wooded area and 7.2% of total area of State.

The Ashland forest reserve (18,560 acres) in the extreme south and the Bull Run timber land reserve (142,080 acres) in the extreme north of the Cascade Range are small and unim-

FOREST POLICY.

portant. The Bull Run reserve includes Mount Hood. Between the two reserves stretches the Cascade Range forest reserve, a reserve of 4,436,120 acres enclosing the Crater Lake National Park of 150,000 acres. The reserves extend, practically, from the Washington line to the California line, are 50 to 100 miles wide, lie largely above 7,500 feet above sea level and include many summits above timber line.

9. Irrigation. The agricultural development of central Oregon depends on the possibility of utilizing for irrigation the scanty and intermittent streams of the region.

The success of a deep well system would allow of an enormous increase of the cattle and sheep industry.

In 1899, 388,000 acres of farm land, producing \$3,100,000 worth of crops, were irrigated from works constructed at an outlay of \$1,800,000.

FORESTRY CONDITIONS OF PENNSYLVANIA:

1. Area: The woodlands comprise 23,000 square miles, or 51% of total area. The forest is said to be, in a great part, depleted of its merchantable timber.

2. Physiography: A belt of mountains 50 miles wide and 240 miles long traverses the State diagonally from southwest to northeast. The mountain ranges are from 1,000 to 2,000 feet high, Negro Mountain forming the highest peak, at an altitude of 2,826 feet.

Northwest of the mountain belt are the broad Allegheny Uplands, rolling high plateaux covering over one-third of the State. Southeast of the mountain belt appears the northern extension of the Coastal Plains at an average elevation of 500 feet. The Susquehanna drains the eastern half of the State, together with the Delaware on the New Jersey line.

3. Distribution: Pennsylvania was originally covered from end to end with heavy forests. White pine and hemlock formed vast forests on both flanks of the Alleghenies. East and west of the mountains the conifers gave way gradually to a heavy growth of broad-leaved species.

In the southeastern section, white oak was and is the most valuable species. The second growth of hardwoods is otherwise

FOREST POLICY.

composed of hickories and birches; further, chestnut, locust, maple, walnut and cherry.

In the Allegheny Uplands the hardwoods of the Mississippi are found, notably, red and white oak, beech and sugar maple. In the southwest of this region occur the Kentucky coffee tree, honey locust, chestnut and yellow poplar. West of the Allegheny River no white pine, but some hemlock occurs. East of this river, hemlock; then white pine increases in proportion on the way toward the mountains.

In the mountain belt prevail, below 1,800 feet, white pine, hemlock, pitch pine, sugar maple, black and yellow birch, beech and cherry. On rocky soil, especially in the southern part, occur chestnut oak, chestnut and locust. Above 1,800 feet the Canadian tree flora sets in, consisting of spruce (*Picea rubens*), balsam and larch, with some white pine, Norway (red) pine and hemlock. White pine stands averaging 25,000 feet b. m. per acre on tracts comprising several hundred acres are no longer found.

In 1880 white pine virgin forests occurred only island-like on their original domain, whilst hemlock was then scarcely touched.

In 1900, on burned white pine slashes, yellow and black birch, bird and black cherry, maple, chestnut and beeches come up in profusion.

Regeneration of hemlock is nill; that of white pine very poor.

In 1896, Dr. Rothrock and Dr. Fernow estimated the stand of conifers as follows:—

White pine	500,000,000 feet b. m.
Spruce	70,000,000 feet b. m.
Hemlock	5,000,000,000 feet b. m.

4. Forest ownership: In 1894, over 1,500,000 acres, i. e., over 5% of State's area, were advertised for sale by the counties for tax forfeiture.

614 lumber firms own 645,000 acres of forest, said to be stocked with 9,300 feet b. m. on an average.

83% of the woodlands are said to be attached to farms.

The State reserves now aggregate several hundred thousand acres.

5. Use of timber: Logs on stump are worth \$2.94; at mill, \$6.71. 2,280 mills report an average investment of \$10,083. Penn-

FOREST POLICY.

sylvania, leading the United States lumber industry in 1860, has dropped to fourth rank in 1900, although she succeeded in vastly increasing the value of her output within these 40 years.

The output was in:—

1860	\$11,000,000
1870	29,000,000
1880	22,000,000
1890	29,000,000
1900	36,000,000

The cut in 1900 consisted of:—

Hemlock	1,608,000,000 feet b. m.
White pine	238,000,000 feet b. m.
Other conifers	19,000,000 feet b. m.
Chestnut	51,000,000 feet b. m.
Oak	342,000,000 feet b. m.
Other hardwoods ..	140,000,000 feet b. m.

Total 2,398,000,000 feet b. m.

The shingle mills turned out, in the census year, \$370,000 worth of shingles, largely using the old remnants of white pine and hemlock, also a little oak and chestnut.

Cooperage stock produced in 1900 was valued at \$762,000 (notably for sugar barrels); the miscellaneous industries furnished \$1,443,000 worth of home-grown stock. Very little wagon and furniture stock.

In forest utilization, the rivers, notably the Susquehanna, are made use of. Skidways and sleds are little used. The logs are moved over so-called "slides," V shaped troughs, consisting of hemlock poles placed on hemlock ties, with an ice crust formed by sprinkling. Six to forty peeled logs form a log train, pulled by horses in a tow path.

At the Williamsport boom, the proportion of hemlock and pine logs was, in 1875, 1 to 10; and in 1893, 5½ to 1.

Leather industry: Pennsylvania excels amongst the States of the Union in the output of the leather industry, which output is valued at \$55,615,000. 254 tanneries consumed, in the census year, 565,062 cords of hemlock bark, worth \$3,460,000; 64,392 cords of oak bark, worth \$437,000; 2,800 bales of gambier, worth \$17,000; 304 barrels of hemlock bark extract worth \$3,368; 5,615 barrels of

FOREST POLICY.

oak bark extract, worth \$56,700; 3,775 barrels of quebracho, worth \$50,700; 206 tons of sumac, worth \$10,000. The chemicals used were worth \$919,600.

The output of Pennsylvania's tanneries is mostly sole leather.

In paper and pulp industry, Pennsylvania has 4th rank, producing \$12,268,000 worth of paper in 73 mills and consuming: Home-grown spruce, 16,697 cords, valued at \$85,504; Canadian spruce, 25,442 cords, valued at \$167,200; other pulp wood, 2,262 cords, valued at \$11,000.

6. Forestry movement: Pennsylvania is more awake to the necessity of forest preservation than any other State, thanks to the energy of Dr. Rothrock. A Forest Association backs his work and publishes "Forest Leaves," since 1885. Forestry lectures are occasionally given at the universities. Arbor Day since 1886.

7. Laws: Since 1887, forest plantations of at least 1,200 seedlings enjoy a tax reduction of 90% to their tenth year; of 80% to their twentieth year, and of 50% to their thirtieth year. From 10th year on, 600 saplings per acre are considered a sufficient growing stock. Similar inducements are granted to owners of second growth, consisting of sound tree seedlings, covering not to exceed 50 acres.

In 1897, the Forest Commissioner was authorized to purchase forfeited land at a price not to exceed back taxes and other "unseated" land at a price of not over \$5 per acre, such lands to become part of a forest reservation system.

The constables of townships are ex officio fire, fish and game wardens, entitled to a premium of \$10 for each offense (fire) reported. They are privileged to summon help, and obliged to report to the court of quarter sessions any case of violation of fire, fish and game laws.

The expense of the fire warden system is equally divided between county and State. The county, however, is not required to incur an outlay exceeding \$500 per annum.

The law of 1897 authorizes the acquisition of three tracts at the head waters of the Delaware, Susquehanna and Ohio Rivers by expropriation for the forest reserve. Each tract is to comprise 40,000 acres in a solid body.

In 1901 the Division of Forestry was raised to the rank of a department.

The revenue from the reserves is to be divided between township and State, to reimburse the former for the inevitable

FOREST POLICY.

loss of taxes. The forest commissioner, as superintendent of the reserves, is empowered to enact rules for management and protection of the reserves; may employ detective service and lawyers in case of forest fires; must publish forest statistics, and may spend \$25 annually per mile for improvement of public roads in the reserves, \$12.50 per mile for improvements outside the reserves.

The reserve policy is handicapped by a constitutional clause forbidding the State to take up loans for such purposes of investment as a forest reserve represents.

8. Reservations: 575,000 acres of State forest reserves have been created within four years, during the administration of Governor Stone. The reserves are scattered over 22 counties. Only two reserves cover an acreage exceeding 100,000 acres.

9. Irrigation: 758 acres are irrigated; 93% of this land yields hay crops valued at \$23.64 per acre.

FORESTRY CONDITIONS OF PHILIPPINE ISLANDS:

1. Area: After Capt. Geo. P. Ahern, 25% to 50% of the islands (or an area of 20,000,000 to 40,000,000 acres) are public forest lands. Mindoro and Paragua contain 5,000,000 acres of virgin forest. Mindanao is almost entirely covered with virgin timber (20,000,000 acres).

2. Physiography: The Philippines, consisting of more than 1,000 islands, separate the Pacific from the Chinese Ocean. The configuration is mountainous, with active volcanos in the south. Mount Apo, on Mindanao, is over 10,000 feet high. The climate is tropical; rainy period from June to November; dry spell from December to May.

3. Distribution: The number of native tree species approximates 700.

4. Forest ownership: The federal government and, to a certain extent, religious orders, own all forest land.

5. Use of timber: Forest utilization suffers from the difficulty of transportation, the lack of efficient labor and the variety of growing stock, containing a large number of commercially untested species.

FOREST POLICY.

Gum, rubber and gutta percha trees, dye woods, ylang-ylang, cocoanut palms (in Romblon), etc., have been utilized under Spanish rule.

The occurrence of a pine (*Pinus insularis*) in a tropical climate is geographically interesting.

The price of logs in Manila ranges from 60c. to \$3 (Mexican) per cubic foot. Carabao oxen are used in log transportation. Lumber is hand sawed by the natives. The white ant is the enemy destroying all lumber and timber used and utilized, excepting three or four species.

6. Forestry movement: A Bureau of Forestry, established under G. P. Ahern, succeeded the Spanish forest administration (since 1863) after American occupancy in 1898. The administrative staff is now supplied by American foresters passing the civil service examinations.

The forestry movement centered in the bureau is, naturally, in the direction of forest exploitation only. The botanical and technical characteristics of the timber species are studied and tested. All timber cut on public land is cut by license. Forestry officials, stationed at all important logging centers, inspect, stamp, classify and appraise all shipments of timber cut under license. The cutting of certain species and of certain sizes of trees is prohibited on public land.

The licensee pays from 1c. to 14c. (Mexican) per cubic foot of timber removed from public land.

A forestry school, after the pattern of Dehra Dun, India, should be organized.

7. Laws: The Spanish forestry laws and regulations have been adopted with slight alterations—a course highly commendable.

8. Reservations: None.

9. Irrigation: Not applicable.

FORESTRY CONDITIONS OF PORTO RICO:

1. Area: The island area totals 2,304,000 acres. It is dotted with many trees, park-like; but deforested as a whole, with the exception of eight square miles of inaccessible primeval forest on Mount El Yunque.

FOREST POLICY.

2. Physiography: The climate is tropical. The south is drier than the north. The mountains (volcanic) are continuously bathed in moisture.

3. Distribution: The mountain tree flora is composed of a large number of species, including palms and tree ferns, none of commercial importance.

The coastal forest is said to be often chaparal-like.

Fruit trees (orange, lime, lemon, banana) are common all over the island.

The coffee plantations often appear as dense forest thickets.

4. Forest ownership: No information available. The federal government owns but little land.

5. Use of timber: Fruit trees are most valuable. There is not one saw mill in the island. Natives drag logs cut and roughly squared to the nearest ox-trail. Logs are often whip-sawed into planks or boards. About \$300,000 worth of timber and timber products are annually exported.

6. Forestry movement: None. Avenues of shade trees frame the Spanish highways. Reforestation of denuded slopes seems advisable.

7. Laws: No information available.

8. Reservations: The Luquillo forest reserve, in the eastern part of the island, was established on January 17, 1903.

9. Irrigation: For the cultivation of the staple crops of the south coast, irrigation is practiced with great skill and at considerable expense.

FORESTRY CONDITIONS OF RHODE ISLAND:

1. Area: Area of woodlands, 400 square miles or 40% of the State.

2. Physiography: Flat and sandy. Maritime climate.

3. Distribution: Originally all the island was covered with forest. Now, coppice of chestnut, oak, hickory, ash and birch, with some stray white and pitch pine, are found to form a meager second growth. Trees along the coast are stunted and scarce.

4. Forest ownership: 13 lumber firms own 1,673 acres. Balance of woodland is attached to farms.

FOREST POLICY.

5. Use of timber: Firewood commands a high price, owing to density of population (250 pro square mile). Stumpage costs \$3.02; logs at mill cost \$7.15 per 1,000 feet b. m. 33 saw mills report an average investment of \$3,131. The census gives the value of the output of the lumber mills, since 1870, at about \$250,000 annually.

The cut in 1900 is reported to consist of 18,000,000 feet b. m., including 14,000,000 (?) feet b. m. of white pine.

Leather industry: 5 tanneries, of \$293,000 output, consume 26 cords of hemlock bark, worth \$260, and \$5,000 worth of chemicals.

There is no paper or pulp mill.

6. Forestry movement: None. Some private plantations on sand land.

7. Laws: Fire laws. No case was ever prosecuted.

8. Reservations: None.

9. Irrigation: 2 farms produce on 40 acres \$32,000 worth of vegetables (?).

FORESTRY CONDITIONS OF SOUTH CAROLINA:

1. Area: 20,500 square miles, or 68% of total area, are said to be stocked, generally, with merchantable forest. Sargent's estimate of yellow pine supplies, existing in 1880, was 5.3 billion feet b. m.

2. Physiography: On the North Carolina line, in the extreme northwest, the Blue Ridge Mountains. The Piedmont plateau lies to the east and south of these mountains and extends to a line 150 miles from the coast, where the lowlands of the coastal plain set in.

3. Distribution: In the tier of mountain counties occur the species typical for the southern Appalachians (see Georgia). In the Piedmont section, the hardwoods (especially white, chestnut and red oaks, poplar, hickory, ash, chestnut and cottonwood) occur with *Pinus taeda* and (less) *echinata*. The coastal plain has long leaf pine for the main timber tree. *Cubensis* gives out near Charleston. On moist ground, *Pinus taeda* of splendid growth, often mixed with red oak and white cedar. Huge swamps are occupied by cypress and gums, the hummocks showing elm, hick-

FOREST POLICY.

ory, yellow poplar and red oak. The coast swamps are lined with live oak, magnolia and bays, often with palmetto for an undergrowth.

4. Forest ownership: 251 lumber firms own 454,000 acres of 4,400 feet b. m. average stumpage. Vacant State lands were sold at auction for a song, about 1895.

5. Use of timber: South Carolina seems backward in the lumber industry. The activity was never great. The rivers are not as good for rafting as those in adjoining States, being bordered by broad swamps. Logs are worth \$1.23 on stump and \$4.16 at mill. Mill investments average \$4,097, with 716 firms. The output was valued in

1880	\$2,000,000
1890	2,100,000
1900	5,200,000

The cut of 1900 consisted of:—

Cypress	32,000,000 feet b. m.
Yellow pine	433,000,000 feet b. m.
White oak	11,000,000 feet b. m.
Other hardwoods ...	6,500,000 feet b. m.

In 1880, South Carolina lead in the production of tar and turpentine. Since then, the industry was forced westward.

The miscellaneous forest industries (furniture, wagon, cooperage stock, etc.) produced \$168,000 in the 12th census year.

The leather industry is very small, using 305 cords of oak bark and producing \$18,000 worth of goods.

The paper industry is nill.

6. Forestry movement: Nill.

7. Laws: Stock law prevails over entire State. Fire law provides heavy fines for firing turpentine orchards.

8. Reservations: None.

9. Irrigation: 648 planters irrigate, in 1899, 30,000 acres of rice fields. Rice irrigation has been practiced in South Carolina since 1700.

FORESTRY CONDITIONS OF SOUTH DAKOTA:

1. Area: 2,500 square miles, equal to 3% of the area of the State, are wooded.

2. Physiography: Missouri River running from north to

FOREST POLICY.

south to the center of the State and thence towards the southeast corner. Mountains appear only in the southwest, i. e., the Black Hills on the Wyoming line, drained by the Cheyenne River. A strangely large number of rivulets have their sources in South Dakota.

3. Distribution: South Dakota, like all other prairie States, is the meeting ground of the eastern and western tree flora, the former represented by the hardwood groves in the river bottoms (burr oak predominating, in addition, sycamore, cottonwood, willow, box elder, green ash); the latter (western flora) occurring on hillsides and represented by western yellow pine. This species shows in the Black Hills splendid natural regeneration and better trunks than in the Rockies. White spruce (*canadensis*) occurs in the Black Hills near streams, on high northern slopes. Aspen and canoe birch appear on moist slopes in dense thickets after fires.

4. Forest ownership: Farmers own little aside from prairie plantations. Six lumber firms control 6,000 acres. The federal government has reserved 76% of the wooded area in the "Black Hills reserve."

5. Use: Yellow pine only used for timber and for the lead mining interests centering at Deadwood. The cut of timber in census year equals 30,000,000 feet b. m., drawn from a growing stock of 1,500,000,000 feet b. m. Logs are worth, on stump, \$1.80 per thousand; at mill \$5.25. There are 28 saw-mills of \$5,000 average investment. 5,000 head of stock find pasturage in the hills. A plague of bark beetles occurred in 1900. Hardwoods largely used for firewood and fences. Planted forests have perished, usually through fire or neglect, in the majority of cases.

6. Forestry movement: Arbor Day for ornamental planting. South Dakota Agricultural College makes tree planting experiments and issues bulletins bearing on forestry questions.

7. Laws: As in North Dakota.

8. Reservations: The Black Hills forest reserve comprises 1,211,680 acres, one-third of which lies in Wyoming. The opportunity for forest management in this reserve is unrivalled. The financial problem is easy, since stumpage values are high and the demand good. The silvicultural problem is easy, since regeneration is excellent, and since only one species has to be dealt with. There are no "weed trees." Finally, utilization is easy, the moun-

FOREST POLICY.

tains having gentle slopes. Even firewood can be disposed of to a certain extent. Fires and insects, however, handicap the forester's work.

The Wind Cove national park, in the southern Black Hills, created in 1902, is said to be a Yellowstone without geysers.

9. Irrigation: During the census year, 44,000 acres of farmland, irrigated from works (notably deep artesian wells) costing \$285,000, produced crops valued at \$208,000.

FORESTRY CONDITIONS OF TENNESSEE:

1. Area: 27,300 square miles, or 65% of the State, are under forest.

2. Physiography: Vast bottom lands along the Mississippi, subject to inundation. Cumberland River in the north and Tennessee River in the south. Cumberland and Alleghany Mountains in the east, the latter with summits over 6,000 feet high. Low mountain ranges in central part.

3. Distribution: The Mississippi bottom lands show gigantic hardwood forests without undergrowth and a sprinkling of swamps stocked with cypress, red and black gums. Cypress is said to be of poor quality. Amongst the hardwoods are found cottonwoods, gums, red and cow oaks, hickories, elms, beeches and white oaks of huge proportions.

In the middle division of Tennessee (Blue Grass region) agriculture has entirely superceded the forest. Here have grown, originally, the finest red cedar, black walnut and yellow poplar. Now farm wood-lots even are strangely absent. In the original forest there were further found white, red, green and blue ash; white, chestnut, burr, cow, yellow, chinquapin and Texan oak; red, black, sugar and ash-leaved maple; white linden, hackberry, honey locust; winged and American elm. On dry hills, fire has played havoc with the forest. Here white and post oak are rapidly removed for cooperage, whilst black, Spanish and scarlet oak, chestnut and black hickories are badly handicapped by fires. Chestnut is usually dying or dead.

The "Black Jack Lands" (marilandica) are large stretches of strongly calcareous soil, stocked with a stunted growth of black jack, extremely monotonous and much less productive than

FOREST POLICY.

the "Kentucky Barrens." *Pinus echinata* occurs in island-like groups all over middle Tennessee. *Pinus taeda* forms a narrow belt along the Alabama line.

In the Cumberland Mountains the limestone coves show, or used to show, a splendid growth of all valuable hardwoods (white, red and chestnut oak; hickory, notably shag bark; black walnut and black cherry; yellow poplar, cucumber, ash and basswood; red cedar on dry cliffs), whilst the sandstone plateaus overlying them exhibit a poor growth, badly burned, of black, Spanish, post and white oaks; further, sourwood, black gum, chestnut and red maple, with occasional tracts of *Pinus echinata*, *virginiana* and *rigida*. *Pinus pungens* occurs at an altitude of about 3,000 feet and upwards. Good white pine tracts, heavily stocked, are hidden in the backwood coves of the Great Smokies, accompanied on moist and sheltered land by hemlock, or else occur on long, sharp ridges. Spruce and balsams at elevations from 5,000 to 6,000 feet. The hardwoods of the Great Smokies are those of Pisgah forest.

4. Forest ownership: 1,138,000 acres of land are owned by lumber firms. Average stumpage, 3,900 feet b. m. per acre.

5. Use of timber: Logs are worth \$2.18 on stump and \$6.58 at mill. Logs frequently measured in midst of log. Cedar logs bought by the pound. Lumber centers are Memphis and Nashville. The product of the lumber industry in Tennessee was valued in

1870	\$ 3,400,000
1880	3,700,000
1890	9,100,000
1900	18,100,000

The cut consisted of:—

Conifers	82,000,000 feet b. m.
Ash	18,000,000 feet b. m.
Poplar	275,000,000 feet b. m.
Red gum	52,000,000 feet b. m.
White oak	408,000,000 feet b. m.
Other hardwoods	114,000,000 feet b. m.

Total.....949,000,000 feet b. m.

In 1900 Tennessee leads all States in the produced value of staves (181,000,000 staves, worth \$2,500,000) and furnishes 17,-

FOREST POLICY.

000,000 sets of heading, worth \$441,000. Furniture, agricultural and wagon stock are worth \$1,245,000.

Leather industry: Value of output, \$2,800,000. The tanneries consume 846 cords of hemlock bark and 37,050 cords of oak bark, worth \$210,000; further, 58 barrels extract.

Pulp and paper industry: None.

6. Forestry movement: The "Tennessee Forestry Association" was formed two years ago. The Bureau of Forestry has made and published a working plan for a 7,000 acre tract at Sewanee.

7. Laws: Fire laws absolutely ineffective. Arbor Day.

8. Reservations: None.

9. Irrigation: None.

FORESTRY CONDITIONS OF TEXAS:

1. Area: Woodlands cover 64,000 square miles or 24% of the total area of State.

2. Physiography: The Rio Grande River on the Mexican line, the Red River along Indian Territory and the Pecos River traversing the extreme western section are the principal streams.

The western prairies are underlaid with limestone; the east is diluvial and alluvial, taversed by the Ozarks and Cross Timbers.

3. Distribution: Deserts in the extreme west (Staked Plains). Undulating prairies destitute of timber in the middle west. Western red cedar found along the canyons. Western high hill ranges, between Pecos and Rio Grande Rivers, show New Mexican flora. Mesquit extends to the desert borders. East of the 96th degree of longitude, the maritime pine belt exhibits splendid forests of long leaf pine, loblolly pine and short leaf pine (echinata). Stumpage of long leaf pine averages heavier than anywhere else, on 2,900,000 acres.

The low flats between the pine hills show impenetrable thickets of hawthorn, holly and magnolia. Bald cypress forms extensive forests in the river bottoms. Pecan, live oak, holly and Carolina poplar show their finest development along the rivers of the east. Osage orange is a common tree in the east. The Cross Timbers are covered with poor post oak and black

FOREST POLICY.

jack oak woods. These same species extend westward in open groves, ending abruptly where limestone appears. Hackberry said to be found everywhere.

4. Forest ownership: All deserts and outskirts of the Rockies and large forest tracts in the eastern part belong to the State, which, when admitted to the Union in 1845, was allowed to retain its lands and land laws. Federal government owns but a few military reservations.

Lumber companies, in 1900, own 10 billion feet stumpage on 1,671,000 acres. Under the State's general land act of 1895, amended in 1897, the purchase, by individuals, of large tracts belonging to the State is not prohibited.

5. Use of timber: Mesquit and red cedar used for fuel and posts. Cypress said to be of poor quality. Cottonwoods unused so far. The pine belt has been developed rapidly and recently at rising stumpage prices. The output in 1900 was 1,250,000 feet b. m., valued at \$16,300,000.

There are 601 saw mills, of \$14,000 average investment.

Logs are worth \$1.17 on stump and \$4.47 at mill.

The eastern pine forests are most valuable for Texas, since they have to supply the constantly growing population of the treeless three-quarters of the State.

The most important industry of Texas is cotton growing. Stock raising is a close second.

The naval stores industry gradually adopts dangerous proportions, since it injures the prospects for a second growth.

Paper industry attempts to use pinewood in the soda process.

There are nine tanneries, producing about \$60,000 worth of leather and using about 390 cords of oak and hemlock bark and 137 barrels of bark extract; balance of material used is gambier.

6. Forestry movement: A State "Forestry and Water Supply Association," formed in 1886, seems inactive.

A forestry commissioner cannot be obtained from the legislature. Remarkable is the necessity for the large Kirby Lumber Co. to practice conservative lumbering, owing to stipulations contained in its mortgage bonds.

7. Laws: No information available.

8. Reservations: None.

9. Irrigation: Irrigation on the enormous cattle ranches of central Texas is practically unknown.

FOREST POLICY.

The Mexicans along the Rio Grande and Pecos have irrigated small farms for centuries.

In the east the flooding of rice fields by pumping has recently gained favor.

In 1899, 50,000 acres of farmland were irrigated, yielding crops worth \$539,000 from irrigation systems costing \$1,028,000.

FORESTRY CONDITIONS OF UTAH:

1. Area: 13% of the State, or 10,000 square miles, are wooded.

2. Physiography: The western and eastern thirds of the State are barren. The central third is traversed by the Wahsatch Range, which drains eastward into the Colorado River and westward into Salt Lake, Utah Lake and Sevier Lake.

3. Distribution is little known. In the foothills scrub oaks, nut pine, cedar and juniper occur. Best timber (very poor) obtained from the limber white pine. Higher up in the mountains occur blue spruce (*Picea pungens*), white spruce (Engelmann) and Douglas fir. Yellow pine seems rare, except in the San Pete and San Pitch Ranges. Near Salt Lake the mines have consumed all accessible timber. Cañons are lined with cottonwoods and box elder.

4. Forest ownership: Reserves contain 1,029,760 acres. Large Indian reservation in the northeast called the Uintah Indian reservation. Railroads own alternating sections as usual. Lumber firms own very little.

5. Use: Mine props and fence posts are in chief demand. Coal is cheap. All timber is practically cull; still, log run limber white pine sells at \$40 a thousand. Value of timber output, in 1900, only \$214,000, less than the figures given in the last three census. Stumpage is reported worth \$1.32; logs at mill, \$5.31. Eighty-one mills of \$1,224 average investment. Two very small tanneries, but no pulp industry.

6. Forestry movement: People and legislature are apprehensive of the necessity of forest protection, as shown by petitions to Congress and the Governor's messages. Shade trees planted in cities and on farms, especially box elder, sycamore, cottonwood and lombardy poplar.

FOREST POLICY.

7. Laws: Usual fire laws since 1876. Tax exemption of \$500 worth of property for five years for every acre planted in trees, and of \$50 for every 100 trees planted on streets or streams.

8. Reservations: The Fish Lake forest reserve (67,840 acres) in the San Pete and San Pitch Range of the Wahsatch Mountains. The Uintah forest reserve (875,520 acres) along the Wyoming line at the head waters of the Green River.

The Payson forest reserve of 86,400 acres lies south of Utah Lake.

The Manti forest reserve of 584,640 acres has been established recently in central Utah; the Logan forest reserve of 182,080 acres in northern Utah.

9. Irrigation: The communal organization of the Mormons has admirably subversed the mutualistic cause of irrigation.

Dry farming, for wheat and barley, is possible only on some high bench lands. Generally speaking, however, irrigation is essential for the raising of forage, grain and fruit crops.

The waters of the northeast, emerging from deep canyons, cut into the mountain sides, are diverted into canals, watering the bench land at the foot of the canyons. Large reservoirs are rare.

The value of products raised on 630,000 acres of irrigated land with the help of irrigation works costing \$5,900,000 amounted to \$7,500,000 in the census year.

FORESTRY CONDITIONS OF VERMONT:

1. Area: 3,900 square miles, or 43% of the State, are under forest.

2. Physiography: The Green Mountains, running north and south through the heart of the State, rise to peaks over 4,000 feet high. Lake Champlain and the Connecticut River are the most important water ways.

3. Distribution: Originally, white pine, hemlock and spruce were imbedded in a forest of hardwoods (beech, maple, yellow birch and some little basswood, butternut, ashes, red, white and burr oak and chestnut oak on red sandstone). Spruce, with bal-

FOREST POLICY.

sam, prevails on the ridges. Great bodies of white pine were found on the Connecticut River and in the northwest.

4. Forest ownership: 330 firms own 372,000 acres. 80% of woodlands are attached to farms.

5. Use of timber: White pine is practically exhausted. Quantities of spruce and hemlock are still left. The lumber industry begins to decline slightly. The value of the output of the saw mills was in

1850	\$ 600,000
1860	900,000
1870	3,500,000
1880	3,200,000
1890	6,900,000
1900	6,100,000

The cut in 1900 consists of 376,000,000 feet b. m., comprising 261,000,000 feet b. m. spruce; 43,000,000 feet b. m. hemlock; 21,000,000 feet b. m. white pine; 51,000,000 feet b. m. hardwoods.

657 mills report \$6,304 as the average investment. Stumpage is worth \$2.09; logs at mill cost \$5.80.

The maple sugar industry produced, in 1880, 11,000,000 lbs. of sugar.

The leather industry has consumed, in 1900, 4,990 cords of hemlock bark, worth \$30,000; 163 bales of gambier, worth \$1,200; 100 barrels of extract, worth \$1,200. Eight plants produce \$186,000 worth of leather.

Paper and pulp industry: 27 plants produce, in 1900, \$3,400,000 worth of paper and pulp. There were consumed 31,500 cords of home-grown spruce, worth \$172,000; 25,500 cords of Canadian spruce, worth \$167,000; 2,262 cords of miscellaneous wood, worth \$11,000.

6. Forestry movement: A Forest Commission, appointed in 1882, produced a good report in 1884. No action was taken upon it.

7. Laws: The State pays a premium on forest destruction by exempting the wood lands of saw mill owners for five years from forest taxes. Malicious firing only is punishable.

8. Reservations: None.

9. Irrigation: None.

FOREST POLICY.

FORESTRY CONDITIONS OF VIRGINIA:

1. Area: 23,400 square miles, or 58% of State, are woodland.

2. Physiography:—

(a) Mountain section, a belt 60 miles wide along the West Virginia, Kentucky and Tennessee lines, covering two or three tiers of counties and forming 25% of State.

(b) Piedmont plateau, drained in the main by the James River, lying southeast of "a" and forming 50% of State.

(c) Coastal plains, a belt up to 100 miles wide, extending as far as tidewater in the streams. Swamps near the coast, notably the Dismal Swamp. Soil sandy. The plains cover 25% of the State.

3. Distribution: On Virginia soil the northern tree flora meets the southern. The long leaf and taeda pines do not extend further north than Virginia.

Mountain section: The hardwoods of the southern Appalachians (see under North Carolina) prevail here, with some hemlock and white pine. Spruce at high altitudes. The mountain forests were practically untouched in 1880. It is now claimed that certain species, notably chestnut oak, are exhausted.

Piedmont plateau: In the virgin woods, black oak was the prevailing timber; further, white oak, hickories and black gum. Now no virgin forest is left. Vast areas of fields, exhausted by tobacco growing, come up in Jersey pine (virginiana), rigid pine, echinata pine, sumac and sassafras; further, hardwood brush of chestnut, gum and oaks. Little taeda pine.

Coastal plains: The original growing stock, after Michaux, consisted of belts of taeda pine, alternating with belts of echinata. Now a second growth of taeda forms 75% of the growing stock from the seashore to the meridian of Richmond, whilst echinata appears scatteringly. Long leaf pine is commercially unimportant, reaching its northern limit in stunted specimens near Norfolk. The swamps near the coast show cypress, gums and, after Fernow, red cedar.

4. Forest ownership: 418 lumber firms control 402,000 acres of forest, stocked with 4,300 feet b. m. on an average.

5. Use of timber: Main source of lumber is 2d and 3d growth of loblolly pine, sold under the trade name "Virginia pine," which is said to reproduce exceedingly well. Trees 50

FOREST POLICY.

years old are said to yield three logs. Large quantities of loblolly firewood and kindling are shipped to New York. Sumac leaves are gathered for tanning purposes on such a scale that the railroads reported, in 1885, shipments amounting to 10,300 tons—a good indication of the enormous extent of abandoned fields.

Mill investments average \$3,934, the number of mills being 1,234. Logs on stump are worth \$1.79; at mill, \$8.35. The value of the lumber product was in

1850	\$ 1,000,000
1860	2,200,000
1870	2,100,000
1880	3,400,000
1890	5,600,000
1900	12,100,000

The figures prove a rapidly increasing production, although the virgin woods have gone for many a decade.

The output in 1900 consisted of:—

Hemlock	1,400,000 feet b. m.
Yellow pine	710,000,000 feet b. m.
Yellow poplar	86,000,000 feet b. m.
White oak	143,000,000 feet b. m.
Other hardwoods	13,000,000 feet b. m.

Total.....953,400,000 feet b. m.

The miscellaneous industries report a product worth \$436,000; the cooperage firms, \$587,000; the box concerns, \$900,000.

The leather industry is developed on a large scale. 65 tanneries produce \$4,717,000 worth of leather and consume 73,646 cords of oak bark, worth \$468,000; 420 tons of quebracho, worth \$5,400; 6 tons of sumac, worth \$233. Little extract is locally used, but large amounts are manufactured for exportation.

The paper and pulp industry works in seven plants and consumes 2,917 cords of spruce, worth \$6 per cord; 8,513 cords of poplar, worth \$4.50 per cord, and 3,200 cords of miscellaneous wood, worth \$2.30 per cord.

6. Forestry movement: Nill. The system of forestry actually practiced on abandoned fields may be classed as "intermittent forestry."

FOREST POLICY.

7. Laws: Stock law in many counties. The usual fire laws, existing since 1862, are unobserved.
 8. Reservations: None.
 9. Irrigation: None.
-

FORESTRY CONDITIONS OF WASHINGTON:

1. Area: 71% of the State is classed as forests (H. Gannett). Of this area, however, much is burned and cut over. Of the original timber, 55% stands intact, 22% is burned and 23% is cut over.

2. Physiography: The southeastern part of the State is practically destitute of timber, excepting the region south of the bend of the Snake River, owing to insufficient rainfall. The Coast Range extends northward into the Olympic Mountains where there is the heaviest rainfall in the United States. The valleys of the Chehalis and Cowlitz Rivers, separating the Coast Range from the Cascade Range, are not densely wooded. Mt. Tacoma (Rainier) has highest elevation in the Cascade Range. Irregular mountain chains, sparsely timbered, running north and south are found in the northeastern part, mostly covered by Colville Indian Reservation.

3. Distribution: The Cascade and Coast Ranges bear the heaviest continuous forest belt in the United States.

The Coast Range is timbered down to seashore, a strip of dunes excepted. Predominating species are red fir (Douglas fir) and red cedar (*Thuja plicata*). Tideland spruce (Sitka) is said to run only 50 miles inland. Black hemlock forms an almost tropical undergrowth and is the smallest among the giants. Sargent denies fires ever having swept the virgin forest. Pinchot finds cinders below the vegetable litter all over the Olympics.

On the Cascade Range, we must strictly distinguish between west and east slope, owing to great difference in rainfall.

The west slope has at its highest altitudes alpine fir, hemlock, alpine larch (*Lyalli*) and white bark pine. Descending from the crest we meet Engelmann's spruce, white pine (*monticola*), lowland fir, amiable fir and noble fir.

Lower down, Alaska cedar (*Ch. nootkatensis*), western hemlock and western red cedar are met with, and Douglas fir in-

FOREST POLICY.

creases in proportion until it forms the prevailing species at lower altitudes. Near the Gulf, tideland spruce occurs.

On the east slope, below the timber line fringed by white bark pine and alpine hemlock, we strike Engelmann's spruce and Douglas fir. Lower down, we enter upon forests of yellow pine (*Pinus ponderosa*) and groves of lodge pole pine.

The Blue Mountains in the southeast contain yellow pine, Douglas spruce, Engelmann's spruce and lodge pole pine.

The irregular mountain chains in the northeast are said to show timber in the valleys only (?). Yellow pine predominates; in addition, lodge pole pine, Douglas fir and tamarack larch are found; further, Engelmann's spruce, lowland fir, western white pine and red cedar. A tree alder (*Alnus Oregona*) is remarkable for its size.

The Columbia River and its tributaries are fringed by gigantic broad-leaved species, notably cottonwoods, maples, ashes and willows.

4. Forest ownership: The United States reservations aggregate 7.0 million acres; 0.4 million acres are owned by farmers; lumbermen control the Coast Range and own one-tenth of entire stumpage.

5. Use of timber: Lumber industry is modern. Investment in a saw mill averages \$23,500. 24 million staves of cottonwood were manufactured in 1898. In the coniferous forests a yield of 200,000 feet b. m. per acre is not exceptional. 20,000 square miles in one plot are said to average 25,000 feet b. m. per acre. Mining is undeveloped and requires little timber. Clearing of heavy timbered land costs \$100 to \$200 per acre. Timber claims in 1898 were sold at \$10 per acre. The stumpage price after 12th census is 80 cents per 1,000 board feet; logs at the mill are worth \$5.14 making logging expenses \$4.34.

Washington employs three-fourths of all steam power used in logging in the United States (railroads and donkey engines). The waste in logging is from two-thirds to three-quarters of entire tree. Fires destroy enormous amounts of timber and invariably the hemlock left after lumbering.

During the census year (1900) Washington produced 2.3 billion feet b. m., worth \$30,000,000, holding 5th rank among States. There is no paper, pulp and leather industry. (The latter industry consumes only 400 cords of bark, though red fir bark and hemlock bark are rich in tannin.)

FOREST POLICY.

Tideland spruce is used mainly for car linings and interior finish; cedar mainly for shingles; hemlock is only beginning to be used at all. Douglas fir is used for all building purposes, trestle bridges and ship building.

The growing stock of timber in Washington consists of

Red fir	90,000,000,000 feet b. m.
Spruce	8,000,000,000 feet b. m.
Cedar	23,000,000,000 feet b. m.
Hemlock	42,000,000,000 feet b. m.
Yellow pine	13,000,000,000 feet b. m.
Miscellaneous	20,000,000,000 feet b. m.

Total.....196,000,000,000 feet b. m.

As we are cutting 2.3 billion feet b. m., we are cutting 1.17% of the growing stock per annum.

6. Forestry movement: State association in 1898, composed of lumbermen, securing more stringent fire laws.

7. Laws: Fire laws of 1877 comprehensive and stringent, but unenforced. Law of 1903 makes the land commissioner ex officio "forest firewarden," the county commissioners "deputy firewardens," road supervisors and State land cruisers "forest patrolmen." The firewardens may appoint the cruisers and foremen of lumber firms as "patrolmen at large." Fire laws to be posted; firing of slashings forbidden during dry months. Carelessness in camp fires punishable only if it results in damage to private interests.

8. Reservations: Total area reserved 7,036,000 acres, equal to 15.5% of State. In 1898 there were employed one superintendent, three supervisors and twenty-three rangers.

(a) Olympic forest reserve, 1,466,880 acres. Douglas fir prevails, with hemlock and cedar. Very deep humus. No lumbering, owing to difficulty of transportation. Little chance for farming, grazing, mining.

(b) Washington forest reserve, 3,426,400 acres. Two-thirds of the growing stock (20 billion feet) is formed by hemlock. Little grazing. Timber still inaccessible. Mines beginning to be developed. Reserve is said to include 150,000 acres of agricultural land.

(c) Mt. Rainier forest reserve, 2,027,520 acres, embracing

FOREST POLICY.

the Mt. Rainier National Park of 207,360 acres, with its unrivalled combination of ice and woodland scenery.

(d) Part (about 104,000 acres) of the Priest River forest reserve.

(e) Blue Mountain forest reserve.

9. Irrigation: Irrigation is profitable on the east side of the Cascades.

Small farms, along the narrow strips of land left between the river and the foot of the cliffs framing the canyons, are found along the Columbia and Snake Rivers. Here, the irrigation of fruit orchards is particularly remunerative, the water being lifted from the river by bucket wheels.

In the Great Bend country it will be necessary to construct reservoirs, storing away the supply furnished by intermittent and uncertain streams.

Washington hops are famous. The seemingly arid soil of the rolling uplands in the east has been found to produce splendid wheat, without irrigation, owing to its remarkable hygroscopic qualities.

The irrigated farms, covering 135,000 acres, produced anno 1899, from irrigation works costing \$1,700,000, a crop valued at \$2,400,000.

FORESTRY CONDITIONS OF WEST VIRGINIA:

1. Area: 18,400 square miles, or 73% of State, are stocked mostly with merchantable timber.

2. Physiography: West Virginia has the poorest shipping facilities of any State in the east. The main rivers (the Big Sandy, Guyandotte, Kanawha and Cheat)—which are not navigable—rapidly traverse a plateau sloping from the crest of the Alleghanies westward to the Ohio River. The Potomac alone, rising in the extreme northeast, finds its way to the east along the Maryland line.

3. Distribution: The hardwoods prevail by far. *Echinata* pine is found scatteringly on a narrow belt lying half way between the mountains and the Ohio River. *Pinus virginiana*, *rigida* and *pungens* occur on the east slopes and on the poorer soil of the plateau. A few *Pinus resinosa*, found in the high mountains, are the southernmost representatives of that species.

FOREST POLICY.

In the western and northern section the virgin hardwoods have been removed.

Along the upper course of the rivers the primeval forest is frequently intact. Prime walnut, cherry, yellow poplar and white oak occur here in large quantities. At the headwaters of the Green Briar and Cheat Rivers a large and commercially important belt of white pine is found, and, adjoining it to the north, a long belt of splendid spruce. (Spruce stumpage said to average 25,000 feet b. m. to the acre.)

4. Forest ownership: 221 lumber firms own 506,000 acres, of 5,200 feet b. m. average stumpage.

5. Use of timber: Logging and log transportation in the primeval woods of the mountains is extremely difficult, owing to the character of the rivers, the lack of snow and the high expense of railroading in a broken country. 929 mills represent an average investment of \$5,700. Logs on stump are worth \$2.36; at mill, \$6.59. The output of the mills was valued in

1870	\$ 1,500,000
1880	2,400,000
1890	5,500,000
1900	10,600,000

The cut in 1900 consisted of:—

Hemlock	91,000,000 feet b. m.
Spruce	94,000,000 feet b. m.
Yellow pine	18,000,000 feet b. m.
White pine	5,000,000 feet b. m.
Walnut	150,000 feet b. m.
Poplar	193,000,000 feet b. m.
White oak	353,000,000 feet b. m.
Ash, birch, chestnut	25,000,000 feet b. m.

The cooperage materials produced were worth \$400,000, and the furniture, wagon, etc., stock, \$580,000.

Leather industry: 46 tanneries produce annually \$3,200,000 worth of leather and consume 8,445 cords of hemlock bark, worth \$50,000; 69,286 cords of chestnut oak bark, worth \$305,000; in addition to 394 barrels of bark extract.

Paper and pulp industry: There are 6 mills yielding an output worth \$527,000. They consume 5,729 cords of home-grown

FOREST POLICY.

spruce, for pulp, valued at \$30,500; 11,286 cords of home-grown spruce, for sulphite and soda fibre, valued at only \$39,100; 1,519 cords of miscellaneous wood, valued at \$4,200.

6. Forestry movement: None. Arbor Day failed to be legalized. The West Virginia Agricultural Experiment Station at Morgantown issues valuable bulletins on insect plagues in the forest, written by A. D. Hopkins, the forest insectologist of the United States.

7. Laws: Laws under which unlawful firing is punished are unenforced, although existing on the statute book.

8. Reservations: None.

9. Irrigation: None.

FORESTRY CONDITIONS OF WISCONSIN:

1. Area under forest, 31,750 square miles, or 58% of the State.

2. Physiography: Undulating land. Splendid shipping facilities on the shore line of Lakes Superior and Michigan, and on the Mississippi River, helped by a multitude of lakes and floatable rivers. The Wisconsin, Menomonee and St. Croix Rivers are famous for the output of white pine.

3. Distribution: The southwestern section is prairie, intruded by the black oaks and paper birch.

The southeastern section shows the hardwoods (maple, basswood, elm, white and red oak) prevailing, the overtowering white pines having been removed.

The northeast is characterized by hemlock and birch, whilst white and red oak are scarce.

The north shows pineries stocked with white, jack and Norway pines. A large number of swamps produce spruce, balsam, white cedar, tamarack or nothing.

4. Forest ownership: The northern half of the State—the coniferous region proper—is owned in the following proportion:—

United States	5%
State and counties	2%
Railroads	5%
Resident settlers	24%
Lumbermen	50%
Outsiders	14%

FOREST POLICY.

The last census credits the lumbermen with a total forest property of 1,920,000 acres.

5. Use of timber: The growing stock of white pine was estimated in 1880 (by Sargent) at 41 billion feet b. m., and in 1897 (by Roth) at 17 billion feet. Both estimates were found too small. 4.7 billion feet white pine are still owned by lumbermen alone, whilst the annual cut has been from 2 to 3 billion feet since the estimates were made.

The cut of the census year was:—

Hemlock	402,000,000 feet b. m.
Norway pine	94,000,000 feet b. m.
White pine	2,479,000,000 feet b. m.
Other conifers	66,000,000 feet b. m.
White oak	127,000,000 feet b. m.
Other hardwoods	392,000,000 feet b. m.

The cutting of pines is very close, logs of 4 inches diameter at small end being used. Log drives are said to average frequently only 100 feet b. m. per log. The average investment, in 1,033 saw mills, is \$35,959, a figure exceeded only by the Minnesota mills.

Value of products of lumber industry was:—

In 1860	\$ 4,400,000
In 1870	15,100,000
In 1880	17,900,000
In 1890	61,000,000
In 1900	57,600,000

which latter figure places Wisconsin in the lead of all States.

The leather industry is important, the value of its products being \$20,000,000 per annum. 35 plants use, in the census year, 177.628 cords of hemlock bark, worth \$1,070,000; 770 cords of oak bark, worth \$8,000; 56 barrels of hemlock bark extract and 1,692 barrels of quebracho extract; 41,726 bales of gambier and 247 tons of sumac.

The paper and pulp industry produces in 47 mills products worth \$10,895,000 and consumes 66,300 cords of native spruce for pulp, worth \$398,000; 58,659 cords of native spruce for fibre, worth \$350,000; 24,754 cords of Canadian spruce, worth \$164,000; 1,400 cords of native poplar, worth \$12,000, and 60,000 cords of miscellaneous wood (the majority of which is hemlock), worth \$210,000.

FOREST POLICY.

6. Forestry movement: Forestry commission reports to legislature in 1898. Ernest Bruncken, secretary. (See also XXXI.)

7. Laws: Forest fire warden law of 1898, creating certain county officials ex officio fire wardens.

A law of June 2, 1903, provides for an unpaid "board of forest commissioners" or a "department of forestry." Paid superintendent of State forests acts as secretary of board for records, publications, maps, etc.; acts as "trespass agent" on State forest reserve; acts as chief fire warden of the State; appoints fire wardens in certain counties. Fire wardens and helpers are paid by the towns; but the annual fire expense per township must not exceed \$100. Fire notices. Fire reports. Duty of district attorneys to prosecute incendiarism, upon complaint of fire wardens.

All State lands are withdrawn from sale (excepting swamps, farm wood lots, agricultural land and small tracts) and constitute a "State forest reserve." Here possibility of forestry is to be studied by the superintendent; dead and down timber to be disposed of; experiment stations to be formed.

The State may accept unencumbered forest land donated by private persons for reserve purposes. Insufficient appropriation.

Any 40 acres planted with 1,000 pine trees obtain a tax release for fifteen years.

8. Reservations: No federal forest reserves.

The State forest reserves created in 1903 consist of holdings so scattering that protection from fire will be difficult.

9. Irrigation: None.

FORESTRY CONDITIONS OF WYOMING:

1. Area: 13% of area of State or 12,500 square miles are said to be wooded. (Underestimate??).

2. Physiography: A broad, high, bare plateau, stretching from the northeast to the southwest into the Uintah Range, occupies one-half the State. Deserts in the southwest (Colorado and Red Deserts). The Yellowstone Rockies occupy the northwestern quarter; the Big Horn Mountains, drained by the Yellowstone River, the central north; the Uintah Mountains come from Utah; the Laramie and Medicine Bow Mountains from Colorado; the Black Hills from South Dakota. The northern moun-

FOREST POLICY.

tains are drained by the Yellowstone and Missouri Rivers; the western mountains by the Snake and Colorado Rivers; the southern mountains (Laramie and Medicine Bow Mountains) by the North Platte River.

3. Distribution: Wyoming is the lodgepole pine State. Yellow pine, limber white pine and Engelmann's spruce occupy the moister sections. In the Black Hills, yellow pine prevails, forming valuable forests. Fire has run over all forests. In the Yellowstone Park, lodgepole pine is the prevailing species, of a quality unfit for good timber. Douglas fir and Engelmann's spruce occur at elevations from 7,000 to 10,000 feet.

4. Forest ownership: The United States reserves and parks (aggregating about 10,000,000 acres) cover over two-thirds of the area of woodlands. Only 510 acres of forest are attached to farms, and only 57,000 acres owned by lumbermen.

5. Use: Yellow pine is used for ties and mining timber; lodgepole pine for fencing, fuel, telegraph poles and ties. The other coniferous species are scarcely ever used. From the Big Horn Range and the Laramie Mountains the mining timber is conveyed to the railroads by chutes.

6. Forestry movement: None. Inhabitants are rather opposed to reserves for fear of injury to the growing mining interests. The people outside Wyoming, on the other hand, realize the importance of reserving forested mountain tracts which supply water to the three greatest rivers of the country.

7. Laws: Usual fire laws, but not enforced.

8. Reservations: The Yellowstone National Park contains over 3,000 square miles. It is poorly timbered. Heavy fires prevail in spite of military supervision.

The Yellowstone Park forest reserve contains 1,809,280 acres and lies east of the park.

The Teton forest reserve, of 4,127,360 acres, lies south of the Yellowstone National Park.

The Big Horn forest reserve occupies 1,216,960 acres.

Of the Black Hills forest reserve, the majority of which lies in South Dakota, 429,000 acres are in Wyoming.

The Medicine Bow forest reserve has 420,584 acres.

Features of these reserves are high mountain parks. These parks are very well adapted to stock pasture, notably to sheep grazing. They are, probably, the beds of former lakes.

FOREST POLICY.

9. Irrigation: The climate, owing to high altitude, and the soil of Wyoming do not predestine the State favorably for agricultural pursuits. Grazing and mining must remain its staple industries.

In the north, near Sheridan, at an altitude of only 3,700 feet, irrigation has been most successful.

The irrigated farms—mostly hay farms—are of large size.

One of the most interesting irrigation systems tunnels the Laramie Mountains, so as to deliver the waters of the Laramie River to a number of canals on the east side of the mountains.

The irrigation works constructed previous to 1899 cost \$4,000,000 and supply 610,000 acres of farm land, which produce \$2,900,000 worth of crops.

UNIVERSITY OF CALIFORNIA LIBRARY
Los Angeles

This book is DUE on the last date stamped below.

SD .Schenck-
371 Forest mensura-
S32f tion.

UC SOUTHERN REGIONAL LIBRARY FACILITY

A 001 107 867 2

SD
371
S32f